Autoconf

Creating Automatic Configuration Scripts
for version 2.60, 23 June 2006

David MacKenzie
Ben Elliston
Akim Demaille

This manual is for GNU Autoconf (version 2.60, 23 June 2006), a package for creating scripts to configure source code packages using templates and an M4 macro package.

Copyright © 1992, 1993, 1994, 1995, 1996, 1998, 1999, 2000, 2001, 2002, 2003, 2004, 2005, 2006 Free Software Foundation, Inc.

> Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, with the Front-Cover texts being "A GNU Manual," and with the Back-Cover Texts as in (a) below. A copy of the license is included in the section entitled "GNU Free Documentation License."
>
> (a) The FSF's Back-Cover Text is: "You have freedom to copy and modify this GNU Manual, like GNU software. Copies published by the Free Software Foundation raise funds for GNU development."

Table of Contents

1 Introduction 1

2 The GNU Build System 3

2.1 Automake 3
2.2 Gnulib 3
2.3 Libtool 4
2.4 Pointers 4

3 Making `configure` Scripts 7

3.1 Writing '`configure.ac`' 8
3.1.1 A Shell Script Compiler 8
3.1.2 The Autoconf Language 9
3.1.3 Standard '`configure.ac`' Layout 10
3.2 Using `autoscan` to Create '`configure.ac`' 11
3.3 Using `ifnames` to List Conditionals 12
3.4 Using `autoconf` to Create `configure` 12
3.5 Using `autoreconf` to Update `configure` Scripts 15

4 Initialization and Output Files 17

4.1 Initializing `configure` 17
4.2 Notices in `configure` 18
4.3 Finding `configure` Input 18
4.4 Outputting Files 19
4.5 Performing Configuration Actions 20
4.6 Creating Configuration Files 22
4.7 Substitutions in Makefiles 22
4.7.1 Preset Output Variables 23
4.7.2 Installation Directory Variables 25
4.7.3 Changed Directory Variables 28
4.7.4 Build Directories 29
4.7.5 Automatic Remaking 30
4.8 Configuration Header Files 31
4.8.1 Configuration Header Templates 32
4.8.2 Using `autoheader` to Create '`config.h.in`' 33
4.8.3 Autoheader Macros 34
4.9 Running Arbitrary Configuration Commands 35
4.10 Creating Configuration Links 36
4.11 Configuring Other Packages in Subdirectories 36
4.12 Default Prefix 37

5 Existing Tests ... 39
5.1 Common Behavior ... 39
5.1.1 Standard Symbols ... 39
5.1.2 Default Includes ... 39
5.2 Alternative Programs ... 41
5.2.1 Particular Program Checks ... 41
5.2.2 Generic Program and File Checks ... 43
5.3 Files ... 45
5.4 Library Files ... 46
5.5 Library Functions ... 47
5.5.1 Portability of C Functions ... 47
5.5.2 Particular Function Checks ... 50
5.5.3 Generic Function Checks ... 56
5.6 Header Files ... 57
5.6.1 Portability of Headers ... 58
5.6.2 Particular Header Checks ... 59
5.6.3 Generic Header Checks ... 64
5.7 Declarations ... 65
5.7.1 Particular Declaration Checks ... 65
5.7.2 Generic Declaration Checks ... 65
5.8 Structures ... 66
5.8.1 Particular Structure Checks ... 66
5.8.2 Generic Structure Checks ... 67
5.9 Types ... 68
5.9.1 Particular Type Checks ... 68
5.9.2 Generic Type Checks ... 70
5.10 Compilers and Preprocessors ... 70
5.10.1 Specific Compiler Characteristics ... 71
5.10.2 Generic Compiler Characteristics ... 71
5.10.3 C Compiler Characteristics ... 72
5.10.4 C++ Compiler Characteristics ... 76
5.10.5 Objective C Compiler Characteristics ... 77
5.10.6 Erlang Compiler and Interpreter Characteristics ... 77
5.10.7 Fortran Compiler Characteristics ... 78
5.11 System Services ... 82
5.12 Posix Variants ... 84
5.13 Erlang Libraries ... 84

6 Writing Tests ... 87
6.1 Language Choice ... 87
6.2 Writing Test Programs ... 88
6.2.1 Guidelines for Test Programs ... 89
6.2.2 Test Functions ... 89
6.2.3 Generating Sources ... 90
6.3 Running the Preprocessor ... 92
6.4 Running the Compiler ... 93
6.5 Running the Linker ... 94
6.6 Checking Runtime Behavior ... 94

6.7 Systemology 96
6.8 Multiple Cases 96

7 Results of Tests 99

7.1 Defining C Preprocessor Symbols 99
7.2 Setting Output Variables 100
7.3 Special Characters in Output Variables 102
7.4 Caching Results 102
7.4.1 Cache Variable Names 104
7.4.2 Cache Files 104
7.4.3 Cache Checkpointing 105
7.5 Printing Messages 105

8 Programming in M4 107

8.1 M4 Quotation 107
8.1.1 Active Characters 107
8.1.2 One Macro Call 108
8.1.3 Quotation and Nested Macros 109
8.1.4 `changequote` is Evil 110
8.1.5 Quadrigraphs 111
8.1.6 Quotation Rule Of Thumb 112
8.2 Using `autom4te` 113
8.2.1 Invoking `autom4te` 113
8.2.2 Customizing `autom4te` 117
8.3 Programming in M4sugar 118
8.3.1 Redefined M4 Macros 118
8.3.2 Looping constructs 119
8.3.3 Evaluation Macros 119
8.3.4 Text processing Macros 120
8.3.5 Forbidden Patterns 120
8.4 Programming in M4sh 121
8.5 File Descriptor Macros 122

9 Writing Autoconf Macros 125

9.1 Macro Definitions 125
9.2 Macro Names 125
9.3 Reporting Messages 126
9.4 Dependencies Between Macros 127
9.4.1 Prerequisite Macros 127
9.4.2 Suggested Ordering 128
9.4.3 One-Shot Macros 129
9.5 Obsoleting Macros 129
9.6 Coding Style 130

10 Portable Shell Programming 133
10.1 Shellology 133
10.2 Here-Documents 135
10.3 File Descriptors 136
10.4 File System Conventions 138
10.5 Shell Substitutions 140
10.6 Assignments 144
10.7 Parentheses in Shell Scripts 144
10.8 Slashes in Shell Scripts 145
10.9 Special Shell Variables 145
10.10 Limitations of Shell Builtins 150
10.11 Limitations of Usual Tools 158

11 Portable Make Programming 171
11.1 `$<` in Ordinary Make Rules 171
11.2 Failure in Make Rules 171
11.3 Special Characters in Make Macro Names 171
11.4 Backslash-Newline-Newline in Make Macro Values 172
11.5 Backslash-Newline in Make Comments 172
11.6 Long Lines in Makefiles 172
11.7 `make macro=value` and Submakes 172
11.8 The Make Macro MAKEFLAGS 173
11.9 The Make Macro `SHELL` 174
11.10 Comments in Make Rules 174
11.11 The '`obj/`' Subdirectory and Make 175
11.12 Exit Status of `make -k` 175
11.13 `VPATH` and Make 175
11.13.1 `VPATH` and Double-colon Rules 176
11.13.2 `$<` Not Supported in Explicit Rules 176
11.13.3 Automatic Rule Rewriting 176
11.13.4 OSF/Tru64 `make` Creates Prerequisite Directories Magically 179
11.13.5 Make Target Lookup 179
11.14 Single Suffix Rules and Separated Dependencies 182
11.15 Timestamp Resolution and Make 182

12 Portable C and C++ Programming 185
12.1 Varieties of Unportability 185
12.2 Integer Overflow 186
12.3 Properties of Null Pointers 186
12.4 Buffer Overruns and Subscript Errors 186
12.5 Floating Point Portability 187
12.6 Exiting Portably 187

13 Manual Configuration 189

13.1 Specifying the System Type 189
13.2 Getting the Canonical System Type 190
13.3 Using the System Type 191

14 Site Configuration 193

14.1 Controlling Help Output 193
14.2 Working With External Software 193
14.3 Choosing Package Options 196
14.4 Making Your Help Strings Look Pretty 197
14.5 Configuring Site Details 197
14.6 Transforming Program Names When Installing 198
14.6.1 Transformation Options 198
14.6.2 Transformation Examples 198
14.6.3 Transformation Rules 199
14.7 Setting Site Defaults 199

15 Running `configure` Scripts 201

15.1 Basic Installation 201
15.2 Compilers and Options 202
15.3 Compiling For Multiple Architectures 202
15.4 Installation Names 202
15.5 Optional Features 202
15.6 Specifying the System Type 203
15.7 Sharing Defaults 203
15.8 Defining Variables 203
15.9 `configure` Invocation 203

16 Recreating a Configuration 205

17 Obsolete Constructs 207

17.1 Obsolete '`config.status`' Invocation 207
17.2 '`acconfig.h`' 208
17.3 Using `autoupdate` to Modernize '`configure.ac`' 208
17.4 Obsolete Macros 209
17.5 Upgrading From Version 1 220
17.5.1 Changed File Names 220
17.5.2 Changed Makefiles 220
17.5.3 Changed Macros 220
17.5.4 Changed Results 221
17.5.5 Changed Macro Writing 222
17.6 Upgrading From Version 2.13 222
17.6.1 Changed Quotation 222
17.6.2 New Macros 223
17.6.3 Hosts and Cross-Compilation 224
17.6.4 `AC_LIBOBJ` vs. `LIBOBJS` 226
17.6.5 `AC_FOO_IFELSE` vs. `AC_TRY_FOO` 226

18 Generating Test Suites with Autotest 229
18.1 Using an Autotest Test Suite 229
18.1.1 `testsuite` Scripts 229
18.1.2 Autotest Logs 231
18.2 Writing '`testsuite.at`' 231
18.3 Running `testsuite` Scripts 233
18.4 Making `testsuite` Scripts 234

19 Frequent Autoconf Questions, with answers 237
19.1 Distributing `configure` Scripts 237
19.2 Why Require GNU M4? 237
19.3 How Can I Bootstrap? 237
19.4 Why Not Imake? 238
19.5 How Do I `#define` Installation Directories? 239
19.6 What is '`autom4te.cache`'? 240
19.7 Header Present But Cannot Be Compiled 240

20 History of Autoconf 243
20.1 Genesis 243
20.2 Exodus 243
20.3 Leviticus 244
20.4 Numbers 244
20.5 Deuteronomy 245

Appendix A Copying This Manual 247
A.1 GNU Free Documentation License 247
A.1.1 ADDENDUM: How to use this License for your documents 253

Appendix B Indices 255
B.1 Environment Variable Index 255
B.2 Output Variable Index 255
B.3 Preprocessor Symbol Index 257
B.4 Autoconf Macro Index 259
B.5 M4 Macro Index 264
B.6 Autotest Macro Index 266
B.7 Program and Function Index 266
B.8 Concept Index 268

1 Introduction

> A physicist, an engineer, and a computer scientist were discussing the nature of God. "Surely a Physicist," said the physicist, "because early in the Creation, God made Light; and you know, Maxwell's equations, the dual nature of electromagnetic waves, the relativistic consequences. . ." "An Engineer!," said the engineer, "because before making Light, God split the Chaos into Land and Water; it takes a hell of an engineer to handle that big amount of mud, and orderly separation of solids from liquids. . ." The computer scientist shouted: "And the Chaos, where do you think it was coming from, hmm?"
>
> —Anonymous

Autoconf is a tool for producing shell scripts that automatically configure software source code packages to adapt to many kinds of Posix-like systems. The configuration scripts produced by Autoconf are independent of Autoconf when they are run, so their users do not need to have Autoconf.

The configuration scripts produced by Autoconf require no manual user intervention when run; they do not normally even need an argument specifying the system type. Instead, they individually test for the presence of each feature that the software package they are for might need. (Before each check, they print a one-line message stating what they are checking for, so the user doesn't get too bored while waiting for the script to finish.) As a result, they deal well with systems that are hybrids or customized from the more common Posix variants. There is no need to maintain files that list the features supported by each release of each variant of Posix.

For each software package that Autoconf is used with, it creates a configuration script from a template file that lists the system features that the package needs or can use. After the shell code to recognize and respond to a system feature has been written, Autoconf allows it to be shared by many software packages that can use (or need) that feature. If it later turns out that the shell code needs adjustment for some reason, it needs to be changed in only one place; all of the configuration scripts can be regenerated automatically to take advantage of the updated code.

The Metaconfig package is similar in purpose to Autoconf, but the scripts it produces require manual user intervention, which is quite inconvenient when configuring large source trees. Unlike Metaconfig scripts, Autoconf scripts can support cross-compiling, if some care is taken in writing them.

Autoconf does not solve all problems related to making portable software packages—for a more complete solution, it should be used in concert with other GNU build tools like Automake and Libtool. These other tools take on jobs like the creation of a portable, recursive makefile with all of the standard targets, linking of shared libraries, and so on. See Chapter 2 [The GNU Build System], page 3, for more information.

Autoconf imposes some restrictions on the names of macros used with `#if` in C programs (see Section B.3 [Preprocessor Symbol Index], page 257).

Autoconf requires GNU M4 in order to generate the scripts. It uses features that some versions of M4, including GNU M4 1.3, do not have. You should use version 1.4.4 or later of GNU M4.

See Section 17.5 [Autoconf 1], page 220, for information about upgrading from version 1. See Chapter 20 [History], page 243, for the story of Autoconf's development. See Chapter 19 [FAQ], page 237, for answers to some common questions about Autoconf.

See the Autoconf web page (`http://www.gnu.org/software/autoconf/`) for up-to-date information, details on the mailing lists, pointers to a list of known bugs, etc.

Mail suggestions to the Autoconf mailing list (`autoconf@gnu.org`). Past suggestions are archived (`http://lists.gnu.org/archive/html/autoconf/`).

Mail bug reports to the Autoconf Bugs mailing list (`bug-autoconf@gnu.org`). Past bug reports are archived (`http://lists.gnu.org/archive/html/bug-autoconf/`).

If possible, first check that your bug is not already solved in current development versions, and that it has not been reported yet. Be sure to include all the needed information and a short '`configure.ac`' that demonstrates the problem.

Autoconf's development tree is accessible via anonymous CVS; see the Autoconf Summary (`http://savannah.gnu.org/projects/autoconf/`) for details. Patches relative to the current CVS version can be sent for review to the Autoconf Patches mailing list (`autoconf-patches@gnu.org`). Past patches are archived (`http://lists.gnu.org/archive/html/autoconf-patches/`).

Because of its mission, the Autoconf package itself includes only a set of often-used macros that have already demonstrated their usefulness. Nevertheless, if you wish to share your macros, or find existing ones, see the Autoconf Macro Archive (`http://autoconf-archive.cryp.to/`), which is kindly run by Peter Simons (`simons@cryp.to`).

2 The GNU Build System

Autoconf solves an important problem—reliable discovery of system-specific build and run-time information—but this is only one piece of the puzzle for the development of portable software. To this end, the GNU project has developed a suite of integrated utilities to finish the job Autoconf started: the GNU build system, whose most important components are Autoconf, Automake, and Libtool. In this chapter, we introduce you to those tools, point you to sources of more information, and try to convince you to use the entire GNU build system for your software.

2.1 Automake

The ubiquity of `make` means that a makefile is almost the only viable way to distribute automatic build rules for software, but one quickly runs into its numerous limitations. Its lack of support for automatic dependency tracking, recursive builds in subdirectories, reliable timestamps (e.g., for network file systems), and so on, mean that developers must painfully (and often incorrectly) reinvent the wheel for each project. Portability is non-trivial, thanks to the quirks of `make` on many systems. On top of all this is the manual labor required to implement the many standard targets that users have come to expect (`make install`, `make distclean`, `make uninstall`, etc.). Since you are, of course, using Autoconf, you also have to insert repetitive code in your `Makefile.in` to recognize `@CC@`, `@CFLAGS@`, and other substitutions provided by `configure`. Into this mess steps *Automake*.

Automake allows you to specify your build needs in a `Makefile.am` file with a vastly simpler and more powerful syntax than that of a plain makefile, and then generates a portable `Makefile.in` for use with Autoconf. For example, the `Makefile.am` to build and install a simple "Hello world" program might look like:

```
bin_PROGRAMS = hello
hello_SOURCES = hello.c
```

The resulting `Makefile.in` (~400 lines) automatically supports all the standard targets, the substitutions provided by Autoconf, automatic dependency tracking, `VPATH` building, and so on. `make` builds the `hello` program, and `make install` installs it in '`/usr/local/bin`' (or whatever prefix was given to `configure`, if not '`/usr/local`').

The benefits of Automake increase for larger packages (especially ones with subdirectories), but even for small programs the added convenience and portability can be substantial. And that's not all...

2.2 Gnulib

GNU software has a well-deserved reputation for running on many different types of systems. While our primary goal is to write software for the GNU system, many users and developers have been introduced to us through the systems that they were already using.

Gnulib is a central location for common GNU code, intended to be shared among free software packages. Its components are typically shared at the source level, rather than being a library that gets built, installed, and linked against. The idea is to copy files from Gnulib into your own source tree. There is no distribution tarball; developers should just

grab source modules from the repository. The source files are available online, under various licenses, mostly GNU GPL or GNU LGPL.

Gnulib modules typically contain C source code along with Autoconf macros used to configure the source code. For example, the Gnulib `stdbool` module implements a '`stdbool.h`' header that nearly conforms to C99, even on old-fashioned hosts that lack '`stdbool.h`'. This module contains a source file for the replacement header, along with an Autoconf macro that arranges to use the replacement header on old-fashioned systems.

2.3 Libtool

Often, one wants to build not only programs, but libraries, so that other programs can benefit from the fruits of your labor. Ideally, one would like to produce *shared* (dynamically linked) libraries, which can be used by multiple programs without duplication on disk or in memory and can be updated independently of the linked programs. Producing shared libraries portably, however, is the stuff of nightmares—each system has its own incompatible tools, compiler flags, and magic incantations. Fortunately, GNU provides a solution: *Libtool*.

Libtool handles all the requirements of building shared libraries for you, and at this time seems to be the *only* way to do so with any portability. It also handles many other headaches, such as: the interaction of Make rules with the variable suffixes of shared libraries, linking reliably with shared libraries before they are installed by the superuser, and supplying a consistent versioning system (so that different versions of a library can be installed or upgraded without breaking binary compatibility). Although Libtool, like Autoconf, can be used without Automake, it is most simply utilized in conjunction with Automake—there, Libtool is used automatically whenever shared libraries are needed, and you need not know its syntax.

2.4 Pointers

Developers who are used to the simplicity of `make` for small projects on a single system might be daunted at the prospect of learning to use Automake and Autoconf. As your software is distributed to more and more users, however, you otherwise quickly find yourself putting lots of effort into reinventing the services that the GNU build tools provide, and making the same mistakes that they once made and overcame. (Besides, since you're already learning Autoconf, Automake is a piece of cake.)

There are a number of places that you can go to for more information on the GNU build tools.

– Web

  The home pages for Autoconf (`http://www.gnu.org/software/autoconf/`), Automake (`http://www.gnu.org/software/automake/`), Gnulib (`http://www.gnu.org/software/gnulib/`), and Libtool (`http://www.gnu.org/software/libtool/`).

– Automake Manual

  See section "Automake" in *GNU Automake*, for more information on Automake.

– Books

The book *GNU Autoconf, Automake and Libtool*[1] describes the complete GNU build environment. You can also find the entire book on-line (`http://sources.redhat.com/autobook/`).

[1] *GNU Autoconf, Automake and Libtool*, by G. V. Vaughan, B. Elliston, T. Tromey, and I. L. Taylor. SAMS (originally New Riders), 2000, ISBN 1578701902.

3 Making configure Scripts

The configuration scripts that Autoconf produces are by convention called `configure`. When run, `configure` creates several files, replacing configuration parameters in them with appropriate values. The files that `configure` creates are:

- one or more '`Makefile`' files, usually one in each subdirectory of the package (see Section 4.7 [Makefile Substitutions], page 22);
- optionally, a C header file, the name of which is configurable, containing `#define` directives (see Section 4.8 [Configuration Headers], page 31);
- a shell script called '`config.status`' that, when run, recreates the files listed above (see Chapter 16 [config.status Invocation], page 205);
- an optional shell script normally called '`config.cache`' (created when using '`configure --config-cache`') that saves the results of running many of the tests (see Section 7.4.2 [Cache Files], page 104);
- a file called '`config.log`' containing any messages produced by compilers, to help debugging if `configure` makes a mistake.

To create a `configure` script with Autoconf, you need to write an Autoconf input file '`configure.ac`' (or '`configure.in`') and run `autoconf` on it. If you write your own feature tests to supplement those that come with Autoconf, you might also write files called '`aclocal.m4`' and '`acsite.m4`'. If you use a C header file to contain `#define` directives, you might also run `autoheader`, and you can distribute the generated file '`config.h.in`' with the package.

Here is a diagram showing how the files that can be used in configuration are produced. Programs that are executed are suffixed by '`*`'. Optional files are enclosed in square brackets ('`[]`'). `autoconf` and `autoheader` also read the installed Autoconf macro files (by reading '`autoconf.m4`').

Files used in preparing a software package for distribution:



Files used in configuring a software package:



3.1 Writing 'configure.ac'

To produce a `configure` script for a software package, create a file called '`configure.ac`' that contains invocations of the Autoconf macros that test the system features your package needs or can use. Autoconf macros already exist to check for many features; see Chapter 5 [Existing Tests], page 39, for their descriptions. For most other features, you can use Autoconf template macros to produce custom checks; see Chapter 6 [Writing Tests], page 87, for information about them. For especially tricky or specialized features, '`configure.ac`' might need to contain some hand-crafted shell commands; see Chapter 10 [Portable Shell], page 133. The `autoscan` program can give you a good start in writing '`configure.ac`' (see Section 3.2 [autoscan Invocation], page 11, for more information).

Previous versions of Autoconf promoted the name '`configure.in`', which is somewhat ambiguous (the tool needed to process this file is not described by its extension), and introduces a slight confusion with '`config.h.in`' and so on (for which '`.in`' means "to be processed by `configure`"). Using '`configure.ac`' is now preferred.

3.1.1 A Shell Script Compiler

Just as for any other computer language, in order to properly program '`configure.ac`' in Autoconf you must understand *what* problem the language tries to address and *how* it does so.

The problem Autoconf addresses is that the world is a mess. After all, you are using Autoconf in order to have your package compile easily on all sorts of different systems, some of them being extremely hostile. Autoconf itself bears the price for these differences: `configure` must run on all those systems, and thus `configure` must limit itself to their lowest common denominator of features.

Naturally, you might then think of shell scripts; who needs `autoconf`? A set of properly written shell functions is enough to make it easy to write `configure` scripts by hand. Sigh! Unfortunately, shell functions do not belong to the least common denominator; therefore, where you would like to define a function and use it ten times, you would instead need to copy its body ten times.

So, what is really needed is some kind of compiler, `autoconf`, that takes an Autoconf program, '`configure.ac`', and transforms it into a portable shell script, `configure`.

How does `autoconf` perform this task?

There are two obvious possibilities: creating a brand new language or extending an existing one. The former option is attractive: all sorts of optimizations could easily be implemented in the compiler and many rigorous checks could be performed on the Autoconf program (e.g., rejecting any non-portable construct). Alternatively, you can extend an existing language, such as the `sh` (Bourne shell) language.

Autoconf does the latter: it is a layer on top of `sh`. It was therefore most convenient to implement `autoconf` as a macro expander: a program that repeatedly performs *macro expansions* on text input, replacing macro calls with macro bodies and producing a pure `sh` script in the end. Instead of implementing a dedicated Autoconf macro expander, it is natural to use an existing general-purpose macro language, such as M4, and implement the extensions as a set of M4 macros.

3.1.2 The Autoconf Language

The Autoconf language differs from many other computer languages because it treats actual code the same as plain text. Whereas in C, for instance, data and instructions have different syntactic status, in Autoconf their status is rigorously the same. Therefore, we need a means to distinguish literal strings from text to be expanded: quotation.

When calling macros that take arguments, there must not be any white space between the macro name and the open parenthesis. Arguments should be enclosed within the M4 quote characters '[' and ']', and be separated by commas. Any leading blanks or newlines in arguments are ignored, unless they are quoted. You should always quote an argument that might contain a macro name, comma, parenthesis, or a leading blank or newline. This rule applies recursively for every macro call, including macros called from other macros.

For instance:

```
AC_CHECK_HEADER([stdio.h],
                [AC_DEFINE([HAVE_STDIO_H], [1],
                   [Define to 1 if you have <stdio.h>.])],
                [AC_MSG_ERROR([Sorry, can't do anything for you])])
```

is quoted properly. You may safely simplify its quotation to:

```
AC_CHECK_HEADER([stdio.h],
                [AC_DEFINE([HAVE_STDIO_H], 1,
                   [Define to 1 if you have <stdio.h>.])],
                [AC_MSG_ERROR([Sorry, can't do anything for you])])
```

because '1' cannot contain a macro call. Here, the argument of AC_MSG_ERROR must be quoted; otherwise, its comma would be interpreted as an argument separator. Also, the second and third arguments of 'AC_CHECK_HEADER' must be quoted, since they contain macro calls. The three arguments 'HAVE_STDIO_H', 'stdio.h', and 'Define to 1 if you have <stdio.h>.' do not need quoting, but if you unwisely defined a macro with a name like 'Define' or 'stdio' then they would need quoting. Cautious Autoconf users would keep the quotes, but many Autoconf users find such precautions annoying, and would rewrite the example as follows:

```
AC_CHECK_HEADER(stdio.h,
                [AC_DEFINE(HAVE_STDIO_H, 1,
                   [Define to 1 if you have <stdio.h>.])],
                [AC_MSG_ERROR([Sorry, can't do anything for you])])
```

This is safe, so long as you adopt good naming conventions and do not define macros with names like 'HAVE_STDIO_H', 'stdio', or 'h'. Though it is also safe here to omit the quotes around 'Define to 1 if you have <stdio.h>.' this is not recommended, as message strings are more likely to inadvertently contain commas.

The following example is wrong and dangerous, as it is underquoted:

```
AC_CHECK_HEADER(stdio.h,
                AC_DEFINE(HAVE_STDIO_H, 1,
                   Define to 1 if you have <stdio.h>.),
                AC_MSG_ERROR([Sorry, can't do anything for you]))
```

In other cases, you may have to use text that also resembles a macro call. You must quote that text even when it is not passed as a macro argument:

```
echo "Hard rock was here!  --[AC_DC]"
```

which results in:

```
echo "Hard rock was here!  --AC_DC"
```

When you use the same text in a macro argument, you must therefore have an extra quotation level (since one is stripped away by the macro substitution). In general, then, it is a good idea to *use double quoting for all literal string arguments*:

```
AC_MSG_WARN([[AC_DC stinks  --Iron Maiden]])
```

You are now able to understand one of the constructs of Autoconf that has been continually misunderstood... The rule of thumb is that *whenever you expect macro expansion, expect quote expansion*; i.e., expect one level of quotes to be lost. For instance:

```
AC_COMPILE_IFELSE([char b[10];], [], [AC_MSG_ERROR([you lose])])
```

is incorrect: here, the first argument of `AC_COMPILE_IFELSE` is '`char b[10];`' and is expanded once, which results in '`char b10;`'. (There was an idiom common in Autoconf's past to address this issue via the M4 `changequote` primitive, but do not use it!) Let's take a closer look: the author meant the first argument to be understood as a literal, and therefore it must be quoted twice:

```
AC_COMPILE_IFELSE([[char b[10];]], [], [AC_MSG_ERROR([you lose])])
```

Voilà, you actually produce '`char b[10];`' this time!

On the other hand, descriptions (e.g., the last parameter of `AC_DEFINE` or `AS_HELP_STRING`) are not literals—they are subject to line breaking, for example—and should not be double quoted. Even if these descriptions are short and are not actually broken, double quoting them yields weird results.

Some macros take optional arguments, which this documentation represents as [*arg*] (not to be confused with the quote characters). You may just leave them empty, or use '`[]`' to make the emptiness of the argument explicit, or you may simply omit the trailing commas. The three lines below are equivalent:

```
AC_CHECK_HEADERS([stdio.h], [], [], [])
AC_CHECK_HEADERS([stdio.h],,,)
AC_CHECK_HEADERS([stdio.h])
```

It is best to put each macro call on its own line in '`configure.ac`'. Most of the macros don't add extra newlines; they rely on the newline after the macro call to terminate the commands. This approach makes the generated `configure` script a little easier to read by not inserting lots of blank lines. It is generally safe to set shell variables on the same line as a macro call, because the shell allows assignments without intervening newlines.

You can include comments in '`configure.ac`' files by starting them with the '`#`'. For example, it is helpful to begin '`configure.ac`' files with a line like this:

```
# Process this file with autoconf to produce a configure script.
```

3.1.3 Standard '`configure.ac`' Layout

The order in which '`configure.ac`' calls the Autoconf macros is not important, with a few exceptions. Every '`configure.ac`' must contain a call to `AC_INIT` before the checks, and a call to `AC_OUTPUT` at the end (see Section 4.4 [Output], page 19). Additionally, some macros rely on other macros having been called first, because they check previously set values of

some variables to decide what to do. These macros are noted in the individual descriptions (see Chapter 5 [Existing Tests], page 39), and they also warn you when configure is created if they are called out of order.

To encourage consistency, here is a suggested order for calling the Autoconf macros. Generally speaking, the things near the end of this list are those that could depend on things earlier in it. For example, library functions could be affected by types and libraries.

Autoconf requirements
AC_INIT(*package, version, bug-report-address*)
information on the package
checks for programs
checks for libraries
checks for header files
checks for types
checks for structures
checks for compiler characteristics
checks for library functions
checks for system services
AC_CONFIG_FILES([*file...*])
AC_OUTPUT

3.2 Using autoscan to Create 'configure.ac'

The autoscan program can help you create and/or maintain a 'configure.ac' file for a software package. autoscan examines source files in the directory tree rooted at a directory given as a command line argument, or the current directory if none is given. It searches the source files for common portability problems and creates a file 'configure.scan' which is a preliminary 'configure.ac' for that package, and checks a possibly existing 'configure.ac' for completeness.

When using autoscan to create a 'configure.ac', you should manually examine 'configure.scan' before renaming it to 'configure.ac'; it probably needs some adjustments. Occasionally, autoscan outputs a macro in the wrong order relative to another macro, so that autoconf produces a warning; you need to move such macros manually. Also, if you want the package to use a configuration header file, you must add a call to AC_CONFIG_HEADERS (see Section 4.8 [Configuration Headers], page 31). You might also have to change or add some #if directives to your program in order to make it work with Autoconf (see Section 3.3 [ifnames Invocation], page 12, for information about a program that can help with that job).

When using autoscan to maintain a 'configure.ac', simply consider adding its suggestions. The file 'autoscan.log' contains detailed information on why a macro is requested.

autoscan uses several data files (installed along with Autoconf) to determine which macros to output when it finds particular symbols in a package's source files. These data files all have the same format: each line consists of a symbol, one or more blanks, and the Autoconf macro to output if that symbol is encountered. Lines starting with '#' are comments.

autoscan accepts the following options:

‘`--help`’
‘`-h`’ Print a summary of the command line options and exit.

‘`--version`’
‘`-V`’ Print the version number of Autoconf and exit.

‘`--verbose`’
‘`-v`’ Print the names of the files it examines and the potentially interesting symbols it finds in them. This output can be voluminous.

‘`--include=`*dir*’
‘`-I` *dir*’ Append *dir* to the include path. Multiple invocations accumulate.

‘`--prepend-include=`*dir*’
‘`-B` *dir*’ Prepend *dir* to the include path. Multiple invocations accumulate.

3.3 Using `ifnames` to List Conditionals

`ifnames` can help you write ‘`configure.ac`’ for a software package. It prints the identifiers that the package already uses in C preprocessor conditionals. If a package has already been set up to have some portability, `ifnames` can thus help you figure out what its `configure` needs to check for. It may help fill in some gaps in a ‘`configure.ac`’ generated by `autoscan` (see Section 3.2 [autoscan Invocation], page 11).

`ifnames` scans all of the C source files named on the command line (or the standard input, if none are given) and writes to the standard output a sorted list of all the identifiers that appear in those files in `#if`, `#elif`, `#ifdef`, or `#ifndef` directives. It prints each identifier on a line, followed by a space-separated list of the files in which that identifier occurs.

`ifnames` accepts the following options:

‘`--help`’
‘`-h`’ Print a summary of the command line options and exit.

‘`--version`’
‘`-V`’ Print the version number of Autoconf and exit.

3.4 Using `autoconf` to Create `configure`

To create `configure` from ‘`configure.ac`’, run the `autoconf` program with no arguments. `autoconf` processes ‘`configure.ac`’ with the M4 macro processor, using the Autoconf macros. If you give `autoconf` an argument, it reads that file instead of ‘`configure.ac`’ and writes the configuration script to the standard output instead of to `configure`. If you give `autoconf` the argument ‘`-`’, it reads from the standard input instead of ‘`configure.ac`’ and writes the configuration script to the standard output.

The Autoconf macros are defined in several files. Some of the files are distributed with Autoconf; `autoconf` reads them first. Then it looks for the optional file ‘`acsite.m4`’ in the directory that contains the distributed Autoconf macro files, and for the optional file ‘`aclocal.m4`’ in the current directory. Those files can contain your site's or the package's own Autoconf macro definitions (see Chapter 9 [Writing Autoconf Macros], page 125, for more information). If a macro is defined in more than one of the files that `autoconf` reads, the last definition it reads overrides the earlier ones.

`autoconf` accepts the following options:

‘`--help`’
‘`-h`’ Print a summary of the command line options and exit.

‘`--version`’
‘`-V`’ Print the version number of Autoconf and exit.

‘`--verbose`’
‘`-v`’ Report processing steps.

‘`--debug`’
‘`-d`’ Don’t remove the temporary files.

‘`--force`’
‘`-f`’ Remake ‘`configure`’ even if newer than its input files.

‘`--include=`*`dir`*’
‘`-I` *`dir`*’ Append *dir* to the include path. Multiple invocations accumulate.

‘`--prepend-include=`*`dir`*’
‘`-B` *`dir`*’ Prepend *dir* to the include path. Multiple invocations accumulate.

‘`--output=`*`file`*’
‘`-o` *`file`*’ Save output (script or trace) to *file*. The file ‘`-`’ stands for the standard output.

‘`--warnings=`*`category`*’
‘`-W` *`category`*’
Report the warnings related to *category* (which can actually be a comma separated list). See Section 9.3 [Reporting Messages], page 126, macro `AC_DIAGNOSE`, for a comprehensive list of categories. Special values include:

‘`all`’ report all the warnings

‘`none`’ report none

‘`error`’ treats warnings as errors

‘`no-`*`category`*’
disable warnings falling into *category*

Warnings about ‘`syntax`’ are enabled by default, and the environment variable `WARNINGS`, a comma separated list of categories, is honored as well. Passing ‘`-W` *`category`*’ actually behaves as if you had passed ‘`--warnings=syntax,$WARNINGS,`*`category`*’. If you want to disable the defaults and `WARNINGS`, but (for example) enable the warnings about obsolete constructs, you would use ‘`-W none,obsolete`’.

Because `autoconf` uses `autom4te` behind the scenes, it displays a back trace for errors, but not for warnings; if you want them, just pass ‘`-W error`’. See Section 8.2.1 [autom4te Invocation], page 113, for some examples.

‘`--trace=`*`macro`*`[:`*`format`*`]`’
‘`-t` *`macro`*`[:`*`format`*`]`’
Do not create the `configure` script, but list the calls to *macro* according to the *format*. Multiple ‘`--trace`’ arguments can be used to list several macros.

Multiple '`--trace`' arguments for a single macro are not cumulative; instead, you should just make *format* as long as needed.

The *format* is a regular string, with newlines if desired, and several special escape codes. It defaults to '`$f:$l:$n:$%`'; see Section 8.2.1 [autom4te Invocation], page 113, for details on the *format*.

'`--initialization`'
'`-i`' By default, '`--trace`' does not trace the initialization of the Autoconf macros (typically the `AC_DEFUN` definitions). This results in a noticeable speedup, but can be disabled by this option.

It is often necessary to check the content of a '`configure.ac`' file, but parsing it yourself is extremely fragile and error-prone. It is suggested that you rely upon '`--trace`' to scan '`configure.ac`'. For instance, to find the list of variables that are substituted, use:

```
$ autoconf -t AC_SUBST
configure.ac:2:AC_SUBST:ECHO_C
configure.ac:2:AC_SUBST:ECHO_N
configure.ac:2:AC_SUBST:ECHO_T
More traces deleted
```

The example below highlights the difference between '`$@`', '`$*`', and '`$%`'.

```
$ cat configure.ac
AC_DEFINE(This, is, [an
[example]])
$ autoconf -t 'AC_DEFINE:@: $@
*: $*
%: $%'
@: [This],[is],[an
[example]]
*: This,is,an
[example]
%: This:is:an [example]
```

The *format* gives you a lot of freedom:

```
$ autoconf -t 'AC_SUBST:$$ac_subst{"$1"} = "$f:$l";'
$ac_subst{"ECHO_C"} = "configure.ac:2";
$ac_subst{"ECHO_N"} = "configure.ac:2";
$ac_subst{"ECHO_T"} = "configure.ac:2";
More traces deleted
```

A long *separator* can be used to improve the readability of complex structures, and to ease their parsing (for instance when no single character is suitable as a separator):

```
$ autoconf -t 'AM_MISSING_PROG:${|:::::|}*'
ACLOCAL|:::::|aclocal|:::::|$missing_dir
AUTOCONF|:::::|autoconf|:::::|$missing_dir
AUTOMAKE|:::::|automake|:::::|$missing_dir
More traces deleted
```

3.5 Using autoreconf to Update configure Scripts

Installing the various components of the GNU Build System can be tedious: running `autopoint` for Gettext, `automake` for '`Makefile.in`' etc. in each directory. It may be needed either because some tools such as `automake` have been updated on your system, or because some of the sources such as '`configure.ac`' have been updated, or finally, simply in order to install the GNU Build System in a fresh tree.

`autoreconf` runs `autoconf`, `autoheader`, `aclocal`, `automake`, `libtoolize`, and `autopoint` (when appropriate) repeatedly to update the GNU Build System in the specified directories and their subdirectories (see Section 4.11 [Subdirectories], page 36). By default, it only remakes those files that are older than their sources.

If you install a new version of some tool, you can make `autoreconf` remake *all* of the files by giving it the '`--force`' option.

See Section 4.7.5 [Automatic Remaking], page 30, for Make rules to automatically remake `configure` scripts when their source files change. That method handles the timestamps of configuration header templates properly, but does not pass '`--autoconf-dir=`*dir*' or '`--localdir=`*dir*'.

Gettext supplies the `autopoint` command to add translation infrastructure to a source package. If you use `autopoint`, your '`configure.ac`' should invoke both `AM_GNU_GETTEXT` and `AM_GNU_GETTEXT_VERSION(`*gettext-version*`)`. See section "Invoking the `autopoint` Program" in *GNU* `gettext` *utilities*, for further details.

`autoreconf` accepts the following options:

'`--help`'
'`-h`'
: Print a summary of the command line options and exit.

'`--version`'
'`-V`'
: Print the version number of Autoconf and exit.

'`--verbose`'
: Print the name of each directory `autoreconf` examines and the commands it runs. If given two or more times, pass '`--verbose`' to subordinate tools that support it.

'`--debug`'
'`-d`'
: Don't remove the temporary files.

'`--force`'
'`-f`'
: Remake even '`configure`' scripts and configuration headers that are newer than their input files ('`configure.ac`' and, if present, '`aclocal.m4`').

'`--install`'
'`-i`'
: Install the missing auxiliary files in the package. By default, files are copied; this can be changed with '`--symlink`'.

  If deemed appropriate, this option triggers calls to '`automake --add-missing`', '`libtoolize`', '`autopoint`', etc.

'`--no-recursive`'
: Do not rebuild files in subdirectories to configure (see Section 4.11 [Subdirectories], page 36, macro `AC_CONFIG_SUBDIRS`).

‘`--symlink`’
‘`-s`’ When used with ‘`--install`’, install symbolic links to the missing auxiliary files instead of copying them.

‘`--make`’
‘`-m`’ When the directories were configured, update the configuration by running ‘`./config.status --recheck && ./config.status`’, and then run ‘`make`’.

‘`--include=`*dir*’
‘`-I` *dir*’ Append *dir* to the include path. Multiple invocations accumulate. Passed on to `autoconf` and `autoheader` internally.

‘`--prepend-include=`*dir*’
‘`-B` *dir*’ Prepend *dir* to the include path. Multiple invocations accumulate. Passed on to `autoconf` and `autoheader` internally.

‘`--warnings=`*category*’
‘`-W` *category*’
Report the warnings related to *category* (which can actually be a comma separated list).

‘`cross`’ related to cross compilation issues.

‘`obsolete`’
report the uses of obsolete constructs.

‘`portability`’
portability issues

‘`syntax`’ dubious syntactic constructs.

‘`all`’ report all the warnings

‘`none`’ report none

‘`error`’ treats warnings as errors

‘`no-`*category*’
disable warnings falling into *category*

Warnings about ‘`syntax`’ are enabled by default, and the environment variable `WARNINGS`, a comma separated list of categories, is honored as well. Passing ‘`-W` *category*’ actually behaves as if you had passed ‘`--warnings=syntax,$WARNINGS,`*category*’. If you want to disable the defaults and `WARNINGS`, but (for example) enable the warnings about obsolete constructs, you would use ‘`-W none,obsolete`’.

If you want `autoreconf` to pass flags that are not listed here on to `aclocal`, set `ACLOCAL_AMFLAGS` in your ‘`Makefile.am`’.

4 Initialization and Output Files

Autoconf-generated `configure` scripts need some information about how to initialize, such as how to find the package's source files and about the output files to produce. The following sections describe the initialization and the creation of output files.

4.1 Initializing `configure`

Every `configure` script must call `AC_INIT` before doing anything else. The only other required macro is `AC_OUTPUT` (see Section 4.4 [Output], page 19).

`AC_INIT` (*package*, *version*, [*bug-report*], [*tarname*]) [Macro]

Process any command-line arguments and perform various initializations and verifications.

Set the name of the *package* and its *version*. These are typically used in '`--version`' support, including that of `configure`. The optional argument *bug-report* should be the email to which users should send bug reports. The package *tarname* differs from *package*: the latter designates the full package name (e.g., '`GNU Autoconf`'), while the former is meant for distribution tar ball names (e.g., '`autoconf`'). It defaults to *package* with '`GNU `' stripped, lower-cased, and all characters other than alphanumerics and underscores are changed to '`-`'.

It is preferable that the arguments of `AC_INIT` be static, i.e., there should not be any shell computation, but they can be computed by M4.

The following M4 macros (e.g., `AC_PACKAGE_NAME`), output variables (e.g., `PACKAGE_NAME`), and preprocessor symbols (e.g., `PACKAGE_NAME`) are defined by `AC_INIT`:

`AC_PACKAGE_NAME`, `PACKAGE_NAME`
: Exactly *package*.

`AC_PACKAGE_TARNAME`, `PACKAGE_TARNAME`
: Exactly *tarname*.

`AC_PACKAGE_VERSION`, `PACKAGE_VERSION`
: Exactly *version*.

`AC_PACKAGE_STRING`, `PACKAGE_STRING`
: Exactly '*package version*'.

`AC_PACKAGE_BUGREPORT`, `PACKAGE_BUGREPORT`
: Exactly *bug-report*.

If your `configure` script does its own option processing, it should inspect '`$@`' or '`$*`' immediately after calling `AC_INIT`, because other Autoconf macros liberally use the `set` command to process strings, and this has the side effect of updating '`$@`' and '`$*`'. However, we suggest that you use standard macros like `AC_ARG_ENABLE` instead of attempting to implement your own option processing. See Chapter 14 [Site Configuration], page 193.

4.2 Notices in `configure`

The following macros manage version numbers for `configure` scripts. Using them is optional.

`AC_PREREQ` (*version*) [Macro]

Ensure that a recent enough version of Autoconf is being used. If the version of Autoconf being used to create `configure` is earlier than *version*, print an error message to the standard error output and exit with failure (exit status is 63). For example:

```
AC_PREREQ([2.60])
```

This macro is the only macro that may be used before `AC_INIT`, but for consistency, you are invited not to do so.

`AC_COPYRIGHT` (*copyright-notice*) [Macro]

State that, in addition to the Free Software Foundation's copyright on the Autoconf macros, parts of your `configure` are covered by the *copyright-notice*.

The *copyright-notice* shows up in both the head of `configure` and in '`configure --version`'.

`AC_REVISION` (*revision-info*) [Macro]

Copy revision stamp *revision-info* into the `configure` script, with any dollar signs or double-quotes removed. This macro lets you put a revision stamp from '`configure.ac`' into `configure` without RCS or CVS changing it when you check in `configure`. That way, you can determine easily which revision of '`configure.ac`' a particular `configure` corresponds to.

For example, this line in '`configure.ac`':

```
AC_REVISION([$Revision: 1.30 $])
```

produces this in `configure`:

```
#!/bin/sh
# From configure.ac Revision: 1.30
```

4.3 Finding `configure` Input

`AC_CONFIG_SRCDIR` (*unique-file-in-source-dir*) [Macro]

unique-file-in-source-dir is some file that is in the package's source directory; `configure` checks for this file's existence to make sure that the directory that it is told contains the source code in fact does. Occasionally people accidentally specify the wrong directory with '`--srcdir`'; this is a safety check. See Section 15.9 [configure Invocation], page 203, for more information.

Packages that do manual configuration or use the `install` program might need to tell `configure` where to find some other shell scripts by calling `AC_CONFIG_AUX_DIR`, though the default places it looks are correct for most cases.

`AC_CONFIG_AUX_DIR` (*dir*) [Macro]

Use the auxiliary build tools (e.g., '`install-sh`', '`config.sub`', '`config.guess`', Cygnus `configure`, Automake and Libtool scripts, etc.) that are in directory *dir*. These are auxiliary files used in configuration. *dir* can be either absolute or relative

to '*srcdir*'. The default is '*srcdir*' or '*srcdir*`/..`' or '*srcdir*`/../..`', whichever is the first that contains '`install-sh`'. The other files are not checked for, so that using `AC_PROG_INSTALL` does not automatically require distributing the other auxiliary files. It checks for '`install.sh`' also, but that name is obsolete because some `make` have a rule that creates '`install`' from it if there is no makefile.

The auxiliary directory is commonly named '`build-aux`'. If you need portability to DOS variants, do not name the auxiliary directory '`aux`'. See Section 10.4 [File System Conventions], page 138.

`AC_REQUIRE_AUX_FILE` (*file*) [Macro]

Declares that *file* is expected in the directory defined above. In Autoconf proper, this macro does nothing: its sole purpose is to be traced by third-party tools to produce a list of expected auxiliary files. For instance it is called by macros like `AC_PROG_INSTALL` (see Section 5.2.1 [Particular Programs], page 41) or `AC_CANONICAL_BUILD` (see Section 13.2 [Canonicalizing], page 190) to register the auxiliary files they need.

Similarly, packages that use `aclocal` should declare where local macros can be found using `AC_CONFIG_MACRO_DIR`.

`AC_CONFIG_MACRO_DIR` (*dir*) [Macro]

Future versions of `autopoint`, `libtoolize`, `aclocal` and `autoreconf` will use directory *dir* as the location of additional local Autoconf macros. Be sure to call this macro directly from '`configure.ac`' so that tools that install macros for `aclocal` can find the declaration before '`--trace`' can be called safely.

4.4 Outputting Files

Every Autoconf script, e.g., '`configure.ac`', should finish by calling `AC_OUTPUT`. That is the macro that generates and runs '`config.status`', which in turn creates the makefiles and any other files resulting from configuration. This is the only required macro besides `AC_INIT` (see Section 4.3 [Input], page 18).

`AC_OUTPUT` [Macro]

Generate '`config.status`' and launch it. Call this macro once, at the end of '`configure.ac`'.

'`config.status`' performs all the configuration actions: all the output files (see Section 4.6 [Configuration Files], page 22, macro `AC_CONFIG_FILES`), header files (see Section 4.8 [Configuration Headers], page 31, macro `AC_CONFIG_HEADERS`), commands (see Section 4.9 [Configuration Commands], page 35, macro `AC_CONFIG_COMMANDS`), links (see Section 4.10 [Configuration Links], page 36, macro `AC_CONFIG_LINKS`), subdirectories to configure (see Section 4.11 [Subdirectories], page 36, macro `AC_CONFIG_SUBDIRS`) are honored.

The location of your `AC_OUTPUT` invocation is the exact point where configuration actions are taken: any code afterwards is executed by `configure` once `config.status` was run. If you want to bind actions to `config.status` itself (independently of whether `configure` is being run), see Section 4.9 [Running Arbitrary Configuration Commands], page 35.

Historically, the usage of AC_OUTPUT was somewhat different. See Section 17.4 [Obsolete Macros], page 209, for a description of the arguments that AC_OUTPUT used to support.

If you run make in subdirectories, you should run it using the make variable MAKE. Most versions of make set MAKE to the name of the make program plus any options it was given. (But many do not include in it the values of any variables set on the command line, so those are not passed on automatically.) Some old versions of make do not set this variable. The following macro allows you to use it even with those versions.

AC_PROG_MAKE_SET [Macro]

If the Make command, $MAKE if set or else 'make', predefines $(MAKE), define output variable SET_MAKE to be empty. Otherwise, define SET_MAKE to a macro definition that sets $(MAKE), such as 'MAKE=make'. Calls AC_SUBST for SET_MAKE.

If you use this macro, place a line like this in each 'Makefile.in' that runs MAKE on other directories:

```
@SET_MAKE@
```

4.5 Performing Configuration Actions

'configure' is designed so that it appears to do everything itself, but there is actually a hidden slave: 'config.status'. 'configure' is in charge of examining your system, but it is 'config.status' that actually takes the proper actions based on the results of 'configure'. The most typical task of 'config.status' is to *instantiate* files.

This section describes the common behavior of the four standard instantiating macros: AC_CONFIG_FILES, AC_CONFIG_HEADERS, AC_CONFIG_COMMANDS and AC_CONFIG_LINKS. They all have this prototype:

```
AC_CONFIG_FOOS(tag..., [commands], [init-cmds])
```

where the arguments are:

tag... A blank-or-newline-separated list of tags, which are typically the names of the files to instantiate.

You are encouraged to use literals as *tags*. In particular, you should avoid

```
... && my_foos="$my_foos fooo"
... && my_foos="$my_foos foooo"
AC_CONFIG_FOOS([$my_foos])
```

and use this instead:

```
... && AC_CONFIG_FOOS([fooo])
... && AC_CONFIG_FOOS([foooo])
```

The macros AC_CONFIG_FILES and AC_CONFIG_HEADERS use special *tag* values: they may have the form '*output*' or '*output*:*inputs*'. The file *output* is instantiated from its templates, *inputs* (defaulting to '*output*.in').

'AC_CONFIG_FILES([Makefile:boiler/top.mk:boiler/bot.mk)]', for example, asks for the creation of the file 'Makefile' that contains the expansion of the output variables in the concatenation of 'boiler/top.mk' and 'boiler/bot.mk'.

The special value '-' might be used to denote the standard output when used in *output*, or the standard input when used in the *inputs*. You most probably

don't need to use this in '`configure.ac`', but it is convenient when using the command line interface of '`./config.status`', see Chapter 16 [config.status Invocation], page 205, for more details.

The *inputs* may be absolute or relative file names. In the latter case they are first looked for in the build tree, and then in the source tree.

commands

Shell commands output literally into '`config.status`', and associated with a tag that the user can use to tell '`config.status`' which the commands to run. The commands are run each time a *tag* request is given to '`config.status`', typically each time the file '`tag`' is created.

The variables set during the execution of `configure` are *not* available here: you first need to set them via the *init-cmds*. Nonetheless the following variables are precomputed:

`srcdir`
: The name of the top source directory, assuming that the working directory is the top build directory. This is what the `configure` option '`--srcdir`' sets.

`ac_top_srcdir`
: The name of the top source directory, assuming that the working directory is the current build directory.

`ac_top_build_prefix`
: The name of the top build directory, assuming that the working directory is the current build directory. It can be empty, or else ends with a slash, so that you may concatenate it.

`ac_srcdir`
: The name of the corresponding source directory, assuming that the working directory is the current build directory.

The *current* directory refers to the directory (or pseudo-directory) containing the input part of *tags*. For instance, running

```
AC_CONFIG_COMMANDS([deep/dir/out:in/in.in], [...], [...])
```

with '`--srcdir=../package`' produces the following values:

```
# Argument of --srcdir
srcdir='../package'
# Reversing deep/dir
ac_top_build_prefix='../../'
# Concatenation of $ac_top_build_prefix and srcdir
ac_top_srcdir='../../../package'
# Concatenation of $ac_top_srcdir and deep/dir
ac_srcdir='../../../package/deep/dir'
```

independently of '`in/in.in`'.

init-cmds

Shell commands output *unquoted* near the beginning of '`config.status`', and executed each time '`config.status`' runs (regardless of the tag). Because they are unquoted, for example, '`$var`' is output as the value of `var`. *init-cmds* is

typically used by ‘`configure`’ to give ‘`config.status`’ some variables it needs to run the *commands*.

You should be extremely cautious in your variable names: all the *init-cmds* share the same name space and may overwrite each other in unpredictable ways. Sorry...

All these macros can be called multiple times, with different *tag* values, of course!

4.6 Creating Configuration Files

Be sure to read the previous section, Section 4.5 [Configuration Actions], page 20.

`AC_CONFIG_FILES` (*file...*, [*cmds*], [*init-cmds*]) [Macro]

Make `AC_OUTPUT` create each ‘*file*’ by copying an input file (by default ‘*file*`.in`’), substituting the output variable values. This macro is one of the instantiating macros; see Section 4.5 [Configuration Actions], page 20. See Section 4.7 [Makefile Substitutions], page 22, for more information on using output variables. See Section 7.2 [Setting Output Variables], page 100, for more information on creating them. This macro creates the directory that the file is in if it doesn't exist. Usually, makefiles are created this way, but other files, such as ‘`.gdbinit`’, can be specified as well.

Typical calls to `AC_CONFIG_FILES` look like this:

```
AC_CONFIG_FILES([Makefile src/Makefile man/Makefile X/Imakefile])
AC_CONFIG_FILES([autoconf], [chmod +x autoconf])
```

You can override an input file name by appending to *file* a colon-separated list of input files. Examples:

```
AC_CONFIG_FILES([Makefile:boiler/top.mk:boiler/bot.mk]
                [lib/Makefile:boiler/lib.mk])
```

Doing this allows you to keep your file names acceptable to DOS variants, or to prepend and/or append boilerplate to the file.

4.7 Substitutions in Makefiles

Each subdirectory in a distribution that contains something to be compiled or installed should come with a file ‘`Makefile.in`’, from which `configure` creates a file ‘`Makefile`’ in that directory. To create ‘`Makefile`’, `configure` performs a simple variable substitution, replacing occurrences of ‘`@`*variable*`@`’ in ‘`Makefile.in`’ with the value that `configure` has determined for that variable. Variables that are substituted into output files in this way are called *output variables*. They are ordinary shell variables that are set in `configure`. To make `configure` substitute a particular variable into the output files, the macro `AC_SUBST` must be called with that variable name as an argument. Any occurrences of ‘`@`*variable*`@`’ for other variables are left unchanged. See Section 7.2 [Setting Output Variables], page 100, for more information on creating output variables with `AC_SUBST`.

A software package that uses a `configure` script should be distributed with a file ‘`Makefile.in`’, but no makefile; that way, the user has to properly configure the package for the local system before compiling it.

See section “Makefile Conventions” in *The GNU Coding Standards*, for more information on what to put in makefiles.

4.7.1 Preset Output Variables

Some output variables are preset by the Autoconf macros. Some of the Autoconf macros set additional output variables, which are mentioned in the descriptions for those macros. See Section B.2 [Output Variable Index], page 255, for a complete list of output variables. See Section 4.7.2 [Installation Directory Variables], page 25, for the list of the preset ones related to installation directories. Below are listed the other preset ones. They all are precious variables (see Section 7.2 [Setting Output Variables], page 100, `AC_ARG_VAR`).

`CFLAGS` [Variable]

Debugging and optimization options for the C compiler. If it is not set in the environment when `configure` runs, the default value is set when you call `AC_PROG_CC` (or empty if you don't). `configure` uses this variable when compiling programs to test for C features.

`configure_input` [Variable]

A comment saying that the file was generated automatically by `configure` and giving the name of the input file. `AC_OUTPUT` adds a comment line containing this variable to the top of every makefile it creates. For other files, you should reference this variable in a comment at the top of each input file. For example, an input shell script should begin like this:

```
#!/bin/sh
# @configure_input@
```

The presence of that line also reminds people editing the file that it needs to be processed by `configure` in order to be used.

`CPPFLAGS` [Variable]

Header file search directory (`-I`*dir*) and any other miscellaneous options for the C and C++ preprocessors and compilers. If it is not set in the environment when `configure` runs, the default value is empty. `configure` uses this variable when compiling or preprocessing programs to test for C and C++ features. See Section 7.3 [Special Chars in Variables], page 102, for limitations that `CPPFLAGS` might run into.

`CXXFLAGS` [Variable]

Debugging and optimization options for the C++ compiler. If it is not set in the environment when `configure` runs, the default value is set when you call `AC_PROG_CXX` (or empty if you don't). `configure` uses this variable when compiling programs to test for C++ features.

`DEFS` [Variable]

`-D` options to pass to the C compiler. If `AC_CONFIG_HEADERS` is called, `configure` replaces `@DEFS@` with `-DHAVE_CONFIG_H` instead (see Section 4.8 [Configuration Headers], page 31). This variable is not defined while `configure` is performing its tests, only when creating the output files. See Section 7.2 [Setting Output Variables], page 100, for how to check the results of previous tests.

`ECHO_C` [Variable]
`ECHO_N` [Variable]

ECHO_T [Variable]

How does one suppress the trailing newline from `echo` for question-answer message pairs? These variables provide a way:

```
echo $ECHO_N "And the winner is... $ECHO_C"
sleep 100000000000
echo "${ECHO_T}dead."
```

Some old and uncommon `echo` implementations offer no means to achieve this, in which case `ECHO_T` is set to tab. You might not want to use it.

ERLCFLAGS [Variable]

Debugging and optimization options for the Erlang compiler. If it is not set in the environment when `configure` runs, the default value is empty. `configure` uses this variable when compiling programs to test for Erlang features.

FCFLAGS [Variable]

Debugging and optimization options for the Fortran compiler. If it is not set in the environment when `configure` runs, the default value is set when you call `AC_PROG_FC` (or empty if you don't). `configure` uses this variable when compiling programs to test for Fortran features.

FFLAGS [Variable]

Debugging and optimization options for the Fortran 77 compiler. If it is not set in the environment when `configure` runs, the default value is set when you call `AC_PROG_F77` (or empty if you don't). `configure` uses this variable when compiling programs to test for Fortran 77 features.

LDFLAGS [Variable]

Stripping (‘`-s`’), path (‘`-L`’), and any other miscellaneous options for the linker. Don't use this variable to pass library names (‘`-l`’) to the linker, use `LIBS` instead. If it is not set in the environment when `configure` runs, the default value is empty. `configure` uses this variable when linking programs to test for C, C++, and Fortran features.

LIBS [Variable]

‘`-l`’ options to pass to the linker. The default value is empty, but some Autoconf macros may prepend extra libraries to this variable if those libraries are found and provide necessary functions, see Section 5.4 [Libraries], page 46. `configure` uses this variable when linking programs to test for C, C++, and Fortran features.

OBJCFLAGS [Variable]

Debugging and optimization options for the Objective C compiler. If it is not set in the environment when `configure` runs, the default value is set when you call `AC_PROG_OBJC` (or empty if you don't). `configure` uses this variable when compiling programs to test for Objective C features.

builddir [Variable]

Rigorously equal to ‘`.`’. Added for symmetry only.

abs_builddir [Variable]

Absolute name of `builddir`.

`top_builddir` [Variable]
: The relative name of the top level of the current build tree. In the top-level directory, this is the same as `builddir`.

`abs_top_builddir` [Variable]
: Absolute name of `top_builddir`.

`srcdir` [Variable]
: The relative name of the directory that contains the source code for that makefile.

`abs_srcdir` [Variable]
: Absolute name of `srcdir`.

`top_srcdir` [Variable]
: The relative name of the top-level source code directory for the package. In the top-level directory, this is the same as `srcdir`.

`abs_top_srcdir` [Variable]
: Absolute name of `top_srcdir`.

4.7.2 Installation Directory Variables

The following variables specify the directories for package installation, see section "Variables for Installation Directories" in *The GNU Coding Standards*, for more information. See the end of this section for details on when and how to use these variables.

`bindir` [Variable]
: The directory for installing executables that users run.

`datadir` [Variable]
: The directory for installing idiosyncratic read-only architecture-independent data.

`datarootdir` [Variable]
: The root of the directory tree for read-only architecture-independent data files.

`docdir` [Variable]
: The directory for installing documentation files (other than Info and man).

`dvidir` [Variable]
: The directory for installing documentation files in DVI format.

`exec_prefix` [Variable]
: The installation prefix for architecture-dependent files. By default it's the same as *prefix*. You should avoid installing anything directly to *exec_prefix*. However, the default value for directories containing architecture-dependent files should be relative to *exec_prefix*.

`htmldir` [Variable]
: The directory for installing HTML documentation.

`includedir` [Variable]
: The directory for installing C header files.

`infodir` [Variable]
The directory for installing documentation in Info format.

`libdir` [Variable]
The directory for installing object code libraries.

`libexecdir` [Variable]
The directory for installing executables that other programs run.

`localedir` [Variable]
The directory for installing locale-dependent but architecture-independent data, such as message catalogs. This directory usually has a subdirectory per locale.

`localstatedir` [Variable]
The directory for installing modifiable single-machine data.

`mandir` [Variable]
The top-level directory for installing documentation in man format.

`oldincludedir` [Variable]
The directory for installing C header files for non-GCC compilers.

`pdfdir` [Variable]
The directory for installing PDF documentation.

`prefix` [Variable]
The common installation prefix for all files. If *exec_prefix* is defined to a different value, *prefix* is used only for architecture-independent files.

`psdir` [Variable]
The directory for installing PostScript documentation.

`sbindir` [Variable]
The directory for installing executables that system administrators run.

`sharedstatedir` [Variable]
The directory for installing modifiable architecture-independent data.

`sysconfdir` [Variable]
The directory for installing read-only single-machine data.

Most of these variables have values that rely on `prefix` or `exec_prefix`. It is deliberate that the directory output variables keep them unexpanded: typically '`@datarootdir@`' is replaced by '`${prefix}/share`', not '`/usr/local/share`', and '`@datadir@`' is replaced by '`${datarootdir}`'.

This behavior is mandated by the GNU coding standards, so that when the user runs:

'`make`' she can still specify a different prefix from the one specified to `configure`, in which case, if needed, the package should hard code dependencies corresponding to the make-specified prefix.

'`make install`'
: she can specify a different installation location, in which case the package *must* still depend on the location which was compiled in (i.e., never recompile when '`make install`' is run). This is an extremely important feature, as many people may decide to install all the files of a package grouped together, and then install links from the final locations to there.

In order to support these features, it is essential that `datarootdir` remains being defined as '`${prefix}/share`' to depend upon the current value of `prefix`.

A corollary is that you should not use these variables except in makefiles. For instance, instead of trying to evaluate `datadir` in '`configure`' and hard-coding it in makefiles using e.g., '`AC_DEFINE_UNQUOTED([DATADIR], ["$datadir"], [Data directory.])`', you should add '`-DDATADIR='$(datadir)''` to your makefile's definition of `CPPFLAGS` (`AM_CPPFLAGS` if you are also using Automake).

Similarly, you should not rely on `AC_CONFIG_FILES` to replace `datadir` and friends in your shell scripts and other files; instead, let `make` manage their replacement. For instance Autoconf ships templates of its shell scripts ending with '`.in`', and uses a makefile snippet similar to the following to build scripts like `autoheader` and `autom4te`:

```
edit = sed \
        -e 's|@datadir[@]|$(pkgdatadir)|g' \
        -e 's|@prefix[@]|$(prefix)|g'

autoheader autom4te: Makefile
        rm -f $@ $@.tmp
        $(edit) '$(srcdir)/$@.in' >$@.tmp
        chmod +x $@.tmp
        chmod a-w $@.tmp
        mv $@.tmp $@

autoheader: $(srcdir)/autoheader.in
autom4te: $(srcdir)/autom4te.in
```

Some details are noteworthy:

'`@datadir[@]`'
: The brackets prevent `configure` from replacing '`@datadir@`' in the Sed expression itself. Brackets are preferable to a backslash here, since Posix says '`\@`' is not portable.

'`$(pkgdatadir)`'
: Don't use '`@pkgdatadir@`'! Use the matching makefile variable instead.

'`/`'
: Don't use '`/`' in the Sed expressions that replace file names since most likely the variables you use, such as '`$(pkgdatadir)`', contain '`/`'. Use a shell metacharacter instead, such as '`|`'.

special characters
: File names, file name components, and the value of `VPATH` should not contain shell metacharacters or white space. See Section 7.3 [Special Chars in Variables], page 102.

dependency on '`Makefile`'
: Since `edit` uses values that depend on the configuration specific values (`prefix`, etc.) and not only on `VERSION` and so forth, the output depends on '`Makefile`', not '`configure.ac`'.

'`$@`'
: The main rule is generic, and uses '`$@`' extensively to avoid the need for multiple copies of the rule.

Separated dependencies and single suffix rules
: You can't use them! The above snippet cannot be (portably) rewritten as:

```
autoconf autoheader: Makefile
.in:
        rm -f $@ $@.tmp
        $(edit) $< >$@.tmp
        chmod +x $@.tmp
        mv $@.tmp $@
```

  See Section 11.14 [Single Suffix Rules], page 182, for details.

'`$(srcdir)`'
: Be sure to specify the name of the source directory, otherwise the package won't support separated builds.

For the more specific installation of Erlang libraries, the following variables are defined:

`ERLANG_INSTALL_LIB_DIR` [Variable]
: The common parent directory of Erlang library installation directories. This variable is set by calling the `AC_ERLANG_SUBST_INSTALL_LIB_DIR` macro in '`configure.ac`'.

`ERLANG_INSTALL_LIB_DIR_`*`library`* [Variable]
: The installation directory for Erlang library *library*. This variable is set by calling the '`AC_ERLANG_SUBST_INSTALL_LIB_SUBDIR(`*`library`*`,` *`version`*' macro in '`configure.ac`'.

See Section 5.13 [Erlang Libraries], page 84, for details.

4.7.3 Changed Directory Variables

In Autoconf 2.60, the set of directory variables has changed, and the defaults of some variables have been adjusted (see Section 4.7.2 [Installation Directory Variables], page 25) to changes in the GNU Coding Standards. Notably, '`datadir`', '`infodir`', and '`mandir`' are now expressed in terms of '`datarootdir`'. If you are upgrading from an earlier Autoconf version, you may need to adjust your files to ensure that the directory variables are substituted correctly (see Section 19.5 [Defining Directories], page 239), and that a definition of '`datarootdir`' is in place. For example, in a '`Makefile.in`', adding

```
datarootdir = @datarootdir@
```

is usually sufficient. If you use Automake to create '`Makefile.in`', it will add this for you.

To help with the transition, Autoconf warns about files that seem to use `datarootdir` without defining it. In some cases, it then expands the value of `$datarootdir` in substitutions of the directory variables. The following example shows such a warning:

```
$ cat configure.ac
AC_INIT
AC_CONFIG_FILES([Makefile])
AC_OUTPUT
$ cat Makefile.in
prefix = @prefix@
datadir = @datadir@
$ autoconf
$ configure
configure: creating ./config.status
config.status: creating Makefile
config.status: WARNING:
               Makefile.in seems to ignore the --datarootdir setting
$ cat Makefile
prefix = /usr/local
datadir = ${prefix}/share
```

Usually one can easily change the file to accommodate both older and newer Autoconf releases:

```
$ cat Makefile.in
prefix = @prefix@
datarootdir = @datarootdir@
datadir = @datadir@
$ configure
configure: creating ./config.status
config.status: creating Makefile
$ cat Makefile
prefix = /usr/local
datarootdir = ${prefix}/share
datadir = ${datarootdir}
```

In some cases, however, the checks may not be able to detect that a suitable initialization of `datarootdir` is in place, or they may fail to detect that such an initialization is necessary in the output file. If, after auditing your package, there are still spurious '`configure`' warnings about `datarootdir`, you may add the line

```
AC_DEFUN([AC_DATAROOTDIR_CHECKED])
```

to your '`configure.ac`' to disable the warnings. This is an exception to the usual rule that you should not define a macro whose name begins with `AC_` (see Section 9.2 [Macro Names], page 125).

4.7.4 Build Directories

You can support compiling a software package for several architectures simultaneously from the same copy of the source code. The object files for each architecture are kept in their own directory.

To support doing this, `make` uses the `VPATH` variable to find the files that are in the source directory. GNU Make and most other recent `make` programs can do this. Older `make` programs do not support `VPATH`; when using them, the source code must be in the same directory as the object files.

To support `VPATH`, each '`Makefile.in`' should contain two lines that look like:

```
srcdir = @srcdir@
VPATH = @srcdir@
```

Do not set `VPATH` to the value of another variable, for example '`VPATH = $(srcdir)`', because some versions of `make` do not do variable substitutions on the value of `VPATH`.

`configure` substitutes the correct value for `srcdir` when it produces '`Makefile`'.

Do not use the `make` variable `$<`, which expands to the file name of the file in the source directory (found with `VPATH`), except in implicit rules. (An implicit rule is one such as '`.c.o`', which tells how to create a '`.o`' file from a '`.c`' file.) Some versions of `make` do not set `$<` in explicit rules; they expand it to an empty value.

Instead, Make command lines should always refer to source files by prefixing them with '`$(srcdir)/`'. For example:

```
time.info: time.texinfo
        $(MAKEINFO) '$(srcdir)/time.texinfo'
```

4.7.5 Automatic Remaking

You can put rules like the following in the top-level '`Makefile.in`' for a package to automatically update the configuration information when you change the configuration files. This example includes all of the optional files, such as '`aclocal.m4`' and those related to configuration header files. Omit from the '`Makefile.in`' rules for any of these files that your package does not use.

The '`$(srcdir)/`' prefix is included because of limitations in the `VPATH` mechanism.

The '`stamp-`' files are necessary because the timestamps of '`config.h.in`' and '`config.h`' are not changed if remaking them does not change their contents. This feature avoids unnecessary recompilation. You should include the file '`stamp-h.in`' your package's distribution, so that `make` considers '`config.h.in`' up to date. Don't use `touch` (see Section 10.11 [Limitations of Usual Tools], page 158); instead, use `echo` (using `date` would cause needless differences, hence CVS conflicts, etc.).

```
$(srcdir)/configure: configure.ac aclocal.m4
        cd '$(srcdir)' && autoconf

# autoheader might not change config.h.in, so touch a stamp file.
$(srcdir)/config.h.in: stamp-h.in
$(srcdir)/stamp-h.in: configure.ac aclocal.m4
        cd '$(srcdir)' && autoheader
        echo timestamp > '$(srcdir)/stamp-h.in'

config.h: stamp-h
stamp-h: config.h.in config.status
        ./config.status

Makefile: Makefile.in config.status
        ./config.status

config.status: configure
        ./config.status --recheck
```

(Be careful if you copy these lines directly into your makefile, as you need to convert the indented lines to start with the tab character.)

In addition, you should use

```
AC_CONFIG_FILES([stamp-h], [echo timestamp > stamp-h])
```

so '`config.status`' ensures that '`config.h`' is considered up to date. See Section 4.4 [Output], page 19, for more information about `AC_OUTPUT`.

See Chapter 16 [config.status Invocation], page 205, for more examples of handling configuration-related dependencies.

4.8 Configuration Header Files

When a package contains more than a few tests that define C preprocessor symbols, the command lines to pass '`-D`' options to the compiler can get quite long. This causes two problems. One is that the `make` output is hard to visually scan for errors. More seriously, the command lines can exceed the length limits of some operating systems. As an alternative to passing '`-D`' options to the compiler, `configure` scripts can create a C header file containing '`#define`' directives. The `AC_CONFIG_HEADERS` macro selects this kind of output. Though it can be called anywhere between `AC_INIT` and `AC_OUTPUT`, it is customary to call it right after `AC_INIT`.

The package should '`#include`' the configuration header file before any other header files, to prevent inconsistencies in declarations (for example, if it redefines `const`).

To provide for VPATH builds, remember to pass the C compiler a '`-I.`' option (or '`-I..`'; whichever directory contains '`config.h`'). Even if you use '`#include "config.h"`', the preprocessor searches only the directory of the currently read file, i.e., the source directory, not the build directory.

With the appropriate '`-I`' option, you can use '`#include <config.h>`'. Actually, it's a good habit to use it, because in the rare case when the source directory contains another '`config.h`', the build directory should be searched first.

AC_CONFIG_HEADERS (*header* ..., [*cmds*], [*init-cmds*]) [Macro]

This macro is one of the instantiating macros; see Section 4.5 [Configuration Actions], page 20. Make AC_OUTPUT create the file(s) in the blank-or-newline-separated list *header* containing C preprocessor #define statements, and replace '@DEFS@' in generated files with '-DHAVE_CONFIG_H' instead of the value of DEFS. The usual name for *header* is 'config.h'.

If *header* already exists and its contents are identical to what AC_OUTPUT would put in it, it is left alone. Doing this allows making some changes in the configuration without needlessly causing object files that depend on the header file to be recompiled.

Usually the input file is named '*header*.in'; however, you can override the input file name by appending to *header* a colon-separated list of input files. Examples:

```
AC_CONFIG_HEADERS([config.h:config.hin])
AC_CONFIG_HEADERS([defines.h:defs.pre:defines.h.in:defs.post])
```

Doing this allows you to keep your file names acceptable to DOS variants, or to prepend and/or append boilerplate to the file.

AH_HEADER [Macro]

This macro is defined as the name of the first declared config header and undefined if no config headers have been declared up to this point. A third-party macro may, for example, require use of a config header without invoking AC_CONFIG_HEADERS twice, like this:

```
AC_CONFIG_COMMANDS_PRE(
        [m4_ifndef([AH_HEADER], [AC_CONFIG_HEADERS([config.h])])])
```

See Section 4.5 [Configuration Actions], page 20, for more details on *header*.

4.8.1 Configuration Header Templates

Your distribution should contain a template file that looks as you want the final header file to look, including comments, with #undef statements which are used as hooks. For example, suppose your 'configure.ac' makes these calls:

```
AC_CONFIG_HEADERS([conf.h])
AC_CHECK_HEADERS([unistd.h])
```

Then you could have code like the following in 'conf.h.in'. On systems that have 'unistd.h', configure defines 'HAVE_UNISTD_H' to 1. On other systems, the whole line is commented out (in case the system predefines that symbol).

```
/* Define as 1 if you have unistd.h.  */
#undef HAVE_UNISTD_H
```

Pay attention that '#undef' is in the first column, and there is nothing after 'HAVE_UNISTD_H', not even white space. You can then decode the configuration header using the preprocessor directives:

```
#include <conf.h>

#if HAVE_UNISTD_H
# include <unistd.h>
#else
/* We are in trouble.  */
#endif
```

The use of old form templates, with '`#define`' instead of '`#undef`' is strongly discouraged. Similarly with old templates with comments on the same line as the '`#undef`'. Anyway, putting comments in preprocessor macros has never been a good idea.

Since it is a tedious task to keep a template header up to date, you may use `autoheader` to generate it, see Section 4.8.2 [autoheader Invocation], page 33.

4.8.2 Using `autoheader` to Create '`config.h.in`'

The `autoheader` program can create a template file of C '`#define`' statements for `configure` to use. If '`configure.ac`' invokes `AC_CONFIG_HEADERS(`*`file`*`)`, `autoheader` creates '*`file`*`.in`'; if multiple file arguments are given, the first one is used. Otherwise, `autoheader` creates '`config.h.in`'.

In order to do its job, `autoheader` needs you to document all of the symbols that you might use. Typically this is done via an `AC_DEFINE` or `AC_DEFINE_UNQUOTED` call whose first argument is a literal symbol and whose third argument describes the symbol (see Section 7.1 [Defining Symbols], page 99). Alternatively, you can use `AH_TEMPLATE` (see Section 4.8.3 [Autoheader Macros], page 34), or you can supply a suitable input file for a subsequent configuration header file. Symbols defined by Autoconf's builtin tests are already documented properly; you need to document only those that you define yourself.

You might wonder why `autoheader` is needed: after all, why would `configure` need to "patch" a '`config.h.in`' to produce a '`config.h`' instead of just creating '`config.h`' from scratch? Well, when everything rocks, the answer is just that we are wasting our time maintaining `autoheader`: generating '`config.h`' directly is all that is needed. When things go wrong, however, you'll be thankful for the existence of `autoheader`.

The fact that the symbols are documented is important in order to *check* that '`config.h`' makes sense. The fact that there is a well-defined list of symbols that should be defined (or not) is also important for people who are porting packages to environments where `configure` cannot be run: they just have to *fill in the blanks*.

But let's come back to the point: the invocation of `autoheader`...

If you give `autoheader` an argument, it uses that file instead of '`configure.ac`' and writes the header file to the standard output instead of to '`config.h.in`'. If you give `autoheader` an argument of '`-`', it reads the standard input instead of '`configure.ac`' and writes the header file to the standard output.

`autoheader` accepts the following options:

'`--help`'
'`-h`' Print a summary of the command line options and exit.

'`--version`'
'`-V`' Print the version number of Autoconf and exit.

‘--verbose’
‘-v’ Report processing steps.

‘--debug’
‘-d’ Don’t remove the temporary files.

‘--force’
‘-f’ Remake the template file even if newer than its input files.

‘--include=*dir*’
‘-I *dir*’ Append *dir* to the include path. Multiple invocations accumulate.

‘--prepend-include=*dir*’
‘-B *dir*’ Prepend *dir* to the include path. Multiple invocations accumulate.

‘--warnings=*category*’
‘-W *category*’
Report the warnings related to *category* (which can actually be a comma separated list). Current categories include:

‘obsolete’
report the uses of obsolete constructs

‘all’ report all the warnings

‘none’ report none

‘error’ treats warnings as errors

‘no-*category*’
disable warnings falling into *category*

4.8.3 Autoheader Macros

`autoheader` scans ‘`configure.ac`’ and figures out which C preprocessor symbols it might define. It knows how to generate templates for symbols defined by `AC_CHECK_HEADERS`, `AC_CHECK_FUNCS` etc., but if you `AC_DEFINE` any additional symbol, you must define a template for it. If there are missing templates, `autoheader` fails with an error message.

The simplest way to create a template for a *symbol* is to supply the *description* argument to an ‘`AC_DEFINE(`*symbol*`)`’; see Section 7.1 [Defining Symbols], page 99. You may also use one of the following macros.

`AH_VERBATIM (`*key*, *template*`)` [Macro]
Tell `autoheader` to include the *template* as-is in the header template file. This *template* is associated with the *key*, which is used to sort all the different templates and guarantee their uniqueness. It should be a symbol that can be defined via `AC_DEFINE`.

For example:

```
AH_VERBATIM([_GNU_SOURCE],
[/* Enable GNU extensions on systems that have them.  */
#ifndef _GNU_SOURCE
# define _GNU_SOURCE
#endif])
```

`AH_TEMPLATE` (*key*, *description*) [Macro]

Tell `autoheader` to generate a template for *key*. This macro generates standard templates just like `AC_DEFINE` when a *description* is given.

For example:

```
AH_TEMPLATE([CRAY_STACKSEG_END],
            [Define to one of _getb67, GETB67, getb67
             for Cray-2 and Cray-YMP systems.  This
             function is required for alloca.c support
             on those systems.])
```

generates the following template, with the description properly justified.

```
/* Define to one of _getb67, GETB67, getb67 for Cray-2 and
   Cray-YMP systems.  This function is required for alloca.c
   support on those systems.  */
#undef CRAY_STACKSEG_END
```

`AH_TOP` (*text*) [Macro]

Include *text* at the top of the header template file.

`AH_BOTTOM` (*text*) [Macro]

Include *text* at the bottom of the header template file.

4.9 Running Arbitrary Configuration Commands

You can execute arbitrary commands before, during, and after '`config.status`' is run. The three following macros accumulate the commands to run when they are called multiple times. `AC_CONFIG_COMMANDS` replaces the obsolete macro `AC_OUTPUT_COMMANDS`; see Section 17.4 [Obsolete Macros], page 209, for details.

`AC_CONFIG_COMMANDS` (*tag*..., [*cmds*], [*init-cmds*]) [Macro]

Specify additional shell commands to run at the end of '`config.status`', and shell commands to initialize any variables from `configure`. Associate the commands with *tag*. Since typically the *cmds* create a file, *tag* should naturally be the name of that file. If needed, the directory hosting *tag* is created. This macro is one of the instantiating macros; see Section 4.5 [Configuration Actions], page 20.

Here is an unrealistic example:

```
fubar=42
AC_CONFIG_COMMANDS([fubar],
                   [echo this is extra $fubar, and so on.],
                   [fubar=$fubar])
```

Here is a better one:

```
AC_CONFIG_COMMANDS([timestamp], [date >timestamp])
```

The following two macros look similar, but in fact they are not of the same breed: they are executed directly by '`configure`', so you cannot use '`config.status`' to rerun them.

`AC_CONFIG_COMMANDS_PRE` (*cmds*) [Macro]

Execute the *cmds* right before creating '`config.status`'.

This macro presents the last opportunity to call AC_SUBST, AC_DEFINE, or AC_CONFIG_FOOS macros.

AC_CONFIG_COMMANDS_POST (*cmds*) [Macro]
Execute the *cmds* right after creating 'config.status'.

4.10 Creating Configuration Links

You may find it convenient to create links whose destinations depend upon results of tests. One can use AC_CONFIG_COMMANDS but the creation of relative symbolic links can be delicate when the package is built in a directory different from the source directory.

AC_CONFIG_LINKS (*dest:source*..., [*cmds*], [*init-cmds*]) [Macro]
Make AC_OUTPUT link each of the existing files *source* to the corresponding link name *dest*. Makes a symbolic link if possible, otherwise a hard link if possible, otherwise a copy. The *dest* and *source* names should be relative to the top level source or build directory. This macro is one of the instantiating macros; see Section 4.5 [Configuration Actions], page 20.

For example, this call:

```
AC_CONFIG_LINKS([host.h:config/$machine.h
                 object.h:config/$obj_format.h])
```

creates in the current directory 'host.h' as a link to '*srcdir*/config/$machine.h', and 'object.h' as a link to '*srcdir*/config/$obj_format.h'.

The tempting value '.' for *dest* is invalid: it makes it impossible for 'config.status' to guess the links to establish.

One can then run:

```
./config.status host.h object.h
```

to create the links.

4.11 Configuring Other Packages in Subdirectories

In most situations, calling AC_OUTPUT is sufficient to produce makefiles in subdirectories. However, configure scripts that control more than one independent package can use AC_CONFIG_SUBDIRS to run configure scripts for other packages in subdirectories.

AC_CONFIG_SUBDIRS (*dir* ...) [Macro]
Make AC_OUTPUT run configure in each subdirectory *dir* in the given blank-or-newline-separated list. Each *dir* should be a literal, i.e., please do not use:

```
if test "$package_foo_enabled" = yes; then
  $my_subdirs="$my_subdirs foo"
fi
AC_CONFIG_SUBDIRS([$my_subdirs])
```

because this prevents './configure --help=recursive' from displaying the options of the package foo. Instead, you should write:

```
if test "$package_foo_enabled" = yes; then
  AC_CONFIG_SUBDIRS([foo])
```

```
fi
```

If a given *dir* is not found, an error is reported: if the subdirectory is optional, write:

```
if test -d "$srcdir/foo"; then
  AC_CONFIG_SUBDIRS([foo])
fi
```

If a given *dir* contains `configure.gnu`, it is run instead of `configure`. This is for packages that might use a non-Autoconf script `Configure`, which can't be called through a wrapper `configure` since it would be the same file on case-insensitive file systems. Likewise, if a *dir* contains '`configure.in`' but no `configure`, the Cygnus `configure` script found by `AC_CONFIG_AUX_DIR` is used.

The subdirectory `configure` scripts are given the same command line options that were given to this `configure` script, with minor changes if needed, which include:

- adjusting a relative name for the cache file;
- adjusting a relative name for the source directory;
- propagating the current value of `$prefix`, including if it was defaulted, and if the default values of the top level and of the subdirectory '`configure`' differ.

This macro also sets the output variable `subdirs` to the list of directories '*dir* ...'. Make rules can use this variable to determine which subdirectories to recurse into.

This macro may be called multiple times.

4.12 Default Prefix

By default, `configure` sets the prefix for files it installs to '`/usr/local`'. The user of `configure` can select a different prefix using the '`--prefix`' and '`--exec-prefix`' options. There are two ways to change the default: when creating `configure`, and when running it.

Some software packages might want to install in a directory other than '`/usr/local`' by default. To accomplish that, use the `AC_PREFIX_DEFAULT` macro.

`AC_PREFIX_DEFAULT` (*prefix*) [Macro]

Set the default installation prefix to *prefix* instead of '`/usr/local`'.

It may be convenient for users to have `configure` guess the installation prefix from the location of a related program that they have already installed. If you wish to do that, you can call `AC_PREFIX_PROGRAM`.

`AC_PREFIX_PROGRAM` (*program*) [Macro]

If the user did not specify an installation prefix (using the '`--prefix`' option), guess a value for it by looking for *program* in `PATH`, the way the shell does. If *program* is found, set the prefix to the parent of the directory containing *program*, else default the prefix as described above ('`/usr/local`' or `AC_PREFIX_DEFAULT`). For example, if *program* is `gcc` and the `PATH` contains '`/usr/local/gnu/bin/gcc`', set the prefix to '`/usr/local/gnu`'.

5 Existing Tests

These macros test for particular system features that packages might need or want to use. If you need to test for a kind of feature that none of these macros check for, you can probably do it by calling primitive test macros with appropriate arguments (see Chapter 6 [Writing Tests], page 87).

These tests print messages telling the user which feature they're checking for, and what they find. They cache their results for future `configure` runs (see Section 7.4 [Caching Results], page 102).

Some of these macros set output variables. See Section 4.7 [Makefile Substitutions], page 22, for how to get their values. The phrase "define *name*" is used below as a shorthand to mean "define the C preprocessor symbol *name* to the value 1". See Section 7.1 [Defining Symbols], page 99, for how to get those symbol definitions into your program.

5.1 Common Behavior

Much effort has been expended to make Autoconf easy to learn. The most obvious way to reach this goal is simply to enforce standard interfaces and behaviors, avoiding exceptions as much as possible. Because of history and inertia, unfortunately, there are still too many exceptions in Autoconf; nevertheless, this section describes some of the common rules.

5.1.1 Standard Symbols

All the generic macros that `AC_DEFINE` a symbol as a result of their test transform their *argument* values to a standard alphabet. First, *argument* is converted to upper case and any asterisks ('`*`') are each converted to '`P`'. Any remaining characters that are not alphanumeric are converted to underscores.

For instance,

```
AC_CHECK_TYPES([struct $Expensive*])
```

defines the symbol '`HAVE_STRUCT__EXPENSIVEP`' if the check succeeds.

5.1.2 Default Includes

Several tests depend upon a set of header files. Since these headers are not universally available, tests actually have to provide a set of protected includes, such as:

```
#if TIME_WITH_SYS_TIME
# include <sys/time.h>
# include <time.h>
#else
# if HAVE_SYS_TIME_H
#  include <sys/time.h>
# else
#  include <time.h>
# endif
#endif
```

Unless you know exactly what you are doing, you should avoid using unconditional includes, and check the existence of the headers you include beforehand (see Section 5.6 [Header Files], page 57).

Most generic macros use the following macro to provide the default set of includes:

`AC_INCLUDES_DEFAULT` ([*include-directives*]) [Macro]

Expand to *include-directives* if defined, otherwise to:

```
#include <stdio.h>
#if HAVE_SYS_TYPES_H
# include <sys/types.h>
#endif
#if HAVE_SYS_STAT_H
# include <sys/stat.h>
#endif
#if STDC_HEADERS
# include <stdlib.h>
# include <stddef.h>
#else
# if HAVE_STDLIB_H
#  include <stdlib.h>
# endif
#endif
#if HAVE_STRING_H
# if !STDC_HEADERS && HAVE_MEMORY_H
#  include <memory.h>
# endif
# include <string.h>
#endif
#if HAVE_STRINGS_H
# include <strings.h>
#endif
#if HAVE_INTTYPES_H
# include <inttypes.h>
#endif
#if HAVE_STDINT_H
# include <stdint.h>
#endif
#if HAVE_UNISTD_H
# include <unistd.h>
#endif
```

If the default includes are used, then check for the presence of these headers and their compatibility, i.e., you don't need to run `AC_HEADER_STDC`, nor check for '`stdlib.h`' etc.

These headers are checked for in the same order as they are included. For instance, on some systems '`string.h`' and '`strings.h`' both exist, but conflict. Then `HAVE_STRING_H` is defined, not `HAVE_STRINGS_H`.

5.2 Alternative Programs

These macros check for the presence or behavior of particular programs. They are used to choose between several alternative programs and to decide what to do once one has been chosen. If there is no macro specifically defined to check for a program you need, and you don't need to check for any special properties of it, then you can use one of the general program-check macros.

5.2.1 Particular Program Checks

These macros check for particular programs—whether they exist, and in some cases whether they support certain features.

`AC_PROG_AWK` [Macro]

Check for `gawk`, `mawk`, `nawk`, and `awk`, in that order, and set output variable `AWK` to the first one that is found. It tries `gawk` first because that is reported to be the best implementation.

`AC_PROG_GREP` [Macro]

Look for the best available `grep` or `ggrep` that accepts the longest input lines possible, and that supports multiple '`-e`' options. Set the output variable `GREP` to whatever is chosen. See Section 10.11 [Limitations of Usual Tools], page 158, for more information about portability problems with the `grep` command family.

`AC_PROG_EGREP` [Macro]

Check whether `$GREP -E` works, or else look for the best available `egrep` or `gegrep` that accepts the longest input lines possible. Set the output variable `EGREP` to whatever is chosen.

`AC_PROG_FGREP` [Macro]

Check whether `$GREP -F` works, or else look for the best available `fgrep` or `gfgrep` that accepts the longest input lines possible. Set the output variable `FGREP` to whatever is chosen.

`AC_PROG_INSTALL` [Macro]

Set output variable `INSTALL` to the name of a BSD-compatible `install` program, if one is found in the current `PATH`. Otherwise, set `INSTALL` to '*dir*`/install-sh -c`', checking the directories specified to `AC_CONFIG_AUX_DIR` (or its default directories) to determine *dir* (see Section 4.4 [Output], page 19). Also set the variables `INSTALL_PROGRAM` and `INSTALL_SCRIPT` to '`${INSTALL}`' and `INSTALL_DATA` to '`${INSTALL} -m 644`'.

This macro screens out various instances of `install` known not to work. It prefers to find a C program rather than a shell script, for speed. Instead of '`install-sh`', it can also use '`install.sh`', but that name is obsolete because some `make` programs have a rule that creates '`install`' from it if there is no makefile.

Autoconf comes with a copy of '`install-sh`' that you can use. If you use `AC_PROG_INSTALL`, you must include either '`install-sh`' or '`install.sh`' in your distribution; otherwise `configure` produces an error message saying it can't find them—even if the system you're on has a good `install` program. This check is a safety measure to

prevent you from accidentally leaving that file out, which would prevent your package from installing on systems that don't have a BSD-compatible `install` program.

If you need to use your own installation program because it has features not found in standard `install` programs, there is no reason to use `AC_PROG_INSTALL`; just put the file name of your program into your '`Makefile.in`' files.

`AC_PROG_MKDIR_P` [Macro]

Set output variable `MKDIR_P` to a program that ensures that for each argument, a directory named by this argument exists, creating it and its parent directories if needed, and without race conditions when two instances of the program attempt to make the same directory at nearly the same time.

This macro uses the '`mkdir -p`' command if possible. Otherwise, it falls back on invoking `install-sh` with the '`-d`' option, so your package should contain '`install-sh`' as described under `AC_PROG_INSTALL`. An '`install-sh`' file that predates Autoconf 2.60 or Automake 1.10 is vulnerable to race conditions, so if you want to support parallel installs from different packages into the same directory you need to make sure you have an up-to-date '`install-sh`'. In particular, be careful about using '`autoreconf -if`' if your Automake predates Automake 1.10.

This macro is related to the `AS_MKDIR_P` macro (see Section 8.4 [Programming in M4sh], page 121), but it sets an output variable intended for use in other files, whereas `AS_MKDIR_P` is intended for use in scripts like `configure`. Also, `AS_MKDIR_P` does not accept options, but `MKDIR_P` supports the '`-m`' option, e.g., a makefile might invoke `$(MKDIR_P) -m 0 dir` to create an inaccessible directory, and conversely a makefile should use `$(MKDIR_P) -- $(FOO)` if *FOO* might yield a value that begins with '`-`'. Finally, `AS_MKDIR_P` does not check for race condition vulnerability, whereas `AC_PROG_MKDIR_P` does.

`AC_PROG_LEX` [Macro]

If `flex` is found, set output variable `LEX` to '`flex`' and `LEXLIB` to '`-lfl`', if that library is in a standard place. Otherwise set `LEX` to '`lex`' and `LEXLIB` to '`-ll`'.

Define `YYTEXT_POINTER` if `yytext` is a '`char *`' instead of a '`char []`'. Also set output variable `LEX_OUTPUT_ROOT` to the base of the file name that the lexer generates; usually '`lex.yy`', but sometimes something else. These results vary according to whether `lex` or `flex` is being used.

You are encouraged to use Flex in your sources, since it is both more pleasant to use than plain Lex and the C source it produces is portable. In order to ensure portability, however, you must either provide a function `yywrap` or, if you don't use it (e.g., your scanner has no '`#include`'-like feature), simply include a '`%noyywrap`' statement in the scanner's source. Once this done, the scanner is portable (unless *you* felt free to use nonportable constructs) and does not depend on any library. In this case, and in this case only, it is suggested that you use this Autoconf snippet:

```
AC_PROG_LEX
if test "$LEX" != flex; then
  LEX="$SHELL $missing_dir/missing flex"
  AC_SUBST([LEX_OUTPUT_ROOT], [lex.yy])
  AC_SUBST([LEXLIB], [''])
```

```
fi
```

The shell script `missing` can be found in the Automake distribution.

To ensure backward compatibility, Automake's `AM_PROG_LEX` invokes (indirectly) this macro twice, which causes an annoying but benign "`AC_PROG_LEX` invoked multiple times" warning. Future versions of Automake will fix this issue; meanwhile, just ignore this message.

As part of running the test, this macro may delete any file in the configuration directory named '`lex.yy.c`' or '`lexyy.c`'.

`AC_PROG_LN_S` [Macro]

If '`ln -s`' works on the current file system (the operating system and file system support symbolic links), set the output variable `LN_S` to '`ln -s`'; otherwise, if '`ln`' works, set `LN_S` to '`ln`', and otherwise set it to '`cp -p`'.

If you make a link in a directory other than the current directory, its meaning depends on whether '`ln`' or '`ln -s`' is used. To safely create links using '`$(LN_S)`', either find out which form is used and adjust the arguments, or always invoke `ln` in the directory where the link is to be created.

In other words, it does not work to do:

```
$(LN_S) foo /x/bar
```

Instead, do:

```
(cd /x && $(LN_S) foo bar)
```

`AC_PROG_RANLIB` [Macro]

Set output variable `RANLIB` to '`ranlib`' if `ranlib` is found, and otherwise to '`:`' (do nothing).

`AC_PROG_SED` [Macro]

Set output variable `SED` to a Sed implementation that conforms to Posix and does not have arbitrary length limits. Report an error if no acceptable Sed is found. See Section 10.11 [Limitations of Usual Tools], page 158, for more information about portability problems with Sed.

`AC_PROG_YACC` [Macro]

If `bison` is found, set output variable `YACC` to '`bison -y`'. Otherwise, if `byacc` is found, set `YACC` to '`byacc`'. Otherwise set `YACC` to '`yacc`'.

5.2.2 Generic Program and File Checks

These macros are used to find programs not covered by the "particular" test macros. If you need to check the behavior of a program as well as find out whether it is present, you have to write your own test for it (see Chapter 6 [Writing Tests], page 87). By default, these macros use the environment variable `PATH`. If you need to check for a program that might not be in the user's `PATH`, you can pass a modified path to use instead, like this:

```
AC_PATH_PROG([INETD], [inetd], [/usr/libexec/inetd],
             [$PATH:/usr/libexec:/usr/sbin:/usr/etc:/etc])
```

You are strongly encouraged to declare the *variable* passed to `AC_CHECK_PROG` etc. as precious, See Section 7.2 [Setting Output Variables], page 100, `AC_ARG_VAR`, for more details.

AC_CHECK_PROG (*variable*, *prog-to-check-for*, *value-if-found*, [*value-if-not-found*], [*path*], [*reject*]) [Macro]

Check whether program *prog-to-check-for* exists in PATH. If it is found, set *variable* to *value-if-found*, otherwise to *value-if-not-found*, if given. Always pass over *reject* (an absolute file name) even if it is the first found in the search path; in that case, set *variable* using the absolute file name of the *prog-to-check-for* found that is not *reject*. If *variable* was already set, do nothing. Calls AC_SUBST for *variable*.

AC_CHECK_PROGS (*variable*, *progs-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Check for each program in the blank-separated list *progs-to-check-for* existing in the PATH. If one is found, set *variable* to the name of that program. Otherwise, continue checking the next program in the list. If none of the programs in the list are found, set *variable* to *value-if-not-found*; if *value-if-not-found* is not specified, the value of *variable* is not changed. Calls AC_SUBST for *variable*.

AC_CHECK_TARGET_TOOL (*variable*, *prog-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like AC_CHECK_PROG, but first looks for *prog-to-check-for* with a prefix of the target type as determined by AC_CANONICAL_TARGET, followed by a dash (see Section 13.2 [Canonicalizing], page 190). If the tool cannot be found with a prefix, and if the build and target types are equal, then it is also searched for without a prefix.

As noted in Section 13.1 [Specifying the system type], page 189, the target is rarely specified, because most of the time it is the same as the host: it is the type of system for which any compiler tool in the package produces code. What this macro looks for is, for example, *a tool* (assembler, linker, etc.) *that the compiler driver* (gcc for the GNU C Compiler) *uses to produce objects, archives or executables*.

AC_CHECK_TOOL (*variable*, *prog-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like AC_CHECK_PROG, but first looks for *prog-to-check-for* with a prefix of the host type as determined by AC_CANONICAL_HOST, followed by a dash (see Section 13.2 [Canonicalizing], page 190). For example, if the user runs '`configure --host=i386-gnu`', then this call:

```
AC_CHECK_TOOL([RANLIB], [ranlib], [:])
```

sets RANLIB to '`i386-gnu-ranlib`' if that program exists in PATH, or otherwise to '`ranlib`' if that program exists in PATH, or to '`:`' if neither program exists.

In the future, when cross-compiling this macro will *only* accept program names that are prefixed with the host type. For more information, see Section 13.1 [Specifying the system type], page 189.

AC_CHECK_TARGET_TOOLS (*variable*, *progs-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like AC_CHECK_TARGET_TOOL, each of the tools in the list *progs-to-check-for* are checked with a prefix of the target type as determined by AC_CANONICAL_TARGET, followed by a dash (see Section 13.2 [Canonicalizing], page 190). If none of the tools can be found with a prefix, and if the build and target types are equal, then the

first one without a prefix is used. If a tool is found, set *variable* to the name of that program. If none of the tools in the list are found, set *variable* to *value-if-not-found*; if *value-if-not-found* is not specified, the value of *variable* is not changed. Calls `AC_SUBST` for *variable*.

`AC_CHECK_TOOLS` (*variable*, *progs-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like `AC_CHECK_TOOL`, each of the tools in the list *progs-to-check-for* are checked with a prefix of the host type as determined by `AC_CANONICAL_HOST`, followed by a dash (see Section 13.2 [Canonicalizing], page 190). If none of the tools can be found with a prefix, then the first one without a prefix is used. If a tool is found, set *variable* to the name of that program. If none of the tools in the list are found, set *variable* to *value-if-not-found*; if *value-if-not-found* is not specified, the value of *variable* is not changed. Calls `AC_SUBST` for *variable*.

In the future, when cross-compiling this macro will *not* accept program names that are not prefixed with the host type.

`AC_PATH_PROG` (*variable*, *prog-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like `AC_CHECK_PROG`, but set *variable* to the absolute name of *prog-to-check-for* if found.

`AC_PATH_PROGS` (*variable*, *progs-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like `AC_CHECK_PROGS`, but if any of *progs-to-check-for* are found, set *variable* to the absolute name of the program found.

`AC_PATH_TARGET_TOOL` (*variable*, *prog-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like `AC_CHECK_TARGET_TOOL`, but set *variable* to the absolute name of the program if it is found.

`AC_PATH_TOOL` (*variable*, *prog-to-check-for*, [*value-if-not-found*], [*path*]) [Macro]

Like `AC_CHECK_TOOL`, but set *variable* to the absolute name of the program if it is found.

In the future, when cross-compiling this macro will *not* accept program names that are not prefixed with the host type.

5.3 Files

You might also need to check for the existence of files. Before using these macros, ask yourself whether a runtime test might not be a better solution. Be aware that, like most Autoconf macros, they test a feature of the host machine, and therefore, they die when cross-compiling.

`AC_CHECK_FILE` (*file*, [*action-if-found*], [*action-if-not-found*]) [Macro]

Check whether file *file* exists on the native system. If it is found, execute *action-if-found*, otherwise do *action-if-not-found*, if given.

AC_CHECK_FILES (*files*, [*action-if-found*], [*action-if-not-found*]) [Macro]
Executes AC_CHECK_FILE once for each file listed in *files*. Additionally, defines '`HAVE_file`' (see Section 5.1.1 [Standard Symbols], page 39) for each file found.

5.4 Library Files

The following macros check for the presence of certain C, C++, or Fortran library archive files.

AC_CHECK_LIB (*library*, *function*, [*action-if-found*], [*action-if-not-found*], [*other-libraries*]) [Macro]
Test whether the library *library* is available by trying to link a test program that calls function *function* with the library. *function* should be a function provided by the library. Use the base name of the library; e.g., to check for '`-lmp`', use '`mp`' as the *library* argument.

action-if-found is a list of shell commands to run if the link with the library succeeds; *action-if-not-found* is a list of shell commands to run if the link fails. If *action-if-found* is not specified, the default action prepends '`-llibrary`' to LIBS and defines '`HAVE_LIBlibrary`' (in all capitals). This macro is intended to support building LIBS in a right-to-left (least-dependent to most-dependent) fashion such that library dependencies are satisfied as a natural side effect of consecutive tests. Linkers are sensitive to library ordering so the order in which LIBS is generated is important to reliable detection of libraries.

If linking with *library* results in unresolved symbols that would be resolved by linking with additional libraries, give those libraries as the *other-libraries* argument, separated by spaces: e.g., '`-lXt -lX11`'. Otherwise, this macro fails to detect that *library* is present, because linking the test program always fails with unresolved symbols. The *other-libraries* argument should be limited to cases where it is desirable to test for one library in the presence of another that is not already in LIBS.

AC_CHECK_LIB requires some care in usage, and should be avoided in some common cases. Many standard functions like gethostbyname appear the standard C library on some hosts, and in special libraries like nsl on other hosts. On some hosts the special libraries contain variant implementations that you may not want to use. These days it is normally better to use `AC_SEARCH_LIBS([gethostbyname], [nsl])` instead of `AC_CHECK_LIB([nsl], [gethostbyname])`.

AC_SEARCH_LIBS (*function*, *search-libs*, [*action-if-found*], [*action-if-not-found*], [*other-libraries*]) [Macro]
Search for a library defining *function* if it's not already available. This equates to calling '`AC_LINK_IFELSE([AC_LANG_CALL([], [function])])`' first with no libraries, then for each library listed in *search-libs*.

Add '`-llibrary`' to LIBS for the first library found to contain *function*, and run *action-if-found*. If the function is not found, run *action-if-not-found*.

If linking with *library* results in unresolved symbols that would be resolved by linking with additional libraries, give those libraries as the *other-libraries* argument, separated by spaces: e.g., '`-lXt -lX11`'. Otherwise, this macro fails to detect that *function* is present, because linking the test program always fails with unresolved symbols.

5.5 Library Functions

The following macros check for particular C library functions. If there is no macro specifically defined to check for a function you need, and you don't need to check for any special properties of it, then you can use one of the general function-check macros.

5.5.1 Portability of C Functions

Most usual functions can either be missing, or be buggy, or be limited on some architectures. This section tries to make an inventory of these portability issues. By definition, this list always requires additions. Please help us keeping it as complete as possible.

`exit`
: On ancient hosts, `exit` returned `int`. This is because `exit` predates `void`, and there was a long tradition of it returning `int`.

  On current hosts, the problem more likely is that `exit` is not declared, due to C++ problems of some sort or another. For this reason we suggest that test programs not invoke `exit`, but return from `main` instead.

`free`
: The C standard says a call `free (NULL)` does nothing, but some old systems don't support this (e.g., NextStep).

`isinf`
`isnan`
: The C99 standard says that `isinf` and `isnan` are macros. On some systems just macros are available (e.g., HP-UX and Solaris 10), on some systems both macros and functions (e.g., glibc 2.3.2), and on some systems only functions (e.g., IRIX 6 and Solaris 9). In some cases these functions are declared in nonstandard headers like `<sunmath.h>` and defined in non-default libraries like '`-lm`' or '`-lsunmath`'.

  The C99 `isinf` and `isnan` macros work correctly with `long double` arguments, but pre-C99 systems that use functions typically assume `double` arguments. On such a system, `isinf` incorrectly returns true for a finite `long double` argument that is outside the range of `double`.

  To work around this porting mess, you can use code like the following.

```
#include <math.h>

#ifndef isnan
# define isnan(x) \
    (sizeof (x) == sizeof (long double) ? isnan_ld (x) \
     : sizeof (x) == sizeof (double) ? isnan_d (x) \
     : isnan_f (x))
static inline int isnan_f  (float       x) { return x != x; }
static inline int isnan_d  (double      x) { return x != x; }
static inline int isnan_ld (long double x) { return x != x; }
#endif

#ifndef isinf
# define isinf(x) \
    (sizeof (x) == sizeof (long double) ? isinf_ld (x) \
     : sizeof (x) == sizeof (double) ? isinf_d (x) \
     : isinf_f (x))
static inline int isinf_f  (float       x) { return isnan (x - x); }
static inline int isinf_d  (double      x) { return isnan (x - x); }
static inline int isinf_ld (long double x) { return isnan (x - x); }
```

```
#endif
```

Use `AC_C_INLINE` (see Section 5.10.3 [C Compiler], page 72) so that this code works on compilers that lack the `inline` keyword. Some optimizing compilers mishandle these definitions, but systems with that bug typically have missing or broken `isnan` functions anyway, so it's probably not worth worrying about.

`malloc` The C standard says a call `malloc (0)` is implementation dependent. It may either return `NULL` (e.g., OSF 4) or non-`NULL` (e.g., GNU C Library). `AC_FUNC_MALLOC` can be used to insist on non-`NULL` (see Section 5.5.2 [Particular Functions], page 50).

`putenv` Posix prefers `setenv` to `putenv`; among other things, `putenv` is not required of all Posix implementations, but `setenv` is.

Posix specifies that `putenv` puts the given string directly in `environ`, but some systems make a copy of it instead (e.g., glibc 2.0, or BSD). And when a copy is made, `unsetenv` might not free it, causing a memory leak (e.g., FreeBSD 4).

On some systems `putenv ("FOO")` removes '`FOO`' from the environment, but this is not standard usage and it dumps core on some systems (e.g., AIX).

On MinGW, a call `putenv ("FOO=")` removes '`FOO`' from the environment, rather than inserting it with an empty value.

`realloc` The C standard says a call `realloc (NULL, size)` is equivalent to `malloc (size)`, but some old systems don't support this (e.g., NextStep).

`signal` handler

Normally `signal` takes a handler function with a return type of `void`, but some old systems required `int` instead. Any actual `int` value returned is not used; this is only a difference in the function prototype demanded.

All systems we know of in current use return `void`. The `int` was to support K&R C, where of course `void` is not available. `AC_TYPE_SIGNAL` (see Section 5.9.1 [Particular Types], page 68) can be used to establish the correct type in all cases.

`snprintf` The C99 standard says that if the output array isn't big enough and if no other errors occur, `snprintf` and `vsnprintf` truncate the output and return the number of bytes that ought to have been produced. Some older systems return the truncated length (e.g., GNU C Library 2.0.x or IRIX 6.5), some a negative value (e.g., earlier GNU C Library versions), and some the buffer length without truncation (e.g., 32-bit Solaris 7). Also, some buggy older systems ignore the length and overrun the buffer (e.g., 64-bit Solaris 7).

`sprintf` The C standard says `sprintf` and `vsprintf` return the number of bytes written. On some ancient systems (SunOS 4 for instance) they return the buffer pointer instead, but these no longer need to be worried about.

`sscanf` On various old systems, e.g., HP-UX 9, `sscanf` requires that its input string be writable (though it doesn't actually change it). This can be a problem when using `gcc` since it normally puts constant strings in read-only memory (see section "Incompatibilities" in *Using and Porting the GNU Compiler Collection*). Apparently in some cases even having format strings read-only can be a problem.

`strerror_r`
: Posix specifies that `strerror_r` returns an `int`, but many systems (e.g., GNU C Library version 2.2.4) provide a different version returning a `char *`. `AC_FUNC_STRERROR_R` can detect which is in use (see Section 5.5.2 [Particular Functions], page 50).

`strnlen`
: AIX 4.3 provides a broken version which produces the following results:

```
strnlen ("foobar", 0) = 0
strnlen ("foobar", 1) = 3
strnlen ("foobar", 2) = 2
strnlen ("foobar", 3) = 1
strnlen ("foobar", 4) = 0
strnlen ("foobar", 5) = 6
strnlen ("foobar", 6) = 6
strnlen ("foobar", 7) = 6
strnlen ("foobar", 8) = 6
strnlen ("foobar", 9) = 6
```

`sysconf`
: `_SC_PAGESIZE` is standard, but some older systems (e.g., HP-UX 9) have `_SC_PAGE_SIZE` instead. This can be tested with `#ifdef`.

`unlink`
: The Posix spec says that `unlink` causes the given file to be removed only after there are no more open file handles for it. Some non-Posix hosts have trouble with this requirement, though, and some DOS variants even corrupt the file system.

`unsetenv`
: On MinGW, `unsetenv` is not available, but a variable '`FOO`' can be removed with a call `putenv ("FOO=")`, as described under `putenv` above.

`va_copy`
: The C99 standard provides `va_copy` for copying `va_list` variables. It may be available in older environments too, though possibly as `__va_copy` (e.g., `gcc` in strict pre-C99 mode). These can be tested with `#ifdef`. A fallback to `memcpy (&dst, &src, sizeof (va_list))` gives maximum portability.

`va_list`
: `va_list` is not necessarily just a pointer. It can be a `struct` (e.g., `gcc` on Alpha), which means `NULL` is not portable. Or it can be an array (e.g., `gcc` in some PowerPC configurations), which means as a function parameter it can be effectively call-by-reference and library routines might modify the value back in the caller (e.g., `vsnprintf` in the GNU C Library 2.1).

Signed `>>`
: Normally the C `>>` right shift of a signed type replicates the high bit, giving a so-called "arithmetic" shift. But care should be taken since Standard C doesn't require that behavior. On those few processors without a native arithmetic shift (for instance Cray vector systems) zero bits may be shifted in, the same as a shift of an unsigned type.

Integer `/`
: C divides signed integers by truncating their quotient toward zero, yielding the same result as Fortran. However, before C99 the standard allowed C implementations to take the floor or ceiling of the quotient in some cases. Hardly any implementations took advantage of this freedom, though, and it's probably not worth worrying about this issue nowadays.

5.5.2 Particular Function Checks

These macros check for particular C functions—whether they exist, and in some cases how they respond when given certain arguments.

`AC_FUNC_ALLOCA` [Macro]

Check how to get `alloca`. Tries to get a builtin version by checking for '`alloca.h`' or the predefined C preprocessor macros `__GNUC__` and `_AIX`. If this macro finds '`alloca.h`', it defines `HAVE_ALLOCA_H`.

If those attempts fail, it looks for the function in the standard C library. If any of those methods succeed, it defines `HAVE_ALLOCA`. Otherwise, it sets the output variable `ALLOCA` to '`${LIBOBJDIR}alloca.o`' and defines `C_ALLOCA` (so programs can periodically call '`alloca (0)`' to garbage collect). This variable is separate from `LIBOBJS` so multiple programs can share the value of `ALLOCA` without needing to create an actual library, in case only some of them use the code in `LIBOBJS`. The '`${LIBOBJDIR}`' prefix serves the same purpose as in `LIBOBJS` (see Section 17.6.4 [AC_LIBOBJ vs LIBOBJS], page 226).

This macro does not try to get `alloca` from the System V R3 '`libPW`' or the System V R4 '`libucb`' because those libraries contain some incompatible functions that cause trouble. Some versions do not even contain `alloca` or contain a buggy version. If you still want to use their `alloca`, use `ar` to extract '`alloca.o`' from them instead of compiling '`alloca.c`'.

Source files that use `alloca` should start with a piece of code like the following, to declare it properly.

```
#if HAVE_ALLOCA_H
# include <alloca.h>
#elif defined __GNUC__
# define alloca __builtin_alloca
#elif defined _AIX
# define alloca __alloca
#elif defined _MSC_VER
# include <malloc.h>
# define alloca _alloca
#else
# include <stddef.h>
# ifdef  __cplusplus
extern "C"
# endif
void *alloca (size_t);
#endif
```

`AC_FUNC_CHOWN` [Macro]

If the `chown` function is available and works (in particular, it should accept '`-1`' for `uid` and `gid`), define `HAVE_CHOWN`.

`AC_FUNC_CLOSEDIR_VOID` [Macro]

If the `closedir` function does not return a meaningful value, define `CLOSEDIR_VOID`. Otherwise, callers ought to check its return value for an error indicator.

Currently this test is implemented by running a test program. When cross compiling the pessimistic assumption that `closedir` does not return a meaningful value is made.

This macro is obsolescent, as `closedir` returns a meaningful value on current systems. New programs need not use this macro.

`AC_FUNC_ERROR_AT_LINE` [Macro]

If the `error_at_line` function is not found, require an `AC_LIBOBJ` replacement of '`error`'.

`AC_FUNC_FNMATCH` [Macro]

If the `fnmatch` function conforms to Posix, define `HAVE_FNMATCH`. Detect common implementation bugs, for example, the bugs in Solaris 2.4.

Unlike the other specific `AC_FUNC` macros, `AC_FUNC_FNMATCH` does not replace a broken/missing `fnmatch`. This is for historical reasons. See `AC_REPLACE_FNMATCH` below.

`AC_FUNC_FNMATCH_GNU` [Macro]

Behave like `AC_REPLACE_FNMATCH` (*replace*) but also test whether `fnmatch` supports GNU extensions. Detect common implementation bugs, for example, the bugs in the GNU C Library 2.1.

`AC_FUNC_FORK` [Macro]

This macro checks for the `fork` and `vfork` functions. If a working `fork` is found, define `HAVE_WORKING_FORK`. This macro checks whether `fork` is just a stub by trying to run it.

If '`vfork.h`' is found, define `HAVE_VFORK_H`. If a working `vfork` is found, define `HAVE_WORKING_VFORK`. Otherwise, define `vfork` to be `fork` for backward compatibility with previous versions of `autoconf`. This macro checks for several known errors in implementations of `vfork` and considers the system to not have a working `vfork` if it detects any of them. It is not considered to be an implementation error if a child's invocation of `signal` modifies the parent's signal handler, since child processes rarely change their signal handlers.

Since this macro defines `vfork` only for backward compatibility with previous versions of `autoconf` you're encouraged to define it yourself in new code:

```
#if !HAVE_WORKING_VFORK
# define vfork fork
#endif
```

`AC_FUNC_FSEEKO` [Macro]

If the `fseeko` function is available, define `HAVE_FSEEKO`. Define `_LARGEFILE_SOURCE` if necessary to make the prototype visible on some systems (e.g., glibc 2.2). Otherwise linkage problems may occur when compiling with `AC_SYS_LARGEFILE` on largefile-sensitive systems where `off_t` does not default to a 64bit entity.

`AC_FUNC_GETGROUPS` [Macro]

If the `getgroups` function is available and works (unlike on Ultrix 4.3, where '`getgroups (0, 0)`' always fails), define `HAVE_GETGROUPS`. Set `GETGROUPS_LIBS` to any libraries needed to get that function. This macro runs `AC_TYPE_GETGROUPS`.

AC_FUNC_GETLOADAVG [Macro]

Check how to get the system load averages. To perform its tests properly, this macro needs the file 'getloadavg.c'; therefore, be sure to set the AC_LIBOBJ replacement directory properly (see Section 5.5.3 [Generic Functions], page 56, AC_CONFIG_LIBOBJ_DIR).

If the system has the getloadavg function, define HAVE_GETLOADAVG, and set GETLOADAVG_LIBS to any libraries necessary to get that function. Also add GETLOADAVG_LIBS to LIBS. Otherwise, require an AC_LIBOBJ replacement for 'getloadavg' with source code in '*dir*/getloadavg.c', and possibly define several other C preprocessor macros and output variables:

1. Define C_GETLOADAVG.
2. Define SVR4, DGUX, UMAX, or UMAX4_3 if on those systems.
3. If 'nlist.h' is found, define HAVE_NLIST_H.
4. If 'struct nlist' has an 'n_un.n_name' member, define HAVE_STRUCT_NLIST_N_UN_N_NAME. The obsolete symbol NLIST_NAME_UNION is still defined, but do not depend upon it.
5. Programs may need to be installed set-group-ID (or set-user-ID) for getloadavg to work. In this case, define GETLOADAVG_PRIVILEGED, set the output variable NEED_SETGID to 'true' (and otherwise to 'false'), and set KMEM_GROUP to the name of the group that should own the installed program.

AC_FUNC_GETMNTENT [Macro]

Check for getmntent in the standard C library, and then in the 'sun', 'seq', and 'gen' libraries, for UNICOS, IRIX 4, PTX, and UnixWare, respectively. Then, if getmntent is available, define HAVE_GETMNTENT.

AC_FUNC_GETPGRP [Macro]

Define GETPGRP_VOID if it is an error to pass 0 to getpgrp; this is the Posix behavior. On older BSD systems, you must pass 0 to getpgrp, as it takes an argument and behaves like Posix's getpgid.

```
#if GETPGRP_VOID
  pid = getpgrp ();
#else
  pid = getpgrp (0);
#endif
```

This macro does not check whether getpgrp exists at all; if you need to work in that situation, first call AC_CHECK_FUNC for getpgrp.

This macro is obsolescent, as current systems have a getpgrp whose signature conforms to Posix. New programs need not use this macro.

AC_FUNC_LSTAT_FOLLOWS_SLASHED_SYMLINK [Macro]

If 'link' is a symbolic link, then lstat should treat 'link/' the same as 'link/.'. However, many older lstat implementations incorrectly ignore trailing slashes.

It is safe to assume that if lstat incorrectly ignores trailing slashes, then other symbolic-link-aware functions like unlink also incorrectly ignore trailing slashes.

If `lstat` behaves properly, define `LSTAT_FOLLOWS_SLASHED_SYMLINK`, otherwise require an `AC_LIBOBJ` replacement of `lstat`.

`AC_FUNC_MALLOC` [Macro]

If the `malloc` function is compatible with the GNU C library `malloc` (i.e., '`malloc (0)`' returns a valid pointer), define `HAVE_MALLOC` to 1. Otherwise define `HAVE_MALLOC` to 0, ask for an `AC_LIBOBJ` replacement for '`malloc`', and define `malloc` to `rpl_malloc` so that the native `malloc` is not used in the main project.

Typically, the replacement file '`malloc.c`' should look like (note the '`#undef malloc`'):

```
#if HAVE_CONFIG_H
# include <config.h>
#endif
#undef malloc

#include <sys/types.h>

void *malloc ();

/* Allocate an N-byte block of memory from the heap.
   If N is zero, allocate a 1-byte block.  */

void *
rpl_malloc (size_t n)
{
  if (n == 0)
    n = 1;
  return malloc (n);
}
```

`AC_FUNC_MEMCMP` [Macro]

If the `memcmp` function is not available, or does not work on 8-bit data (like the one on SunOS 4.1.3), or fails when comparing 16 bytes or more and with at least one buffer not starting on a 4-byte boundary (such as the one on NeXT x86 OpenStep), require an `AC_LIBOBJ` replacement for '`memcmp`'.

This macro is obsolescent, as current systems have a working `memcmp`. New programs need not use this macro.

`AC_FUNC_MBRTOWC` [Macro]

Define `HAVE_MBRTOWC` to 1 if the function `mbrtowc` and the type `mbstate_t` are properly declared.

`AC_FUNC_MKTIME` [Macro]

If the `mktime` function is not available, or does not work correctly, require an `AC_LIBOBJ` replacement for '`mktime`'. For the purposes of this test, `mktime` should conform to the Posix standard and should be the inverse of `localtime`.

`AC_FUNC_MMAP` [Macro]

If the `mmap` function exists and works correctly, define `HAVE_MMAP`. This checks only private fixed mapping of already-mapped memory.

AC_FUNC_OBSTACK [Macro]

If the obstacks are found, define HAVE_OBSTACK, else require an AC_LIBOBJ replacement for 'obstack'.

AC_FUNC_REALLOC [Macro]

If the realloc function is compatible with the GNU C library realloc (i.e., 'realloc (NULL, 0)' returns a valid pointer), define HAVE_REALLOC to 1. Otherwise define HAVE_REALLOC to 0, ask for an AC_LIBOBJ replacement for 'realloc', and define realloc to rpl_realloc so that the native realloc is not used in the main project. See AC_FUNC_MALLOC for details.

AC_FUNC_SELECT_ARGTYPES [Macro]

Determines the correct type to be passed for each of the select function's arguments, and defines those types in SELECT_TYPE_ARG1, SELECT_TYPE_ARG234, and SELECT_TYPE_ARG5 respectively. SELECT_TYPE_ARG1 defaults to 'int', SELECT_TYPE_ARG234 defaults to 'int *', and SELECT_TYPE_ARG5 defaults to 'struct timeval *'.

This macro is obsolescent, as current systems have a select whose signature conforms to Posix. New programs need not use this macro.

AC_FUNC_SETPGRP [Macro]

If setpgrp takes no argument (the Posix version), define SETPGRP_VOID. Otherwise, it is the BSD version, which takes two process IDs as arguments. This macro does not check whether setpgrp exists at all; if you need to work in that situation, first call AC_CHECK_FUNC for setpgrp.

This macro is obsolescent, as current systems have a setpgrp whose signature conforms to Posix. New programs need not use this macro.

AC_FUNC_STAT [Macro]
AC_FUNC_LSTAT [Macro]

Determine whether stat or lstat have the bug that it succeeds when given the zero-length file name as argument. The stat and lstat from SunOS 4.1.4 and the Hurd (as of 1998-11-01) do this.

If it does, then define HAVE_STAT_EMPTY_STRING_BUG (or HAVE_LSTAT_EMPTY_STRING_BUG) and ask for an AC_LIBOBJ replacement of it.

These macros are obsolescent, as no current systems have the bug. New programs need not use these macros.

AC_FUNC_SETVBUF_REVERSED [Macro]

If setvbuf takes the buffering type as its second argument and the buffer pointer as the third, instead of the other way around, define SETVBUF_REVERSED.

This macro is obsolescent, as no current systems have the bug. New programs need not use this macro.

AC_FUNC_STRCOLL [Macro]

If the strcoll function exists and works correctly, define HAVE_STRCOLL. This does a bit more than 'AC_CHECK_FUNCS(strcoll)', because some systems have incorrect definitions of strcoll that should not be used.

`AC_FUNC_STRERROR_R` [Macro]

If `strerror_r` is available, define `HAVE_STRERROR_R`, and if it is declared, define `HAVE_DECL_STRERROR_R`. If it returns a `char *` message, define `STRERROR_R_CHAR_P`; otherwise it returns an `int` error number. The Thread-Safe Functions option of Posix requires `strerror_r` to return `int`, but many systems (including, for example, version 2.2.4 of the GNU C Library) return a `char *` value that is not necessarily equal to the buffer argument.

`AC_FUNC_STRFTIME` [Macro]

Check for `strftime` in the '`intl`' library, for SCO Unix. Then, if `strftime` is available, define `HAVE_STRFTIME`.

This macro is obsolescent, as no current systems require the '`intl`' library for `strftime`. New programs need not use this macro.

`AC_FUNC_STRTOD` [Macro]

If the `strtod` function does not exist or doesn't work correctly, ask for an `AC_LIBOBJ` replacement of '`strtod`'. In this case, because '`strtod.c`' is likely to need '`pow`', set the output variable `POW_LIB` to the extra library needed.

`AC_FUNC_STRTOLD` [Macro]

If the `strtold` function exists and conforms to C99, define `HAVE_STRTOLD`.

`AC_FUNC_STRNLEN` [Macro]

If the `strnlen` function is not available, or is buggy (like the one from AIX 4.3), require an `AC_LIBOBJ` replacement for it.

`AC_FUNC_UTIME_NULL` [Macro]

If '`utime (file, NULL)`' sets *file*'s timestamp to the present, define `HAVE_UTIME_NULL`.

This macro is obsolescent, as all current systems have a `utime` that behaves this way. New programs need not use this macro.

`AC_FUNC_VPRINTF` [Macro]

If `vprintf` is found, define `HAVE_VPRINTF`. Otherwise, if `_doprnt` is found, define `HAVE_DOPRNT`. (If `vprintf` is available, you may assume that `vfprintf` and `vsprintf` are also available.)

This macro is obsolescent, as all current systems have `vprintf`. New programs need not use this macro.

`AC_REPLACE_FNMATCH` [Macro]

If the `fnmatch` function does not conform to Posix (see `AC_FUNC_FNMATCH`), ask for its `AC_LIBOBJ` replacement.

The files '`fnmatch.c`', '`fnmatch_loop.c`', and '`fnmatch_.h`' in the `AC_LIBOBJ` replacement directory are assumed to contain a copy of the source code of GNU `fnmatch`. If necessary, this source code is compiled as an `AC_LIBOBJ` replacement, and the '`fnmatch_.h`' file is linked to '`fnmatch.h`' so that it can be included in place of the system `<fnmatch.h>`.

5.5.3 Generic Function Checks

These macros are used to find functions not covered by the "particular" test macros. If the functions might be in libraries other than the default C library, first call `AC_CHECK_LIB` for those libraries. If you need to check the behavior of a function as well as find out whether it is present, you have to write your own test for it (see Chapter 6 [Writing Tests], page 87).

`AC_CHECK_FUNC (`*`function`*`, [`*`action-if-found`*`], [`*`action-if-not-found`*`])` [Macro]

If C function *function* is available, run shell commands *action-if-found*, otherwise *action-if-not-found*. If you just want to define a symbol if the function is available, consider using `AC_CHECK_FUNCS` instead. This macro checks for functions with C linkage even when `AC_LANG(C++)` has been called, since C is more standardized than C++. (see Section 6.1 [Language Choice], page 87, for more information about selecting the language for checks.)

`AC_CHECK_FUNCS (`*`function...`*`, [`*`action-if-found`*`], [`*`action-if-not-found`*`])` [Macro]

For each *function* enumerated in the blank-or-newline-separated argument list, define `HAVE_`*`function`* (in all capitals) if it is available. If *action-if-found* is given, it is additional shell code to execute when one of the functions is found. You can give it a value of '`break`' to break out of the loop on the first match. If *action-if-not-found* is given, it is executed when one of the functions is not found.

`AC_CHECK_FUNCS_ONCE (`*`function...`*`)` [Macro]

For each *function* enumerated in the blank-or-newline-separated argument list, define `HAVE_`*`function`* (in all capitals) if it is available. This is a once-only variant of `AC_CHECK_FUNCS`. It generates the checking code at most once, so that `configure` is smaller and faster; but the checks cannot be conditionalized and are always done once, early during the `configure` run.

Autoconf follows a philosophy that was formed over the years by those who have struggled for portability: isolate the portability issues in specific files, and then program as if you were in a Posix environment. Some functions may be missing or unfixable, and your package must be ready to replace them.

Suitable replacements for many such problem functions are available from Gnulib (see Section 2.2 [Gnulib], page 3).

`AC_LIBOBJ (`*`function`*`)` [Macro]

Specify that '*`function`*`.c`' must be included in the executables to replace a missing or broken implementation of *function*.

Technically, it adds '*`function`*`.$ac_objext`' to the output variable `LIBOBJS` if it is not already in, and calls `AC_LIBSOURCE` for '*`function`*`.c`'. You should not directly change `LIBOBJS`, since this is not traceable.

`AC_LIBSOURCE (`*`file`*`)` [Macro]

Specify that *file* might be needed to compile the project. If you need to know what files might be needed by a '`configure.ac`', you should trace `AC_LIBSOURCE`. *file* must be a literal.

This macro is called automatically from `AC_LIBOBJ`, but you must call it explicitly if you pass a shell variable to `AC_LIBOBJ`. In that case, since shell variables cannot be traced statically, you must pass to `AC_LIBSOURCE` any possible files that the shell variable might cause `AC_LIBOBJ` to need. For example, if you want to pass a variable `$foo_or_bar` to `AC_LIBOBJ` that holds either `"foo"` or `"bar"`, you should do:

```
AC_LIBSOURCE([foo.c])
AC_LIBSOURCE([bar.c])
AC_LIBOBJ([$foo_or_bar])
```

There is usually a way to avoid this, however, and you are encouraged to simply call `AC_LIBOBJ` with literal arguments.

Note that this macro replaces the obsolete `AC_LIBOBJ_DECL`, with slightly different semantics: the old macro took the function name, e.g., `foo`, as its argument rather than the file name.

`AC_LIBSOURCES` (*files*) [Macro]

Like `AC_LIBSOURCE`, but accepts one or more *files* in a comma-separated M4 list. Thus, the above example might be rewritten:

```
AC_LIBSOURCES([foo.c, bar.c])
AC_LIBOBJ([$foo_or_bar])
```

`AC_CONFIG_LIBOBJ_DIR` (*directory*) [Macro]

Specify that `AC_LIBOBJ` replacement files are to be found in *directory*, a name relative to the top level of the source tree. The replacement directory defaults to '`.`', the top level directory, and the most typical value is '`lib`', corresponding to '`AC_CONFIG_LIBOBJ_DIR([lib])`'.

`configure` might need to know the replacement directory for the following reasons: (i) some checks use the replacement files, (ii) some macros bypass broken system headers by installing links to the replacement headers (iii) when used in conjunction with Automake, within each makefile, *directory* is used as a relative path from `$(top_srcdir)` to each object named in `LIBOBJS` and `LTLIBOBJS`, etc.

It is common to merely check for the existence of a function, and ask for its `AC_LIBOBJ` replacement if missing. The following macro is a convenient shorthand.

`AC_REPLACE_FUNCS` (*function...*) [Macro]

Like `AC_CHECK_FUNCS`, but uses '`AC_LIBOBJ(`*function*`)`' as *action-if-not-found*. You can declare your replacement function by enclosing the prototype in '`#if !HAVE_`*function*'. If the system has the function, it probably declares it in a header file you should be including, so you shouldn't redeclare it lest your declaration conflict.

5.6 Header Files

The following macros check for the presence of certain C header files. If there is no macro specifically defined to check for a header file you need, and you don't need to check for any special properties of it, then you can use one of the general header-file check macros.

5.6.1 Portability of Headers

This section tries to collect knowledge about common headers, and the problems they cause. By definition, this list always requires additions. Please help us keeping it as complete as possible.

‘`limits.h`’
: C99 says that ‘`limits.h`’ defines `LLONG_MIN`, `LLONG_MAX`, and `ULLONG_MAX`, but many almost-C99 environments (e.g., default GCC 4.0.2 + glibc 2.4) do not define them.

‘`inttypes.h`’ vs. ‘`stdint.h`’
: The C99 standard says that ‘`inttypes.h`’ includes ‘`stdint.h`’, so there’s no need to include ‘`stdint.h`’ separately in a standard environment. Some implementations have ‘`inttypes.h`’ but not ‘`stdint.h`’ (e.g., Solaris 7), but we don’t know of any implementation that has ‘`stdint.h`’ but not ‘`inttypes.h`’.

‘`linux/irda.h`’
: It requires ‘`linux/types.h`’ and ‘`sys/socket.h`’.

‘`linux/random.h`’
: It requires ‘`linux/types.h`’.

‘`net/if.h`’
: On Darwin, this file requires that ‘`sys/socket.h`’ be included beforehand. One should run:

```
AC_CHECK_HEADERS([sys/socket.h])
AC_CHECK_HEADERS([net/if.h], [], [],
[#include <stdio.h>
#if STDC_HEADERS
# include <stdlib.h>
# include <stddef.h>
#else
# if HAVE_STDLIB_H
#  include <stdlib.h>
# endif
#endif
#if HAVE_SYS_SOCKET_H
# include <sys/socket.h>
#endif
])
```

‘`netinet/if_ether.h`’
: On Darwin, this file requires that ‘`stdio.h`’ and ‘`sys/socket.h`’ be included beforehand. One should run:

```
AC_CHECK_HEADERS([sys/socket.h])
AC_CHECK_HEADERS([netinet/if_ether.h], [], [],
[#include <stdio.h>
#if STDC_HEADERS
# include <stdlib.h>
```

```
# include <stddef.h>
#else
# if HAVE_STDLIB_H
#  include <stdlib.h>
# endif
#endif
#if HAVE_SYS_SOCKET_H
# include <sys/socket.h>
#endif
])
```

‘stdint.h’
: See above, item ‘inttypes.h’ vs. ‘stdint.h’.

‘stdlib.h’
: On many systems (e.g., Darwin), ‘stdio.h’ is a prerequisite.

‘sys/mount.h’
: On FreeBSD 4.8 on ia32 and using gcc version 2.95.4, ‘sys/params.h’ is a prerequisite.

‘sys/ptem.h’
: On Solaris 8, ‘sys/stream.h’ is a prerequisite.

‘sys/socket.h’
: On Darwin, ‘stdlib.h’ is a prerequisite.

‘sys/ucred.h’
: On HP Tru64 5.1, ‘sys/types.h’ is a prerequisite.

‘X11/extensions/scrnsaver.h’
: Using XFree86, this header requires ‘X11/Xlib.h’, which is probably so required that you might not even consider looking for it.

```
AC_CHECK_HEADERS([X11/extensions/scrnsaver.h], [], [],
[[#include <X11/Xlib.h>
]])
```

5.6.2 Particular Header Checks

These macros check for particular system header files—whether they exist, and in some cases whether they declare certain symbols.

AC_HEADER_ASSERT [Macro]
: Check whether to enable assertions in the style of ‘assert.h’. Assertions are enabled by default, but the user can override this by invoking `configure` with the ‘--disable-assert’ option.

AC_HEADER_DIRENT [Macro]
: Check for the following header files. For the first one that is found and defines ‘DIR’, define the listed C preprocessor macro:

‘dirent.h’	HAVE_DIRENT_H
‘sys/ndir.h’	HAVE_SYS_NDIR_H

‘sys/dir.h’ HAVE_SYS_DIR_H
‘ndir.h’ HAVE_NDIR_H

The directory-library declarations in your source code should look something like the following:

```
#include <sys/types.h>
#ifdef HAVE_DIRENT_H
# include <dirent.h>
# define NAMLEN(dirent) strlen ((dirent)->d_name)
#else
# define dirent direct
# define NAMLEN(dirent) ((dirent)->d_namlen)
# if HAVE_SYS_NDIR_H
#  include <sys/ndir.h>
# endif
# if HAVE_SYS_DIR_H
#  include <sys/dir.h>
# endif
# if HAVE_NDIR_H
#  include <ndir.h>
# endif
#endif
```

Using the above declarations, the program would declare variables to be of type `struct dirent`, not `struct direct`, and would access the length of a directory entry name by passing a pointer to a `struct dirent` to the `NAMLEN` macro.

This macro also checks for the SCO Xenix ‘`dir`’ and ‘`x`’ libraries.

This macro is obsolescent, as all current systems with directory libraries have `<dirent.h>`. New programs need not use this macro.

Also see `AC_STRUCT_DIRENT_D_INO` and `AC_STRUCT_DIRENT_D_TYPE` (see Section 5.8.1 [Particular Structures], page 66).

`AC_HEADER_MAJOR` [Macro]

If ‘`sys/types.h`’ does not define `major`, `minor`, and `makedev`, but ‘`sys/mkdev.h`’ does, define `MAJOR_IN_MKDEV`; otherwise, if ‘`sys/sysmacros.h`’ does, define `MAJOR_IN_SYSMACROS`.

`AC_HEADER_RESOLV` [Macro]

Checks for header ‘`resolv.h`’, checking for prerequisites first. To properly use ‘`resolv.h`’, your code should contain something like the following:

```
#if HAVE_SYS_TYPES_H
#  include <sys/types.h>
#endif
#ifdef HAVE_NETINET_IN_H
#  include <netinet/in.h>   /* inet_ functions / structs */
#endif
#ifdef HAVE_ARPA_NAMESER_H
#  include <arpa/nameser.h> /* DNS HEADER struct */
```

```
#endif
#ifdef HAVE_NETDB_H
#  include <netdb.h>
#endif
#include <resolv.h>
```

AC_HEADER_STAT [Macro]

If the macros `S_ISDIR`, `S_ISREG`, etc. defined in '`sys/stat.h`' do not work properly (returning false positives), define `STAT_MACROS_BROKEN`. This is the case on Tektronix UTekV, Amdahl UTS and Motorola System V/88.

This macro is obsolescent, as no current systems have the bug. New programs need not use this macro.

AC_HEADER_STDBOOL [Macro]

If '`stdbool.h`' exists and conforms to C99, define `HAVE_STDBOOL_H` to 1; if the type `_Bool` is defined, define `HAVE__BOOL` to 1. To fulfill the C99 requirements, your '`system.h`' could contain the following code:

```
#if HAVE_STDBOOL_H
# include <stdbool.h>
#else
# if ! HAVE__BOOL
#  ifdef __cplusplus
typedef bool _Bool;
#  else
#   define _Bool signed char
#  endif
# endif
# define bool _Bool
# define false 0
# define true 1
# define __bool_true_false_are_defined 1
#endif
```

Alternatively you can use the '`stdbool`' package of Gnulib (see Section 2.2 [Gnulib], page 3); it packages the above code into a replacement header and contains a few other bells and whistles.

AC_HEADER_STDC [Macro]

Define `STDC_HEADERS` if the system has C header files conforming to ANSI C89 (ISO C90). Specifically, this macro checks for '`stdlib.h`', '`stdarg.h`', '`string.h`', and '`float.h`'; if the system has those, it probably has the rest of the C89 header files. This macro also checks whether '`string.h`' declares `memchr` (and thus presumably the other `mem` functions), whether '`stdlib.h`' declare `free` (and thus presumably `malloc` and other related functions), and whether the '`ctype.h`' macros work on characters with the high bit set, as the C standard requires.

If you use this macro, your code can refer to `STDC_HEADERS` to determine whether the system has conforming header files (and probably C library functions).

This macro is obsolescent, as current systems have conforming header files. New programs need not use this macro.

Nowadays '`string.h`' is part of the C standard and declares functions like `strcpy`, and '`strings.h`' is standardized by Posix and declares BSD functions like `bcopy`; but historically, string functions were a major sticking point in this area. If you still want to worry about portability to ancient systems without standard headers, there is so much variation that it is probably easier to declare the functions you use than to figure out exactly what the system header files declare. Some ancient systems contained a mix of functions from the C standard and from BSD; some were mostly standard but lacked '`memmove`'; some defined the BSD functions as macros in '`string.h`' or '`strings.h`'; some had only the BSD functions but '`string.h`'; some declared the memory functions in '`memory.h`', some in '`string.h`'; etc. It is probably sufficient to check for one string function and one memory function; if the library had the standard versions of those then it probably had most of the others. If you put the following in '`configure.ac`':

```
# This example is obsolescent.
# Nowadays you can omit these macro calls.
AC_HEADER_STDC
AC_CHECK_FUNCS([strchr memcpy])
```

then, in your code, you can use declarations like this:

```
/* This example is obsolescent.
   Nowadays you can just #include <string.h>.  */
#if STDC_HEADERS
# include <string.h>
#else
# if !HAVE_STRCHR
#  define strchr index
#  define strrchr rindex
# endif
char *strchr (), *strrchr ();
# if !HAVE_MEMCPY
#  define memcpy(d, s, n) bcopy ((s), (d), (n))
#  define memmove(d, s, n) bcopy ((s), (d), (n))
# endif
#endif
```

If you use a function like `memchr`, `memset`, `strtok`, or `strspn`, which have no BSD equivalent, then macros don't suffice to port to ancient hosts; you must provide an implementation of each function. An easy way to incorporate your implementations only when needed (since the ones in system C libraries may be hand optimized) is to, taking `memchr` for example, put it in '`memchr.c`' and use '`AC_REPLACE_FUNCS([memchr])`'.

`AC_HEADER_SYS_WAIT` [Macro]

If '`sys/wait.h`' exists and is compatible with Posix, define `HAVE_SYS_WAIT_H`. Incompatibility can occur if '`sys/wait.h`' does not exist, or if it uses the old BSD `union wait` instead of `int` to store a status value. If '`sys/wait.h`' is not Posix compatible,

then instead of including it, define the Posix macros with their usual interpretations. Here is an example:

```
#include <sys/types.h>
#if HAVE_SYS_WAIT_H
# include <sys/wait.h>
#endif
#ifndef WEXITSTATUS
# define WEXITSTATUS(stat_val) ((unsigned int) (stat_val) >> 8)
#endif
#ifndef WIFEXITED
# define WIFEXITED(stat_val) (((stat_val) & 255) == 0)
#endif
```

This macro is obsolescent, as current systems are compatible with Posix. New programs need not use this macro.

`_POSIX_VERSION` is defined when '`unistd.h`' is included on Posix systems. If there is no '`unistd.h`', it is definitely not a Posix system. However, some non-Posix systems do have '`unistd.h`'.

The way to check whether the system supports Posix is:

```
#if HAVE_UNISTD_H
# include <sys/types.h>
# include <unistd.h>
#endif

#ifdef _POSIX_VERSION
/* Code for Posix systems.  */
#endif
```

`AC_HEADER_TIME` [Macro]

If a program may include both '`time.h`' and '`sys/time.h`', define `TIME_WITH_SYS_TIME`. On some ancient systems, '`sys/time.h`' included '`time.h`', but '`time.h`' was not protected against multiple inclusion, so programs could not explicitly include both files. This macro is useful in programs that use, for example, `struct timeval` as well as `struct tm`. It is best used in conjunction with `HAVE_SYS_TIME_H`, which can be checked for using `AC_CHECK_HEADERS([sys/time.h])`.

```
#if TIME_WITH_SYS_TIME
# include <sys/time.h>
# include <time.h>
#else
# if HAVE_SYS_TIME_H
#  include <sys/time.h>
# else
#  include <time.h>
# endif
#endif
```

This macro is obsolescent, as current systems can include both files when they exist. New programs need not use this macro.

`AC_HEADER_TIOCGWINSZ` [Macro]

If the use of `TIOCGWINSZ` requires '`<sys/ioctl.h>`', then define `GWINSZ_IN_SYS_IOCTL`. Otherwise `TIOCGWINSZ` can be found in '`<termios.h>`'.

Use:

```
#if HAVE_TERMIOS_H
# include <termios.h>
#endif

#if GWINSZ_IN_SYS_IOCTL
# include <sys/ioctl.h>
#endif
```

5.6.3 Generic Header Checks

These macros are used to find system header files not covered by the "particular" test macros. If you need to check the contents of a header as well as find out whether it is present, you have to write your own test for it (see Chapter 6 [Writing Tests], page 87).

`AC_CHECK_HEADER (`*header-file*, [*action-if-found*], [*action-if-not-found*], [*includes* = '`default-includes`'])` [Macro]

If the system header file *header-file* is compilable, execute shell commands *action-if-found*, otherwise execute *action-if-not-found*. If you just want to define a symbol if the header file is available, consider using `AC_CHECK_HEADERS` instead.

For compatibility issues with older versions of Autoconf, please read below.

`AC_CHECK_HEADERS (`*header-file*..., [*action-if-found*], [*action-if-not-found*], [*includes* = '`default-includes`'])` [Macro]

For each given system header file *header-file* in the blank-separated argument list that exists, define `HAVE_`*header-file* (in all capitals). If *action-if-found* is given, it is additional shell code to execute when one of the header files is found. You can give it a value of '`break`' to break out of the loop on the first match. If *action-if-not-found* is given, it is executed when one of the header files is not found.

For compatibility issues with older versions of Autoconf, please read below.

Previous versions of Autoconf merely checked whether the header was accepted by the preprocessor. This was changed because the old test was inappropriate for typical uses. Headers are typically used to compile, not merely to preprocess, and the old behavior sometimes accepted headers that clashed at compile-time. If you need to check whether a header is preprocessable, you can use `AC_PREPROC_IFELSE` (see Section 6.3 [Running the Preprocessor], page 92).

This scheme, which improves the robustness of the test, also requires that you make sure that headers that must be included before the *header-file* be part of the *includes*, (see Section 5.1.2 [Default Includes], page 39). If looking for '`bar.h`', which requires that '`foo.h`' be included before if it exists, we suggest the following scheme:

```
AC_CHECK_HEADERS([foo.h])
AC_CHECK_HEADERS([bar.h], [], [],
[#if HAVE_FOO_H
```

```
# include <foo.h>
# endif
])
```

The following variant generates smaller, faster `configure` files if you do not need the full power of `AC_CHECK_HEADERS`.

`AC_CHECK_HEADERS_ONCE (`*`header-file...`*`)` [Macro]

For each given system header file *header-file* in the blank-separated argument list that exists, define `HAVE_`*`header-file`* (in all capitals). This is a once-only variant of `AC_CHECK_HEADERS`. It generates the checking code at most once, so that `configure` is smaller and faster; but the checks cannot be conditionalized and are always done once, early during the `configure` run.

5.7 Declarations

The following macros check for the declaration of variables and functions. If there is no macro specifically defined to check for a symbol you need, then you can use the general macros (see Section 5.7.2 [Generic Declarations], page 65) or, for more complex tests, you may use `AC_COMPILE_IFELSE` (see Section 6.4 [Running the Compiler], page 93).

5.7.1 Particular Declaration Checks

There are no specific macros for declarations.

5.7.2 Generic Declaration Checks

These macros are used to find declarations not covered by the "particular" test macros.

`AC_CHECK_DECL (`*`symbol`*`, [`*`action-if-found`*`], [`*`action-if-not-found`*`],` [Macro]
`[`*`includes`*` = 'default-includes'])`

If *symbol* (a function or a variable) is not declared in *includes* and a declaration is needed, run the shell commands *action-if-not-found*, otherwise *action-if-found*. If no *includes* are specified, the default includes are used (see Section 5.1.2 [Default Includes], page 39).

This macro actually tests whether it is valid to use *symbol* as an r-value, not if it is really declared, because it is much safer to avoid introducing extra declarations when they are not needed.

`AC_CHECK_DECLS (`*`symbols`*`, [`*`action-if-found`*`],` [Macro]
`[`*`action-if-not-found`*`], [`*`includes`*` = 'default-includes'])`

For each of the *symbols* (*comma*-separated list), define `HAVE_DECL_`*`symbol`* (in all capitals) to '`1`' if *symbol* is declared, otherwise to '`0`'. If *action-if-not-found* is given, it is additional shell code to execute when one of the function declarations is needed, otherwise *action-if-found* is executed.

This macro uses an M4 list as first argument:

```
AC_CHECK_DECLS([strdup])
AC_CHECK_DECLS([strlen])
AC_CHECK_DECLS([malloc, realloc, calloc, free])
```

Unlike the other '`AC_CHECK_*S`' macros, when a *symbol* is not declared, `HAVE_DECL_`*`symbol`* is defined to '`0`' instead of leaving `HAVE_DECL_`*`symbol`* undeclared. When you are *sure* that the check was performed, use `HAVE_DECL_`*`symbol`* just like any other result of Autoconf:

```
#if !HAVE_DECL_SYMBOL
extern char *symbol;
#endif
```

If the test may have not been performed, however, because it is safer *not* to declare a symbol than to use a declaration that conflicts with the system's one, you should use:

```
#if defined HAVE_DECL_MALLOC && !HAVE_DECL_MALLOC
void *malloc (size_t *s);
#endif
```

You fall into the second category only in extreme situations: either your files may be used without being configured, or they are used during the configuration. In most cases the traditional approach is enough.

`AC_CHECK_DECLS_ONCE (`*`symbols`*`)` [Macro]

For each of the *symbols* (*comma*-separated list), define `HAVE_DECL_`*`symbol`* (in all capitals) to '`1`' if *symbol* is declared in the default include files, otherwise to '`0`'. This is a once-only variant of `AC_CHECK_DECLS`. It generates the checking code at most once, so that `configure` is smaller and faster; but the checks cannot be conditionalized and are always done once, early during the `configure` run.

5.8 Structures

The following macros check for the presence of certain members in C structures. If there is no macro specifically defined to check for a member you need, then you can use the general structure-member macros (see Section 5.8.2 [Generic Structures], page 67) or, for more complex tests, you may use `AC_COMPILE_IFELSE` (see Section 6.4 [Running the Compiler], page 93).

5.8.1 Particular Structure Checks

The following macros check for certain structures or structure members.

`AC_STRUCT_DIRENT_D_INO` [Macro]

Perform all the actions of `AC_HEADER_DIRENT` (see Section 5.6.2 [Particular Headers], page 59). Then, if `struct dirent` contains a `d_ino` member, define `HAVE_STRUCT_DIRENT_D_INO`.

`HAVE_STRUCT_DIRENT_D_INO` indicates only the presence of `d_ino`, not whether its contents are always reliable. Traditionally, a zero `d_ino` indicated a deleted directory entry, though current systems hide this detail from the user and never return zero `d_ino` values. Many current systems report an incorrect `d_ino` for a directory entry that is a mount point.

`AC_STRUCT_DIRENT_D_TYPE` [Macro]

Perform all the actions of `AC_HEADER_DIRENT` (see Section 5.6.2 [Particular Headers], page 59). Then, if `struct dirent` contains a `d_type` member, define `HAVE_STRUCT_DIRENT_D_TYPE`.

`AC_STRUCT_ST_BLKSIZE` [Macro]

If `struct stat` contains an `st_blksize` member, define `HAVE_STRUCT_STAT_ST_BLKSIZE`. The former name, `HAVE_ST_BLKSIZE` is to be avoided, as its support will cease in the future. This macro is obsoleted, and should be replaced by

```
AC_CHECK_MEMBERS([struct stat.st_blksize])
```

`AC_STRUCT_ST_BLOCKS` [Macro]

If `struct stat` contains an `st_blocks` member, define `HAVE_STRUCT_STAT_ST_BLOCKS`. Otherwise, require an `AC_LIBOBJ` replacement of '`fileblocks`'. The former name, `HAVE_ST_BLOCKS` is to be avoided, as its support will cease in the future.

`AC_STRUCT_ST_RDEV` [Macro]

If `struct stat` contains an `st_rdev` member, define `HAVE_STRUCT_STAT_ST_RDEV`. The former name for this macro, `HAVE_ST_RDEV`, is to be avoided as it will cease to be supported in the future. Actually, even the new macro is obsolete and should be replaced by:

```
AC_CHECK_MEMBERS([struct stat.st_rdev])
```

`AC_STRUCT_TM` [Macro]

If '`time.h`' does not define `struct tm`, define `TM_IN_SYS_TIME`, which means that including '`sys/time.h`' had better define `struct tm`.

This macro is obsolescent, as '`time.h`' defines `struct tm` in current systems. New programs need not use this macro.

`AC_STRUCT_TIMEZONE` [Macro]

Figure out how to get the current timezone. If `struct tm` has a `tm_zone` member, define `HAVE_STRUCT_TM_TM_ZONE` (and the obsoleted `HAVE_TM_ZONE`). Otherwise, if the external array `tzname` is found, define `HAVE_TZNAME`; if it is declared, define `HAVE_DECL_TZNAME`.

5.8.2 Generic Structure Checks

These macros are used to find structure members not covered by the "particular" test macros.

`AC_CHECK_MEMBER (`*aggregate.member*`, [`*action-if-found*`], [`*action-if-not-found*`], [`*includes* = '`default-includes`'])` [Macro]

Check whether *member* is a member of the aggregate *aggregate*. If no *includes* are specified, the default includes are used (see Section 5.1.2 [Default Includes], page 39).

```
AC_CHECK_MEMBER([struct passwd.pw_gecos], [],
                [AC_MSG_ERROR([We need 'passwd.pw_gecos'!])],
                [#include <pwd.h>])
```

You can use this macro for submembers:

```
AC_CHECK_MEMBER(struct top.middle.bot)
```

AC_CHECK_MEMBERS (*members*, [*action-if-found*], [Macro]
[*action-if-not-found*], [*includes* = 'default-includes'])

Check for the existence of each '*aggregate.member*' of *members* using the previous macro. When *member* belongs to *aggregate*, define HAVE_*aggregate*_*member* (in all capitals, with spaces and dots replaced by underscores). If *action-if-found* is given, it is executed for each of the found members. If *action-if-not-found* is given, it is executed for each of the members that could not be found.

This macro uses M4 lists:

```
AC_CHECK_MEMBERS([struct stat.st_rdev, struct stat.st_blksize])
```

5.9 Types

The following macros check for C types, either builtin or typedefs. If there is no macro specifically defined to check for a type you need, and you don't need to check for any special properties of it, then you can use a general type-check macro.

5.9.1 Particular Type Checks

These macros check for particular C types in 'sys/types.h', 'stdlib.h', 'stdint.h', 'inttypes.h' and others, if they exist.

The Gnulib stdint module is an alternate way to define many of these symbols; it is useful if you prefer your code to assume a C99-or-better environment. See Section 2.2 [Gnulib], page 3.

AC_TYPE_GETGROUPS [Macro]

Define GETGROUPS_T to be whichever of gid_t or int is the base type of the array argument to getgroups.

AC_TYPE_INT8_T [Macro]

If 'stdint.h' or 'inttypes.h' defines the type int8_t, define HAVE_INT8_T. Otherwise, define int8_t to a signed integer type that is exactly 8 bits wide and that uses two's complement representation, if such a type exists.

AC_TYPE_INT16_T [Macro]

This is like AC_TYPE_INT8_T, except for 16-bit integers.

AC_TYPE_INT32_T [Macro]

This is like AC_TYPE_INT8_T, except for 32-bit integers.

AC_TYPE_INT64_T [Macro]

This is like AC_TYPE_INT8_T, except for 64-bit integers.

AC_TYPE_INTMAX_T [Macro]

If 'stdint.h' or 'inttypes.h' defines the type intmax_t, define HAVE_INTMAX_T. Otherwise, define intmax_t to the widest signed integer type.

AC_TYPE_INTPTR_T [Macro]

If 'stdint.h' or 'inttypes.h' defines the type intptr_t, define HAVE_INTPTR_T. Otherwise, define intptr_t to a signed integer type wide enough to hold a pointer, if such a type exists.

`AC_TYPE_LONG_DOUBLE` [Macro]
If the C compiler supports a working `long double` type, define `HAVE_LONG_DOUBLE`. The `long double` type might have the same range and precision as `double`.

`AC_TYPE_LONG_DOUBLE_WIDER` [Macro]
If the C compiler supports a working `long double` type with more range or precision than the `double` type, define `HAVE_LONG_DOUBLE_WIDER`.

`AC_TYPE_LONG_LONG_INT` [Macro]
If the C compiler supports a working `long long int` type, define `HAVE_LONG_LONG_INT`.

`AC_TYPE_MBSTATE_T` [Macro]
Define `HAVE_MBSTATE_T` if `<wchar.h>` declares the `mbstate_t` type. Also, define `mbstate_t` to be a type if `<wchar.h>` does not declare it.

`AC_TYPE_MODE_T` [Macro]
Define `mode_t` to a suitable type, if standard headers do not define it.

`AC_TYPE_OFF_T` [Macro]
Define `off_t` to a suitable type, if standard headers do not define it.

`AC_TYPE_PID_T` [Macro]
Define `pid_t` to a suitable type, if standard headers do not define it.

`AC_TYPE_SIGNAL` [Macro]
If '`signal.h`' declares `signal` as returning a pointer to a function returning `void`, define `RETSIGTYPE` to be `void`; otherwise, define it to be `int`.

Define signal handlers as returning type `RETSIGTYPE`:

```
RETSIGTYPE
hup_handler ()
{
...
}
```

`AC_TYPE_SIZE_T` [Macro]
Define `size_t` to a suitable type, if standard headers do not define it.

`AC_TYPE_SSIZE_T` [Macro]
Define `ssize_t` to a suitable type, if standard headers do not define it.

`AC_TYPE_UID_T` [Macro]
Define `uid_t` and `gid_t` to suitable types, if standard headers do not define them.

`AC_TYPE_UINT8_T` [Macro]
If '`stdint.h`' or '`inttypes.h`' defines the type `uint8_t`, define `HAVE_UINT8_T`. Otherwise, define `uint8_t` to an unsigned integer type that is exactly 8 bits wide, if such a type exists.

`AC_TYPE_UINT16_T` [Macro]
This is like `AC_TYPE_UINT8_T`, except for 16-bit unsigned integers.

`AC_TYPE_UINT32_T` [Macro]
This is like `AC_TYPE_UINT8_T`, except for 32-bit unsigned integers.

`AC_TYPE_UINT64_T` [Macro]
This is like `AC_TYPE_UINT8_T`, except for 64-bit unsigned integers.

`AC_TYPE_UINTMAX_T` [Macro]
If '`stdint.h`' or '`inttypes.h`' defines the type `uintmax_t`, define `HAVE_UINTMAX_T`. Otherwise, define `uintmax_t` to the widest unsigned integer type.

`AC_TYPE_UINTPTR_T` [Macro]
If '`stdint.h`' or '`inttypes.h`' defines the type `uintptr_t`, define `HAVE_UINTPTR_T`. Otherwise, define `uintptr_t` to an unsigned integer type wide enough to hold a pointer, if such a type exists.

`AC_TYPE_UNSIGNED_LONG_LONG_INT` [Macro]
If the C compiler supports a working `unsigned long long int` type, define `HAVE_UNSIGNED_LONG_LONG_INT`.

5.9.2 Generic Type Checks

These macros are used to check for types not covered by the "particular" test macros.

`AC_CHECK_TYPE` (*type*, [*action-if-found*], [*action-if-not-found*], [*includes* = '`default-includes`']) [Macro]
Check whether *type* is defined. It may be a compiler builtin type or defined by the *includes* (see Section 5.1.2 [Default Includes], page 39).

`AC_CHECK_TYPES` (*types*, [*action-if-found*], [*action-if-not-found*], [*includes* = '`default-includes`']) [Macro]
For each *type* of the *types* that is defined, define `HAVE_`*type* (in all capitals). If no *includes* are specified, the default includes are used (see Section 5.1.2 [Default Includes], page 39). If *action-if-found* is given, it is additional shell code to execute when one of the types is found. If *action-if-not-found* is given, it is executed when one of the types is not found.

This macro uses M4 lists:

```
AC_CHECK_TYPES([ptrdiff_t])
AC_CHECK_TYPES([unsigned long long int, uintmax_t])
```

Autoconf, up to 2.13, used to provide to another version of `AC_CHECK_TYPE`, broken by design. In order to keep backward compatibility, a simple heuristics, quite safe but not totally, is implemented. In case of doubt, read the documentation of the former `AC_CHECK_TYPE`, see Section 17.4 [Obsolete Macros], page 209.

5.10 Compilers and Preprocessors

All the tests for compilers (`AC_PROG_CC`, `AC_PROG_CXX`, `AC_PROG_F77`) define the output variable `EXEEXT` based on the output of the compiler, typically to the empty string if Posix and '`.exe`' if a DOS variant.

They also define the output variable `OBJEXT` based on the output of the compiler, after '`.c`' files have been excluded, typically to '`o`' if Posix, '`obj`' if a DOS variant.

If the compiler being used does not produce executables, the tests fail. If the executables can't be run, and cross-compilation is not enabled, they fail too. See Chapter 13 [Manual Configuration], page 189, for more on support for cross compiling.

5.10.1 Specific Compiler Characteristics

Some compilers exhibit different behaviors.

Static/Dynamic Expressions

Autoconf relies on a trick to extract one bit of information from the C compiler: using negative array sizes. For instance the following excerpt of a C source demonstrates how to test whether '`int`' objects are 4 bytes wide:

```
int
main (void)
{
  static int test_array [sizeof (int) == 4 ? 1 : -1];
  test_array [0] = 0;
  return 0;
}
```

To our knowledge, there is a single compiler that does not support this trick: the HP C compilers (the real one, not only the "bundled") on HP-UX 11.00. They incorrectly reject the above program with the diagnostic "Variable-length arrays cannot have static storage." This bug comes from HP compilers' mishandling of `sizeof (int)`, not from the `? 1 : -1`, and Autoconf works around this problem by casting `sizeof (int)` to `long int` before comparing it.

5.10.2 Generic Compiler Characteristics

`AC_CHECK_SIZEOF (`*type*`, [`*unused*`], [`*includes* = '`default-includes`'])` [Macro]

Define `SIZEOF_`*type* (see Section 5.1.1 [Standard Symbols], page 39) to be the size in bytes of *type*. If '`type`' is unknown, it gets a size of 0. If no *includes* are specified, the default includes are used (see Section 5.1.2 [Default Includes], page 39). If you provide *include*, be sure to include '`stdio.h`' which is required for this macro to run.

This macro now works even when cross-compiling. The *unused* argument was used when cross-compiling.

For example, the call

```
AC_CHECK_SIZEOF([int *])
```

defines `SIZEOF_INT_P` to be 8 on DEC Alpha AXP systems.

`AC_CHECK_ALIGNOF (`*type*`, [`*includes* = '`default-includes`'])` [Macro]

Define `ALIGNOF_`*type* (see Section 5.1.1 [Standard Symbols], page 39) to be the alignment in bytes of *type*. If '`type`' is unknown, it gets a size of 0. If no *includes* are specified, the default includes are used (see Section 5.1.2 [Default Includes], page 39). If you provide *include*, be sure to include '`stddef.h`' and '`stdio.h`' which are required for this macro to work correctly.

`AC_LANG_WERROR` [Macro]

Normally Autoconf ignores warnings generated by the compiler, linker, and preprocessor. If this macro is used, warnings count as fatal errors for the current language. This macro is useful when the results of configuration are used where warnings are unacceptable; for instance, if parts of a program are built with the GCC '`-Werror`' option. If the whole program is built using '`-Werror`' it is often simpler to put '`-Werror`' in the compiler flags (`CFLAGS`, etc.).

5.10.3 C Compiler Characteristics

The following macros provide ways to find and exercise a C Compiler. There are a few constructs that ought to be avoided, but do not deserve being checked for, since they can easily be worked around.

Don't use lines containing solitary backslashes

They tickle a bug in the HP-UX C compiler (checked on HP-UX 10.20, 11.00, and 11i). When given the following source:

```
#ifdef __STDC__
/\
* A comment with backslash-newlines in it.  %{ %} *\
\
/
char str[] = "\\
" A string with backslash-newlines in it %{ %} \\
"";
char apostrophe = '\\
\
'\
';
#endif
```

the compiler incorrectly fails with the diagnostics "Non-terminating comment at end of file" and "Missing '`#endif`' at end of file." Removing the lines with solitary backslashes solves the problem.

Don't compile several files at once if output matters to you

Some compilers, such as the HP's, reports the name of the file it is compiling *when* they are several. For instance:

```
$ cc a.c b.c
a.c:
b.c:
```

This can cause problems if you observe the output of the compiler to detect failures. Invoking '`cc -c a.c && cc -c b.c && cc -o c a.o b.o`' solves the issue.

Don't rely on `#error` failing

The IRIX C compiler does not fail when #error is preprocessed; it simply emits a diagnostic and continues, exiting successfully. So, instead of an error directive like `#error "Unsupported word size"` it is more portable to use an invalid directive like `#Unsupported word size` in Autoconf tests. In ordinary source

code, `#error` is OK, since installers with inadequate compilers like IRIX can simply examine these compilers' diagnostic output.

Don't rely on correct `#line` support
: On Solaris, `c89` (at least Sun C 5.3 through 5.8) diagnoses `#line` directives whose line numbers are greater than 32767. Nothing in Posix makes this invalid. That is why Autoconf stopped issuing `#line` directives.

`AC_PROG_CC` ([*compiler-search-list*]) [Macro]

Determine a C compiler to use. If `CC` is not already set in the environment, check for `gcc` and `cc`, then for other C compilers. Set output variable `CC` to the name of the compiler found.

This macro may, however, be invoked with an optional first argument which, if specified, must be a blank-separated list of C compilers to search for. This just gives the user an opportunity to specify an alternative search list for the C compiler. For example, if you didn't like the default order, then you could invoke `AC_PROG_CC` like this:

```
AC_PROG_CC([gcc cl cc])
```

If the C compiler does not handle function prototypes correctly by default, try to add an option to output variable `CC` to make it so. This macro tries various options that select standard-conformance modes on various systems.

After calling this macro you can check whether the C compiler has been set to accept ANSI C89 (ISO C90); if not, the shell variable `ac_cv_prog_cc_c89` is set to '`no`'. See also `AC_C_PROTOTYPES` below.

If using the GNU C compiler, set shell variable `GCC` to '`yes`'. If output variable `CFLAGS` was not already set, set it to '`-g -O2`' for the GNU C compiler ('`-O2`' on systems where GCC does not accept '`-g`'), or '`-g`' for other compilers.

`AC_PROG_CC_C_O` [Macro]

If the C compiler does not accept the '`-c`' and '`-o`' options simultaneously, define `NO_MINUS_C_MINUS_O`. This macro actually tests both the compiler found by `AC_PROG_CC`, and, if different, the first `cc` in the path. The test fails if one fails. This macro was created for GNU Make to choose the default C compilation rule.

`AC_PROG_CPP` [Macro]

Set output variable `CPP` to a command that runs the C preprocessor. If '`$CC -E`' doesn't work, '`/lib/cpp`' is used. It is only portable to run `CPP` on files with a '`.c`' extension.

Some preprocessors don't indicate missing include files by the error status. For such preprocessors an internal variable is set that causes other macros to check the standard error from the preprocessor and consider the test failed if any warnings have been reported. For most preprocessors, though, warnings do not cause include-file tests to fail unless `AC_PROG_CPP_WERROR` is also specified.

`AC_PROG_CPP_WERROR` [Macro]

This acts like `AC_PROG_CPP`, except it treats warnings from the preprocessor as errors even if the preprocessor exit status indicates success. This is useful for avoiding headers that generate mandatory warnings, such as deprecation notices.

The following macros check for C compiler or machine architecture features. To check for characteristics not listed here, use `AC_COMPILE_IFELSE` (see Section 6.4 [Running the Compiler], page 93) or `AC_RUN_IFELSE` (see Section 6.6 [Runtime], page 94).

`AC_PROG_CC_STDC` [Macro]

If the C compiler cannot compile ISO Standard C (currently C99), try to add an option to output variable `CC` to make it work. If the compiler does not support C99, fall back to supporting ANSI C89 (ISO C90).

After calling this macro you can check whether the C compiler has been set to accept Standard C; if not, the shell variable `ac_cv_prog_cc_stdc` is set to '`no`'.

`AC_PROG_CC_C89` [Macro]

If the C compiler is not in ANSI C89 (ISO C90) mode by default, try to add an option to output variable `CC` to make it so. This macro tries various options that select ANSI C89 on some system or another. It considers the compiler to be in ANSI C89 mode if it handles function prototypes correctly.

After calling this macro you can check whether the C compiler has been set to accept ANSI C89; if not, the shell variable `ac_cv_prog_cc_c89` is set to '`no`'.

This macro is called automatically by `AC_PROG_CC`.

`AC_PROG_CC_C99` [Macro]

If the C compiler is not in C99 mode by default, try to add an option to output variable `CC` to make it so. This macro tries various options that select C99 on some system or another. It considers the compiler to be in C99 mode if it handles `_Bool`, flexible arrays, `inline`, `long long int`, mixed code and declarations, named initialization of structs, `restrict`, varargs macros, variable declarations in `for` loops and variable length arrays.

After calling this macro you can check whether the C compiler has been set to accept C99; if not, the shell variable `ac_cv_prog_cc_c99` is set to '`no`'.

`AC_C_BACKSLASH_A` [Macro]

Define '`HAVE_C_BACKSLASH_A`' to 1 if the C compiler understands '`\a`'.

This macro is obsolescent, as current C compilers understand '`\a`'. New programs need not use this macro.

`AC_C_BIGENDIAN` ([*action-if-true*], [*action-if-false*], [*action-if-unknown*]) [Macro]

If words are stored with the most significant byte first (like Motorola and SPARC CPUs), execute *action-if-true*. If words are stored with the least significant byte first (like Intel and VAX CPUs), execute *action-if-false*.

This macro runs a test-case if endianness cannot be determined from the system header files. When cross-compiling, the test-case is not run but grep'ed for some magic values. *action-if-unknown* is executed if the latter case fails to determine the byte sex of the host system.

The default for *action-if-true* is to define '`WORDS_BIGENDIAN`'. The default for *action-if-false* is to do nothing. And finally, the default for *action-if-unknown* is to abort configure and tell the installer which variable he should preset to bypass this test.

`AC_C_CONST` [Macro]

If the C compiler does not fully support the `const` keyword, define `const` to be empty. Some C compilers that do not define `__STDC__` do support `const`; some compilers that define `__STDC__` do not completely support `const`. Programs can simply use `const` as if every C compiler supported it; for those that don't, the makefile or configuration header file defines it as empty.

Occasionally installers use a C++ compiler to compile C code, typically because they lack a C compiler. This causes problems with `const`, because C and C++ treat `const` differently. For example:

```
const int foo;
```

is valid in C but not in C++. These differences unfortunately cannot be papered over by defining `const` to be empty.

If `autoconf` detects this situation, it leaves `const` alone, as this generally yields better results in practice. However, using a C++ compiler to compile C code is not recommended or supported, and installers who run into trouble in this area should get a C compiler like GCC to compile their C code.

This macro is obsolescent, as current C compilers support `const`. New programs need not use this macro.

`AC_C_RESTRICT` [Macro]

If the C compiler recognizes the `restrict` keyword, don't do anything. If it recognizes only a variant spelling (`__restrict`, `__restrict__`, or `_Restrict`), then define `restrict` to that. Otherwise, define `restrict` to be empty. Thus, programs may simply use `restrict` as if every C compiler supported it; for those that do not, the makefile or configuration header defines it away.

Although support in C++ for the `restrict` keyword is not required, several C++ compilers do accept the keyword. This macro works for them, too.

`AC_C_VOLATILE` [Macro]

If the C compiler does not understand the keyword `volatile`, define `volatile` to be empty. Programs can simply use `volatile` as if every C compiler supported it; for those that do not, the makefile or configuration header defines it as empty.

If the correctness of your program depends on the semantics of `volatile`, simply defining it to be empty does, in a sense, break your code. However, given that the compiler does not support `volatile`, you are at its mercy anyway. At least your program compiles, when it wouldn't before.

In general, the `volatile` keyword is a standard C feature, so you might expect that `volatile` is available only when `__STDC__` is defined. However, Ultrix 4.3's native compiler does support volatile, but does not define `__STDC__`.

This macro is obsolescent, as current C compilers support `volatile`. New programs need not use this macro.

`AC_C_INLINE` [Macro]

If the C compiler supports the keyword `inline`, do nothing. Otherwise define `inline` to `__inline__` or `__inline` if it accepts one of those, otherwise define `inline` to be empty.

AC_C_CHAR_UNSIGNED [Macro]

If the C type `char` is unsigned, define `__CHAR_UNSIGNED__`, unless the C compiler predefines it.

AC_C_STRINGIZE [Macro]

If the C preprocessor supports the stringizing operator, define `HAVE_STRINGIZE`. The stringizing operator is '`#`' and is found in macros such as this:

```
#define x(y) #y
```

This macro is obsolescent, as current C compilers support the stringizing operator. New programs need not use this macro.

AC_C_TYPEOF [Macro]

If the C compiler supports GCC's `typeof` syntax either directly or through a different spelling of the keyword (e.g., `__typeof__`), define `HAVE_TYPEOF`. If the support is available only through a different spelling, define `typeof` to that spelling.

AC_C_PROTOTYPES [Macro]

If function prototypes are understood by the compiler (as determined by `AC_PROG_CC`), define `PROTOTYPES` and `__PROTOTYPES`. Defining `__PROTOTYPES` is for the benefit of header files that cannot use macros that infringe on user name space.

This macro is obsolescent, as current C compilers support prototypes. New programs need not use this macro.

AC_PROG_GCC_TRADITIONAL [Macro]

Add '`-traditional`' to output variable `CC` if using the GNU C compiler and `ioctl` does not work properly without '`-traditional`'. That usually happens when the fixed header files have not been installed on an old system.

This macro is obsolescent, since current versions of the GNU C compiler fix the header files automatically when installed.

5.10.4 C++ Compiler Characteristics

AC_PROG_CXX ([*compiler-search-list*]) [Macro]

Determine a C++ compiler to use. Check whether the environment variable `CXX` or `CCC` (in that order) is set; if so, then set output variable `CXX` to its value.

Otherwise, if the macro is invoked without an argument, then search for a C++ compiler under the likely names (first `g++` and `c++` then other names). If none of those checks succeed, then as a last resort set `CXX` to `g++`.

This macro may, however, be invoked with an optional first argument which, if specified, must be a blank-separated list of C++ compilers to search for. This just gives the user an opportunity to specify an alternative search list for the C++ compiler. For example, if you didn't like the default order, then you could invoke `AC_PROG_CXX` like this:

```
AC_PROG_CXX([gcc cl KCC CC cxx cc++ xlC aCC c++ g++])
```

If using the GNU C++ compiler, set shell variable `GXX` to '`yes`'. If output variable `CXXFLAGS` was not already set, set it to '`-g -O2`' for the GNU C++ compiler ('`-O2`' on systems where G++ does not accept '`-g`'), or '`-g`' for other compilers.

`AC_PROG_CXXCPP` [Macro]

Set output variable `CXXCPP` to a command that runs the C++ preprocessor. If '`$CXX -E`' doesn't work, '`/lib/cpp`' is used. It is portable to run `CXXCPP` only on files with a '`.c`', '`.C`', '`.cc`', or '`.cpp`' extension.

Some preprocessors don't indicate missing include files by the error status. For such preprocessors an internal variable is set that causes other macros to check the standard error from the preprocessor and consider the test failed if any warnings have been reported. However, it is not known whether such broken preprocessors exist for C++.

`AC_PROG_CXX_C_O` [Macro]

Test whether the C++ compiler accepts the options '`-c`' and '`-o`' simultaneously, and define `CXX_NO_MINUS_C_MINUS_O`, if it does not.

5.10.5 Objective C Compiler Characteristics

`AC_PROG_OBJC` ([*compiler-search-list*]) [Macro]

Determine an Objective C compiler to use. If `OBJC` is not already set in the environment, check for Objective C compilers. Set output variable `OBJC` to the name of the compiler found.

This macro may, however, be invoked with an optional first argument which, if specified, must be a blank-separated list of Objective C compilers to search for. This just gives the user an opportunity to specify an alternative search list for the Objective C compiler. For example, if you didn't like the default order, then you could invoke `AC_PROG_OBJC` like this:

```
AC_PROG_OBJC([gcc objcc objc])
```

If using the GNU Objective C compiler, set shell variable `GOBJC` to '`yes`'. If output variable `OBJCFLAGS` was not already set, set it to '`-g -O2`' for the GNU Objective C compiler ('`-O2`' on systems where `gcc` does not accept '`-g`'), or '`-g`' for other compilers.

`AC_PROG_OBJCCPP` [Macro]

Set output variable `OBJCCPP` to a command that runs the Objective C preprocessor. If '`$OBJC -E`' doesn't work, '`/lib/cpp`' is used.

5.10.6 Erlang Compiler and Interpreter Characteristics

Autoconf defines the following macros for determining paths to the essential Erlang/OTP programs:

`AC_ERLANG_PATH_ERLC` ([*value-if-not-found*], [*path*]) [Macro]

Determine an Erlang compiler to use. If `ERLC` is not already set in the environment, check for `erlc`. Set output variable `ERLC` to the complete path of the compiler command found. In addition, if `ERLCFLAGS` is not set in the environment, set it to an empty value.

The two optional arguments have the same meaning as the two last arguments of macro `AC_PROG_PATH` for looking for the `erlc` program. For example, to look for `erlc` only in the '`/usr/lib/erlang/bin`' directory:

```
AC_ERLANG_PATH_ERLC([not found], [/usr/lib/erlang/bin])
```

AC_ERLANG_NEED_ERLC ([*path*]) [Macro]
A simplified variant of the AC_ERLANG_PATH_ERLC macro, that prints an error message and exits the configure script if the erlc program is not found.

AC_ERLANG_PATH_ERL ([*value-if-not-found*], [*path*]) [Macro]
Determine an Erlang interpreter to use. If ERL is not already set in the environment, check for erl. Set output variable ERL to the complete path of the interpreter command found.

The two optional arguments have the same meaning as the two last arguments of macro AC_PROG_PATH for looking for the erl program. For example, to look for erl only in the '/usr/lib/erlang/bin' directory:

```
AC_ERLANG_PATH_ERL([not found], [/usr/lib/erlang/bin])
```

AC_ERLANG_NEED_ERL ([*path*]) [Macro]
A simplified variant of the AC_ERLANG_PATH_ERL macro, that prints an error message and exits the configure script if the erl program is not found.

5.10.7 Fortran Compiler Characteristics

The Autoconf Fortran support is divided into two categories: legacy Fortran 77 macros (F77), and modern Fortran macros (FC). The former are intended for traditional Fortran 77 code, and have output variables like F77, FFLAGS, and FLIBS. The latter are for newer programs that can (or must) compile under the newer Fortran standards, and have output variables like FC, FCFLAGS, and FCLIBS.

Except for two new macros AC_FC_SRCEXT and AC_FC_FREEFORM (see below), the FC and F77 macros behave almost identically, and so they are documented together in this section.

AC_PROG_F77 ([*compiler-search-list*]) [Macro]
Determine a Fortran 77 compiler to use. If F77 is not already set in the environment, then check for g77 and f77, and then some other names. Set the output variable F77 to the name of the compiler found.

This macro may, however, be invoked with an optional first argument which, if specified, must be a blank-separated list of Fortran 77 compilers to search for. This just gives the user an opportunity to specify an alternative search list for the Fortran 77 compiler. For example, if you didn't like the default order, then you could invoke AC_PROG_F77 like this:

```
AC_PROG_F77([fl32 f77 fort77 xlf g77 f90 xlf90])
```

If using g77 (the GNU Fortran 77 compiler), then set the shell variable G77 to 'yes'. If the output variable FFLAGS was not already set in the environment, then set it to '-g -O2' for g77 (or '-O2' where g77 does not accept '-g'). Otherwise, set FFLAGS to '-g' for all other Fortran 77 compilers.

AC_PROG_FC ([*compiler-search-list*], [*dialect*]) [Macro]
Determine a Fortran compiler to use. If FC is not already set in the environment, then dialect is a hint to indicate what Fortran dialect to search for; the default is to search for the newest available dialect. Set the output variable FC to the name of the compiler found.

By default, newer dialects are preferred over older dialects, but if `dialect` is specified then older dialects are preferred starting with the specified dialect. `dialect` can currently be one of Fortran 77, Fortran 90, or Fortran 95. However, this is only a hint of which compiler *name* to prefer (e.g., `f90` or `f95`), and no attempt is made to guarantee that a particular language standard is actually supported. Thus, it is preferable that you avoid the `dialect` option, and use AC_PROG_FC only for code compatible with the latest Fortran standard.

This macro may, alternatively, be invoked with an optional first argument which, if specified, must be a blank-separated list of Fortran compilers to search for, just as in `AC_PROG_F77`.

If the output variable `FCFLAGS` was not already set in the environment, then set it to '`-g -O2`' for GNU `g77` (or '`-O2`' where `g77` does not accept '`-g`'). Otherwise, set `FCFLAGS` to '`-g`' for all other Fortran compilers.

`AC_PROG_F77_C_O` [Macro]
`AC_PROG_FC_C_O` [Macro]

Test whether the Fortran compiler accepts the options '`-c`' and '`-o`' simultaneously, and define `F77_NO_MINUS_C_MINUS_O` or `FC_NO_MINUS_C_MINUS_O`, respectively, if it does not.

The following macros check for Fortran compiler characteristics. To check for characteristics not listed here, use `AC_COMPILE_IFELSE` (see Section 6.4 [Running the Compiler], page 93) or `AC_RUN_IFELSE` (see Section 6.6 [Runtime], page 94), making sure to first set the current language to Fortran 77 or Fortran via `AC_LANG([Fortran 77])` or `AC_LANG(Fortran)` (see Section 6.1 [Language Choice], page 87).

`AC_F77_LIBRARY_LDFLAGS` [Macro]
`AC_FC_LIBRARY_LDFLAGS` [Macro]

Determine the linker flags (e.g., '`-L`' and '`-l`') for the *Fortran intrinsic and runtime libraries* that are required to successfully link a Fortran program or shared library. The output variable `FLIBS` or `FCLIBS` is set to these flags (which should be included after `LIBS` when linking).

This macro is intended to be used in those situations when it is necessary to mix, e.g., C++ and Fortran source code in a single program or shared library (see section "Mixing Fortran 77 With C and C++" in *GNU Automake*).

For example, if object files from a C++ and Fortran compiler must be linked together, then the C++ compiler/linker must be used for linking (since special C++-ish things need to happen at link time like calling global constructors, instantiating templates, enabling exception support, etc.).

However, the Fortran intrinsic and runtime libraries must be linked in as well, but the C++ compiler/linker doesn't know by default how to add these Fortran 77 libraries. Hence, this macro was created to determine these Fortran libraries.

The macros `AC_F77_DUMMY_MAIN` and `AC_FC_DUMMY_MAIN` or `AC_F77_MAIN` and `AC_FC_MAIN` are probably also necessary to link C/C++ with Fortran; see below.

`AC_F77_DUMMY_MAIN` ([*action-if-found*], [*action-if-not-found*]) [Macro]

AC_FC_DUMMY_MAIN ([*action-if-found*], [*action-if-not-found*]) [Macro]

With many compilers, the Fortran libraries detected by AC_F77_LIBRARY_LDFLAGS or AC_FC_LIBRARY_LDFLAGS provide their own main entry function that initializes things like Fortran I/O, and which then calls a user-provided entry function named (say) MAIN__ to run the user's program. The AC_F77_DUMMY_MAIN and AC_FC_DUMMY_MAIN or AC_F77_MAIN and AC_FC_MAIN macros figure out how to deal with this interaction.

When using Fortran for purely numerical functions (no I/O, etc.) often one prefers to provide one's own main and skip the Fortran library initializations. In this case, however, one may still need to provide a dummy MAIN__ routine in order to prevent linking errors on some systems. AC_F77_DUMMY_MAIN or AC_FC_DUMMY_MAIN detects whether any such routine is *required* for linking, and what its name is; the shell variable F77_DUMMY_MAIN or FC_DUMMY_MAIN holds this name, unknown when no solution was found, and none when no such dummy main is needed.

By default, *action-if-found* defines F77_DUMMY_MAIN or FC_DUMMY_MAIN to the name of this routine (e.g., MAIN__) *if* it is required. *action-if-not-found* defaults to exiting with an error.

In order to link with Fortran routines, the user's C/C++ program should then include the following code to define the dummy main if it is needed:

```
#ifdef F77_DUMMY_MAIN
#  ifdef __cplusplus
     extern "C"
#  endif
   int F77_DUMMY_MAIN() { return 1; }
#endif
```

(Replace F77 with FC for Fortran instead of Fortran 77.)

Note that this macro is called automatically from AC_F77_WRAPPERS or AC_FC_WRAPPERS; there is generally no need to call it explicitly unless one wants to change the default actions.

AC_F77_MAIN [Macro]

AC_FC_MAIN [Macro]

As discussed above, many Fortran libraries allow you to provide an entry point called (say) MAIN__ instead of the usual main, which is then called by a main function in the Fortran libraries that initializes things like Fortran I/O. The AC_F77_MAIN and AC_FC_MAIN macros detect whether it is *possible* to utilize such an alternate main function, and defines F77_MAIN and FC_MAIN to the name of the function. (If no alternate main function name is found, F77_MAIN and FC_MAIN are simply defined to main.)

Thus, when calling Fortran routines from C that perform things like I/O, one should use this macro and name the "main" function F77_MAIN or FC_MAIN instead of main.

AC_F77_WRAPPERS [Macro]

AC_FC_WRAPPERS [Macro]

Defines C macros F77_FUNC(name, NAME), FC_FUNC(name, NAME), F77_FUNC_(name, NAME), and FC_FUNC_(name, NAME) to properly mangle the names of C/C++

identifiers, and identifiers with underscores, respectively, so that they match the name-mangling scheme used by the Fortran compiler.

Fortran is case-insensitive, and in order to achieve this the Fortran compiler converts all identifiers into a canonical case and format. To call a Fortran subroutine from C or to write a C function that is callable from Fortran, the C program must explicitly use identifiers in the format expected by the Fortran compiler. In order to do this, one simply wraps all C identifiers in one of the macros provided by `AC_F77_WRAPPERS` or `AC_FC_WRAPPERS`. For example, suppose you have the following Fortran 77 subroutine:

```
subroutine foobar (x, y)
double precision x, y
y = 3.14159 * x
return
end
```

You would then declare its prototype in C or C++ as:

```
#define FOOBAR_F77 F77_FUNC (foobar, FOOBAR)
#ifdef __cplusplus
extern "C"  /* prevent C++ name mangling */
#endif
void FOOBAR_F77(double *x, double *y);
```

Note that we pass both the lowercase and uppercase versions of the function name to `F77_FUNC` so that it can select the right one. Note also that all parameters to Fortran 77 routines are passed as pointers (see section "Mixing Fortran 77 With C and C++" in *GNU Automake*).

(Replace `F77` with `FC` for Fortran instead of Fortran 77.)

Although Autoconf tries to be intelligent about detecting the name-mangling scheme of the Fortran compiler, there may be Fortran compilers that it doesn't support yet. In this case, the above code generates a compile-time error, but some other behavior (e.g., disabling Fortran-related features) can be induced by checking whether `F77_FUNC` or `FC_FUNC` is defined.

Now, to call that routine from a C program, we would do something like:

```
{
    double x = 2.7183, y;
    FOOBAR_F77 (&x, &y);
}
```

If the Fortran identifier contains an underscore (e.g., `foo_bar`), you should use `F77_FUNC_` or `FC_FUNC_` instead of `F77_FUNC` or `FC_FUNC` (with the same arguments). This is because some Fortran compilers mangle names differently if they contain an underscore.

`AC_F77_FUNC` (*name*, [*shellvar*]) [Macro]
`AC_FC_FUNC` (*name*, [*shellvar*]) [Macro]

Given an identifier *name*, set the shell variable *shellvar* to hold the mangled version *name* according to the rules of the Fortran linker (see also `AC_F77_WRAPPERS` or `AC_FC_WRAPPERS`). *shellvar* is optional; if it is not supplied, the shell variable is simply

name. The purpose of this macro is to give the caller a way to access the name-mangling information other than through the C preprocessor as above, for example, to call Fortran routines from some language other than C/C++.

`AC_FC_SRCEXT` (*ext*, [*action-if-success*], [*action-if-failure*]) [Macro]

By default, the `FC` macros perform their tests using a '`.f`' extension for source-code files. Some compilers, however, only enable newer language features for appropriately named files, e.g., Fortran 90 features only for '`.f90`' files. On the other hand, some other compilers expect all source files to end in '`.f`' and require special flags to support other file name extensions. The `AC_FC_SRCEXT` macro deals with both of these issues.

The `AC_FC_SRCEXT` tries to get the `FC` compiler to accept files ending with the extension *.ext* (i.e., *ext* does *not* contain the dot). If any special compiler flags are needed for this, it stores them in the output variable `FCFLAGS_`*ext*. This extension and these flags are then used for all subsequent `FC` tests (until `AC_FC_SRCEXT` is called again).

For example, you would use `AC_FC_SRCEXT(f90)` to employ the '`.f90`' extension in future tests, and it would set a `FCFLAGS_f90` output variable with any extra flags that are needed to compile such files.

The `FCFLAGS_`*ext* can *not* be simply absorbed into `FCFLAGS`, for two reasons based on the limitations of some compilers. First, only one `FCFLAGS_`*ext* can be used at a time, so files with different extensions must be compiled separately. Second, `FCFLAGS_`*ext* must appear *immediately* before the source-code file name when compiling. So, continuing the example above, you might compile a '`foo.f90`' file in your makefile with the command:

```
foo.o: foo.f90
     $(FC) -c $(FCFLAGS) $(FCFLAGS_f90) '$(srcdir)/foo.f90'
```

If `AC_FC_SRCEXT` succeeds in compiling files with the *ext* extension, it calls *action-if-success* (defaults to nothing). If it fails, and cannot find a way to make the `FC` compiler accept such files, it calls *action-if-failure* (defaults to exiting with an error message).

`AC_FC_FREEFORM` ([*action-if-success*], [*action-if-failure*]) [Macro]

The `AC_FC_FREEFORM` tries to ensure that the Fortran compiler (`$FC`) allows free-format source code (as opposed to the older fixed-format style from Fortran 77). If necessary, it may add some additional flags to `FCFLAGS`.

This macro is most important if you are using the default '`.f`' extension, since many compilers interpret this extension as indicating fixed-format source unless an additional flag is supplied. If you specify a different extension with `AC_FC_SRCEXT`, such as '`.f90`' or '`.f95`', then `AC_FC_FREEFORM` ordinarily succeeds without modifying `FCFLAGS`.

If `AC_FC_FREEFORM` succeeds in compiling free-form source, it calls *action-if-success* (defaults to nothing). If it fails, it calls *action-if-failure* (defaults to exiting with an error message).

5.11 System Services

The following macros check for operating system services or capabilities.

`AC_PATH_X` [Macro]

Try to locate the X Window System include files and libraries. If the user gave the command line options '`--x-includes=dir`' and '`--x-libraries=dir`', use those directories.

If either or both were not given, get the missing values by running `xmkmf` (or an executable pointed to by the `XMKMF` environment variable) on a trivial '`Imakefile`' and examining the makefile that it produces. Setting `XMKMF` to '`false`' disables this method.

If this method fails to find the X Window System, `configure` looks for the files in several directories where they often reside. If either method is successful, set the shell variables `x_includes` and `x_libraries` to their locations, unless they are in directories the compiler searches by default.

If both methods fail, or the user gave the command line option '`--without-x`', set the shell variable `no_x` to '`yes`'; otherwise set it to the empty string.

`AC_PATH_XTRA` [Macro]

An enhanced version of `AC_PATH_X`. It adds the C compiler flags that X needs to output variable `X_CFLAGS`, and the X linker flags to `X_LIBS`. Define `X_DISPLAY_MISSING` if X is not available.

This macro also checks for special libraries that some systems need in order to compile X programs. It adds any that the system needs to output variable `X_EXTRA_LIBS`. And it checks for special X11R6 libraries that need to be linked with before '`-lX11`', and adds any found to the output variable `X_PRE_LIBS`.

`AC_SYS_INTERPRETER` [Macro]

Check whether the system supports starting scripts with a line of the form '`#!/bin/sh`' to select the interpreter to use for the script. After running this macro, shell code in '`configure.ac`' can check the shell variable `interpval`; it is set to '`yes`' if the system supports '`#!`', '`no`' if not.

`AC_SYS_LARGEFILE` [Macro]

Arrange for large-file support (`http://www.unix-systems.org/version2/whatsnew/lfs20mar.html`). On some hosts, one must use special compiler options to build programs that can access large files. Append any such options to the output variable `CC`. Define `_FILE_OFFSET_BITS` and `_LARGE_FILES` if necessary.

Large-file support can be disabled by configuring with the '`--disable-largefile`' option.

If you use this macro, check that your program works even when `off_t` is wider than `long int`, since this is common when large-file support is enabled. For example, it is not correct to print an arbitrary `off_t` value `X` with `printf ("%ld", (long int) X)`.

The LFS introduced the `fseeko` and `ftello` functions to replace their C counterparts `fseek` and `ftell` that do not use `off_t`. Take care to use `AC_FUNC_FSEEKO` to make their prototypes available when using them and large-file support is enabled.

`AC_SYS_LONG_FILE_NAMES` [Macro]

If the system supports file names longer than 14 characters, define `HAVE_LONG_FILE_NAMES`.

`AC_SYS_POSIX_TERMIOS` [Macro]

Check to see if the Posix termios headers and functions are available on the system. If so, set the shell variable `ac_cv_sys_posix_termios` to '`yes`'. If not, set the variable to '`no`'.

5.12 Posix Variants

The following macros check for certain operating systems that need special treatment for some programs, due to exceptional oddities in their header files or libraries. These macros are warts; they will be replaced by a more systematic approach, based on the functions they make available or the environments they provide.

`AC_AIX` [Macro]

If on AIX, define `_ALL_SOURCE`. Allows the use of some BSD functions. Should be called before any macros that run the C compiler.

`AC_GNU_SOURCE` [Macro]

If using the GNU C library, define `_GNU_SOURCE`. Allows the use of some GNU functions. Should be called before any macros that run the C compiler.

`AC_ISC_POSIX` [Macro]

For INTERACTIVE Systems Corporation Unix, add '`-lcposix`' to output variable `LIBS` if necessary for Posix facilities. Call this after `AC_PROG_CC` and before any other macros that use Posix interfaces. INTERACTIVE Unix is no longer sold, and Sun says that they will drop support for it on 2006-07-23, so this macro is becoming obsolescent.

`AC_MINIX` [Macro]

If on Minix, define `_MINIX` and `_POSIX_SOURCE` and define `_POSIX_1_SOURCE` to be 2. This allows the use of Posix facilities. Should be called before any macros that run the C compiler.

`AC_USE_SYSTEM_EXTENSIONS` [Macro]

If possible, enable extensions to Posix on hosts that normally disable the extensions, typically due to standards-conformance namespace issues. This may involve defining `__EXTENSIONS__` and `_POSIX_PTHREAD_SEMANTICS`, which are macros used by Solaris. This macro also has the combined effects of `AC_GNU_SOURCE`, `AC_AIX`, and `AC_MINIX`.

5.13 Erlang Libraries

The following macros check for an installation of Erlang/OTP, and for the presence of certain Erlang libraries. All those macros require the configuration of an Erlang interpreter and an Erlang compiler (see Section 5.10.6 [Erlang Compiler and Interpreter], page 77).

`AC_ERLANG_SUBST_ROOT_DIR` [Macro]

Set the output variable `ERLANG_ROOT_DIR` to the path to the base directory in which Erlang/OTP is installed (as returned by Erlang's `code:root_dir/0` function). The result of this test is cached if caching is enabled when running `configure`.

`AC_ERLANG_SUBST_LIB_DIR` [Macro]

Set the output variable `ERLANG_LIB_DIR` to the path of the library directory of Erlang/OTP (as returned by Erlang's `code:lib_dir/0` function), which subdirectories

each contain an installed Erlang/OTP library. The result of this test is cached if caching is enabled when running `configure`.

`AC_ERLANG_CHECK_LIB` (*library*, [*action-if-found*], [*action-if-not-found*]) [Macro]

Test whether the Erlang/OTP library *library* is installed by calling Erlang's `code:lib_dir/1` function. The result of this test is cached if caching is enabled when running `configure`. *action-if-found* is a list of shell commands to run if the library is installed; *action-if-not-found* is a list of shell commands to run if it is not. Additionally, if the library is installed, the output variable '`ERLANG_LIB_DIR_`*library*' is set to the path to the library installation directory. For example, to check if library `stdlib` is installed:

```
AC_ERLANG_CHECK_LIB([stdlib],
  [echo "stdlib is installed in $ERLANG_LIB_DIR_stdlib"],
  [AC_MSG_ERROR([stdlib was not found!])])
```

In addition to the above macros, which test installed Erlang libraries, the following macros determine the paths to the directories into which newly built Erlang libraries are to be installed:

`AC_ERLANG_SUBST_INSTALL_LIB_DIR` [Macro]

Set the `ERLANG_INSTALL_LIB_DIR` output variable to the directory into which every built Erlang library should be installed in a separate subdirectory. If this variable is not set in the environment when `configure` runs, its default value is `$ERLANG_LIB_DIR`, which value is set by the `AC_ERLANG_SUBST_LIB_DIR` macro.

`AC_ERLANG_SUBST_INSTALL_LIB_SUBDIR` (*library*, *version*) [Macro]

Set the '`ERLANG_INSTALL_LIB_DIR_`*library*' output variable to the directory into which the built Erlang library *library* version *version* should be installed. If this variable is not set in the environment when `configure` runs, its default value is '`$ERLANG_INSTALL_LIB_DIR/`*library*`-`*version*', the value of the `ERLANG_INSTALL_LIB_DIR` variable being set by the `AC_ERLANG_SUBST_INSTALL_LIB_DIR` macro.

6 Writing Tests

If the existing feature tests don't do something you need, you have to write new ones. These macros are the building blocks. They provide ways for other macros to check whether various kinds of features are available and report the results.

This chapter contains some suggestions and some of the reasons why the existing tests are written the way they are. You can also learn a lot about how to write Autoconf tests by looking at the existing ones. If something goes wrong in one or more of the Autoconf tests, this information can help you understand the assumptions behind them, which might help you figure out how to best solve the problem.

These macros check the output of the compiler system of the current language (see Section 6.1 [Language Choice], page 87). They do not cache the results of their tests for future use (see Section 7.4 [Caching Results], page 102), because they don't know enough about the information they are checking for to generate a cache variable name. They also do not print any messages, for the same reason. The checks for particular kinds of features call these macros and do cache their results and print messages about what they're checking for.

When you write a feature test that could be applicable to more than one software package, the best thing to do is encapsulate it in a new macro. See Chapter 9 [Writing Autoconf Macros], page 125, for how to do that.

6.1 Language Choice

Autoconf-generated `configure` scripts check for the C compiler and its features by default. Packages that use other programming languages (maybe more than one, e.g., C and C++) need to test features of the compilers for the respective languages. The following macros determine which programming language is used in the subsequent tests in '`configure.ac`'.

`AC_LANG (`*`language`*`)` [Macro]

Do compilation tests using the compiler, preprocessor, and file extensions for the specified *language*.

Supported languages are:

'`C`' Do compilation tests using `CC` and `CPP` and use extension '`.c`' for test programs. Use compilation flags: `CPPFLAGS` with `CPP`, and both `CPPFLAGS` and `CFLAGS` with `CC`.

'`C++`' Do compilation tests using `CXX` and `CXXCPP` and use extension '`.C`' for test programs. Use compilation flags: `CPPFLAGS` with `CXXPP`, and both `CPPFLAGS` and `CXXFLAGS` with `CXX`.

'`Fortran 77`'
Do compilation tests using `F77` and use extension '`.f`' for test programs. Use compilation flags: `FFLAGS`.

'`Fortran`' Do compilation tests using `FC` and use extension '`.f`' (or whatever has been set by `AC_FC_SRCEXT`) for test programs. Use compilation flags: `FCFLAGS`.

'Erlang' Compile and execute tests using ERLC and ERL and use extension '.erl' for test Erlang modules. Use compilation flags: ERLCFLAGS.

'Objective C'
Do compilation tests using OBJC and OBJCCPP and use extension '.m' for test programs. Use compilation flags: CPPFLAGS with OBJCPP, and both CPPFLAGS and OBJCFLAGS with OBJC.

AC_LANG_PUSH (*language*) [Macro]
Remember the current language (as set by AC_LANG) on a stack, and then select the *language*. Use this macro and AC_LANG_POP in macros that need to temporarily switch to a particular language.

AC_LANG_POP ([*language*]) [Macro]
Select the language that is saved on the top of the stack, as set by AC_LANG_PUSH, and remove it from the stack.

If given, *language* specifies the language we just *quit*. It is a good idea to specify it when it's known (which should be the case...), since Autoconf detects inconsistencies.

```
AC_LANG_PUSH([Fortran 77])
# Perform some tests on Fortran 77.
# ...
AC_LANG_POP([Fortran 77])
```

AC_LANG_ASSERT (*language*) [Macro]
Check statically that the current language is *language*. You should use this in your language specific macros to avoid that they be called with an inappropriate language.

This macro runs only at autoconf time, and incurs no cost at configure time. Sadly enough and because Autoconf is a two layer language[1], the macros AC_LANG_PUSH and AC_LANG_POP cannot be "optimizing", therefore as much as possible you ought to avoid using them to wrap your code, rather, require from the user to run the macro with a correct current language, and check it with AC_LANG_ASSERT. And anyway, that may help the user understand she is running a Fortran macro while expecting a result about her Fortran 77 compiler...

AC_REQUIRE_CPP [Macro]
Ensure that whichever preprocessor would currently be used for tests has been found. Calls AC_REQUIRE (see Section 9.4.1 [Prerequisite Macros], page 127) with an argument of either AC_PROG_CPP or AC_PROG_CXXCPP, depending on which language is current.

6.2 Writing Test Programs

Autoconf tests follow a common scheme: feed some program with some input, and most of the time, feed a compiler with some source file. This section is dedicated to these source samples.

[1] Because M4 is not aware of Sh code, especially conditionals, some optimizations that look nice statically may produce incorrect results at runtime.

6.2.1 Guidelines for Test Programs

The most important rule to follow when writing testing samples is:

Look for realism.

This motto means that testing samples must be written with the same strictness as real programs are written. In particular, you should avoid "shortcuts" and simplifications.

Don't just play with the preprocessor if you want to prepare a compilation. For instance, using `cpp` to check whether a header is functional might let your `configure` accept a header which causes some *compiler* error. Do not hesitate to check a header with other headers included before, especially required headers.

Make sure the symbols you use are properly defined, i.e., refrain for simply declaring a function yourself instead of including the proper header.

Test programs should not write to standard output. They should exit with status 0 if the test succeeds, and with status 1 otherwise, so that success can be distinguished easily from a core dump or other failure; segmentation violations and other failures produce a nonzero exit status. Unless you arrange for `exit` to be declared, test programs should `return`, not `exit`, from `main`, because on many systems `exit` is not declared by default.

Test programs can use `#if` or `#ifdef` to check the values of preprocessor macros defined by tests that have already run. For example, if you call `AC_HEADER_STDBOOL`, then later on in '`configure.ac`' you can have a test program that includes '`stdbool.h`' conditionally:

```
#if HAVE_STDBOOL_H
# include <stdbool.h>
#endif
```

If a test program needs to use or create a data file, give it a name that starts with '`conftest`', such as '`conftest.data`'. The `configure` script cleans up by running '`rm -f -r conftest*`' after running test programs and if the script is interrupted.

6.2.2 Test Functions

These days it's safe to assume support for function prototypes (introduced in C89).

Functions that test programs declare should also be conditionalized for C++, which requires '`extern "C"`' prototypes. Make sure to not include any header files containing clashing prototypes.

```
#ifdef __cplusplus
extern "C"
#endif
void *valloc (size_t);
```

If a test program calls a function with invalid parameters (just to see whether it exists), organize the program to ensure that it never invokes that function. You can do this by calling it in another function that is never invoked. You can't do it by putting it after a call to `exit`, because GCC version 2 knows that `exit` never returns and optimizes out any code that follows it in the same block.

If you include any header files, be sure to call the functions relevant to them with the correct number of arguments, even if they are just 0, to avoid compilation errors due to prototypes. GCC version 2 has internal prototypes for several functions that it automatically

inlines; for example, `memcpy`. To avoid errors when checking for them, either pass them the correct number of arguments or redeclare them with a different return type (such as `char`).

6.2.3 Generating Sources

Autoconf provides a set of macros that can be used to generate test source files. They are written to be language generic, i.e., they actually depend on the current language (see Section 6.1 [Language Choice], page 87) to "format" the output properly.

`AC_LANG_CONFTEST (`*source*`)` [Macro]

Save the *source* text in the current test source file: '`conftest.`*extension*' where the *extension* depends on the current language.

Note that the *source* is evaluated exactly once, like regular Autoconf macro arguments, and therefore (i) you may pass a macro invocation, (ii) if not, be sure to double quote if needed.

`AC_LANG_SOURCE (`*source*`)` [Macro]

Expands into the *source*, with the definition of all the `AC_DEFINE` performed so far.

For instance executing (observe the double quotation!):

```
AC_INIT([Hello], [1.0], [bug-hello@example.org])
AC_DEFINE([HELLO_WORLD], ["Hello, World\n"],
  [Greetings string.])
AC_LANG(C)
AC_LANG_CONFTEST(
   [AC_LANG_SOURCE([[const char hw[] = "Hello, World\n";]])])
gcc -E -dD -o - conftest.c
```

results in:

```
...
# 1 "conftest.c"

#define PACKAGE_NAME "Hello"
#define PACKAGE_TARNAME "hello"
#define PACKAGE_VERSION "1.0"
#define PACKAGE_STRING "Hello 1.0"
#define PACKAGE_BUGREPORT "bug-hello@example.org"
#define HELLO_WORLD "Hello, World\n"

const char hw[] = "Hello, World\n";
```

When the test language is Fortran or Erlang, the `AC_DEFINE` definitions are not automatically translated into constants in the source code by this macro.

`AC_LANG_PROGRAM (`*prologue*, *body*`)` [Macro]

Expands into a source file which consists of the *prologue*, and then *body* as body of the main function (e.g., `main` in C). Since it uses `AC_LANG_SOURCE`, the features of the latter are available.

For instance:

```
AC_INIT([Hello], [1.0], [bug-hello@example.org])
AC_DEFINE([HELLO_WORLD], ["Hello, World\n"],
  [Greetings string.])
AC_LANG_CONFTEST(
[AC_LANG_PROGRAM([[const char hw[] = "Hello, World\n";]],
                 [[fputs (hw, stdout);]])])
gcc -E -dD -o - conftest.c
```

results in:

```
...
# 1 "conftest.c"

#define PACKAGE_NAME "Hello"
#define PACKAGE_TARNAME "hello"
#define PACKAGE_VERSION "1.0"
#define PACKAGE_STRING "Hello 1.0"
#define PACKAGE_BUGREPORT "bug-hello@example.org"
#define HELLO_WORLD "Hello, World\n"

const char hw[] = "Hello, World\n";
int
main ()
{
fputs (hw, stdout);
  ;
  return 0;
}
```

In Erlang tests, the created source file is that of an Erlang module called `conftest` (‘`conftest.erl`’). This module defines and exports at least one `start/0` function, which is called to perform the test. The *prologue* is optional code that is inserted between the module header and the `start/0` function definition. *body* is the body of the `start/0` function without the final period (see Section 6.6 [Runtime], page 94, about constraints on this function’s behaviour).

For instance:

```
AC_INIT([Hello], [1.0], [bug-hello@example.org])
AC_LANG(Erlang)
AC_LANG_CONFTEST(
[AC_LANG_PROGRAM([[-define(HELLO_WORLD, "Hello, world!").]],
                 [[io:format("~s~n", [?HELLO_WORLD])]])])
cat conftest.erl
```

results in:

```
-module(conftest).
-export([start/0]).
-define(HELLO_WORLD, "Hello, world!").
start() ->
io:format("~s~n", [?HELLO_WORLD])
```

.

AC_LANG_CALL (*prologue*, *function*) [Macro]

Expands into a source file which consists of the *prologue*, and then a call to the *function* as body of the main function (e.g., `main` in C). Since it uses `AC_LANG_PROGRAM`, the feature of the latter are available.

This function will probably be replaced in the future by a version which would enable specifying the arguments. The use of this macro is not encouraged, as it violates strongly the typing system.

This macro cannot be used for Erlang tests.

AC_LANG_FUNC_LINK_TRY (*function*) [Macro]

Expands into a source file which uses the *function* in the body of the main function (e.g., `main` in C). Since it uses `AC_LANG_PROGRAM`, the features of the latter are available.

As `AC_LANG_CALL`, this macro is documented only for completeness. It is considered to be severely broken, and in the future will be removed in favor of actual function calls (with properly typed arguments).

This macro cannot be used for Erlang tests.

6.3 Running the Preprocessor

Sometimes one might need to run the preprocessor on some source file. *Usually it is a bad idea*, as you typically need to *compile* your project, not merely run the preprocessor on it; therefore you certainly want to run the compiler, not the preprocessor. Resist the temptation of following the easiest path.

Nevertheless, if you need to run the preprocessor, then use `AC_PREPROC_IFELSE`.

The macros described in this section cannot be used for tests in Erlang or Fortran, since those languages require no preprocessor.

AC_PREPROC_IFELSE (*input*, [*action-if-true*], [*action-if-false*]) [Macro]

Run the preprocessor of the current language (see Section 6.1 [Language Choice], page 87) on the *input*, run the shell commands *action-if-true* on success, *action-if-false* otherwise. The *input* can be made by `AC_LANG_PROGRAM` and friends.

This macro uses `CPPFLAGS`, but not `CFLAGS`, because '`-g`', '`-O`', etc. are not valid options to many C preprocessors.

It is customary to report unexpected failures with `AC_MSG_FAILURE`.

For instance:

```
AC_INIT([Hello], [1.0], [bug-hello@example.org])
AC_DEFINE([HELLO_WORLD], ["Hello, World\n"],
  [Greetings string.])
AC_PREPROC_IFELSE(
   [AC_LANG_PROGRAM([[const char hw[] = "Hello, World\n";]],
                    [[fputs (hw, stdout);]])],
   [AC_MSG_RESULT([OK])],
   [AC_MSG_FAILURE([unexpected preprocessor failure])])
```

results in:

```
checking for gcc... gcc
checking for C compiler default output file name... a.out
checking whether the C compiler works... yes
checking whether we are cross compiling... no
checking for suffix of executables...
checking for suffix of object files... o
checking whether we are using the GNU C compiler... yes
checking whether gcc accepts -g... yes
checking for gcc option to accept ISO C89... none needed
checking how to run the C preprocessor... gcc -E
OK
```

The macro `AC_TRY_CPP` (see Section 17.4 [Obsolete Macros], page 209) used to play the role of `AC_PREPROC_IFELSE`, but double quotes its argument, making it impossible to use it to elaborate sources. You are encouraged to get rid of your old use of the macro `AC_TRY_CPP` in favor of `AC_PREPROC_IFELSE`, but, in the first place, are you sure you need to run the *preprocessor* and not the compiler?

`AC_EGREP_HEADER` (*pattern*, *header-file*, *action-if-found*, [*action-if-not-found*]) [Macro]

If the output of running the preprocessor on the system header file *header-file* matches the extended regular expression *pattern*, execute shell commands *action-if-found*, otherwise execute *action-if-not-found*.

`AC_EGREP_CPP` (*pattern*, *program*, [*action-if-found*], [*action-if-not-found*]) [Macro]

program is the text of a C or C++ program, on which shell variable, back quote, and backslash substitutions are performed. If the output of running the preprocessor on *program* matches the extended regular expression *pattern*, execute shell commands *action-if-found*, otherwise execute *action-if-not-found*.

6.4 Running the Compiler

To check for a syntax feature of the current language's (see Section 6.1 [Language Choice], page 87) compiler, such as whether it recognizes a certain keyword, or simply to try some library feature, use `AC_COMPILE_IFELSE` to try to compile a small program that uses that feature.

`AC_COMPILE_IFELSE` (*input*, [*action-if-true*], [*action-if-false*]) [Macro]

Run the compiler and compilation flags of the current language (see Section 6.1 [Language Choice], page 87) on the *input*, run the shell commands *action-if-true* on success, *action-if-false* otherwise. The *input* can be made by `AC_LANG_PROGRAM` and friends.

It is customary to report unexpected failures with `AC_MSG_FAILURE`. This macro does not try to link; use `AC_LINK_IFELSE` if you need to do that (see Section 6.5 [Running the Linker], page 94).

For tests in Erlang, the *input* must be the source code of a module named `conftest`. `AC_COMPILE_IFELSE` generates a '`conftest.beam`' file that can be interpreted by the Erlang virtual machine (`ERL`). It is recommended to use `AC_LANG_PROGRAM` to specify the test program, to ensure that the Erlang module has the right name.

6.5 Running the Linker

To check for a library, a function, or a global variable, Autoconf `configure` scripts try to compile and link a small program that uses it. This is unlike Metaconfig, which by default uses `nm` or `ar` on the C library to try to figure out which functions are available. Trying to link with the function is usually a more reliable approach because it avoids dealing with the variations in the options and output formats of `nm` and `ar` and in the location of the standard libraries. It also allows configuring for cross-compilation or checking a function's runtime behavior if needed. On the other hand, it can be slower than scanning the libraries once, but accuracy is more important than speed.

`AC_LINK_IFELSE` is used to compile test programs to test for functions and global variables. It is also used by `AC_CHECK_LIB` to check for libraries (see Section 5.4 [Libraries], page 46), by adding the library being checked for to `LIBS` temporarily and trying to link a small program.

`AC_LINK_IFELSE` (*input*, [*action-if-true*], [*action-if-false*]) [Macro]

Run the compiler (and compilation flags) and the linker of the current language (see Section 6.1 [Language Choice], page 87) on the *input*, run the shell commands *action-if-true* on success, *action-if-false* otherwise. The *input* can be made by `AC_LANG_PROGRAM` and friends.

`LDFLAGS` and `LIBS` are used for linking, in addition to the current compilation flags.

It is customary to report unexpected failures with `AC_MSG_FAILURE`. This macro does not try to execute the program; use `AC_RUN_IFELSE` if you need to do that (see Section 6.6 [Runtime], page 94).

The `AC_LINK_IFELSE` macro cannot be used for Erlang tests, since Erlang programs are interpreted and do not require linking.

6.6 Checking Runtime Behavior

Sometimes you need to find out how a system performs at runtime, such as whether a given function has a certain capability or bug. If you can, make such checks when your program runs instead of when it is configured. You can check for things like the machine's endianness when your program initializes itself.

If you really need to test for a runtime behavior while configuring, you can write a test program to determine the result, and compile and run it using `AC_RUN_IFELSE`. Avoid running test programs if possible, because this prevents people from configuring your package for cross-compiling.

`AC_RUN_IFELSE` (*input*, [*action-if-true*], [*action-if-false*], [*action-if-cross-compiling*]) [Macro]

If *program* compiles and links successfully and returns an exit status of 0 when executed, run shell commands *action-if-true*. Otherwise, run shell commands *action-if-false*.

The *input* can be made by `AC_LANG_PROGRAM` and friends. `LDFLAGS` and `LIBS` are used for linking, in addition to the compilation flags of the current language (see Section 6.1 [Language Choice], page 87).

If the compiler being used does not produce executables that run on the system where `configure` is being run, then the test program is not run. If the optional shell commands *action-if-cross-compiling* are given, they are run instead. Otherwise, `configure` prints an error message and exits.

In the *action-if-false* section, the failing exit status is available in the shell variable '`$?`'. This exit status might be that of a failed compilation, or it might be that of a failed program execution.

It is customary to report unexpected failures with `AC_MSG_FAILURE`.

Try to provide a pessimistic default value to use when cross-compiling makes runtime tests impossible. You do this by passing the optional last argument to `AC_RUN_IFELSE`. `autoconf` prints a warning message when creating `configure` each time it encounters a call to `AC_RUN_IFELSE` with no *action-if-cross-compiling* argument given. You may ignore the warning, though users cannot configure your package for cross-compiling. A few of the macros distributed with Autoconf produce this warning message.

To configure for cross-compiling you can also choose a value for those parameters based on the canonical system name (see Chapter 13 [Manual Configuration], page 189). Alternatively, set up a test results cache file with the correct values for the host system (see Section 7.4 [Caching Results], page 102).

To provide a default for calls of `AC_RUN_IFELSE` that are embedded in other macros, including a few of the ones that come with Autoconf, you can test whether the shell variable `cross_compiling` is set to '`yes`', and then use an alternate method to get the results instead of calling the macros.

A C or C++ runtime test should be portable. See Chapter 12 [Portable C and C++], page 185.

Erlang tests must exit themselves the Erlang VM by calling the `halt/1` function: the given status code is used to determine the success of the test (status is `0`) or its failure (status is different than `0`), as explained above. It must be noted that data output through the standard output (e.g. using `io:format/2`) may be truncated when halting the VM. Therefore, if a test must output configuration information, it is recommended to create and to output data into the temporary file named '`conftest.out`', using the functions of module `file`. The `conftest.out` file is automatically deleted by the `AC_RUN_IFELSE` macro. For instance, a simplified implementation of Autoconf's `AC_ERLANG_SUBST_LIB_DIR` macro is:

```
AC_INIT([LibdirTest], [1.0], [bug-libdirtest@example.org])
AC_ERLANG_NEED_ERL
AC_LANG(Erlang)
AC_RUN_IFELSE(
  [AC_LANG_PROGRAM([], [dnl
    file:write_file("conftest.out", code:lib_dir()),
    halt(0)])],
  [echo "code:lib_dir() returned: `cat conftest.out`"],
  [AC_MSG_FAILURE([test Erlang program execution failed])])
```

6.7 Systemology

This section aims at presenting some systems and pointers to documentation. It may help you addressing particular problems reported by users.

Posix-conforming systems (`http://www.opengroup.org/susv3`) are derived from the Unix operating system (`http://www.bell-labs.com/history/unix/`).

The Rosetta Stone for Unix (`http://bhami.com/rosetta.html`) contains a table correlating the features of various Posix-conforming systems. Unix History (`http://www.levenez.com/unix/`) is a simplified diagram of how many Unix systems were derived from each other.

The Heirloom Project (`http://heirloom.sourceforge.net/`) provides some variants of traditional implementations of Unix utilities.

Darwin
: Darwin is also known as Mac OS X. Beware that the file system *can* be case-preserving, but case insensitive. This can cause nasty problems, since for instance the installation attempt for a package having an '`INSTALL`' file can result in '`make install`' report that nothing was to be done!

  That's all dependent on whether the file system is a UFS (case sensitive) or HFS+ (case preserving). By default Apple wants you to install the OS on HFS+. Unfortunately, there are some pieces of software which really need to be built on UFS. We may want to rebuild Darwin to have both UFS and HFS+ available (and put the /local/build tree on the UFS).

QNX 4.25
: QNX is a realtime operating system running on Intel architecture meant to be scalable from the small embedded systems to the hundred processor supercomputer. It claims to be Posix certified. More information is available on the QNX home page (`http://www.qnx.com/`).

Tru64
: Documentation of several versions of Tru64 (`http://h30097.www3.hp.com/docs/`) is available in different formats.

Unix version 7
: Officially this was called the "Seventh Edition" of "the UNIX time-sharing system" but we use the more-common name "Unix version 7". Documentation is available in the Unix Seventh Edition Manual (`http://plan9.bell-labs.com/7thEdMan/`). Previous versions of Unix are called "Unix version 6", etc., but they were not as widely used.

6.8 Multiple Cases

Some operations are accomplished in several possible ways, depending on the OS variant. Checking for them essentially requires a "case statement". Autoconf does not directly provide one; however, it is easy to simulate by using a shell variable to keep track of whether a way to perform the operation has been found yet.

Here is an example that uses the shell variable `fstype` to keep track of whether the remaining cases need to be checked.

```
AC_MSG_CHECKING([how to get file system type])
fstype=no
# The order of these tests is important.
AC_COMPILE_IFELSE([AC_LANG_PROGRAM([[#include <sys/statvfs.h>
#include <sys/fstyp.h>]])],
                  [AC_DEFINE([FSTYPE_STATVFS], [1],
                     [Define if statvfs exists.])
                   fstype=SVR4])
if test $fstype = no; then
  AC_COMPILE_IFELSE([AC_LANG_PROGRAM([[#include <sys/statfs.h>
#include <sys/fstyp.h>]])],
                  [AC_DEFINE([FSTYPE_USG_STATFS], [1],
                     [Define if USG statfs.])
                   fstype=SVR3])
fi
if test $fstype = no; then
  AC_COMPILE_IFELSE([AC_LANG_PROGRAM([[#include <sys/statfs.h>
#include <sys/vmount.h>]])]),
                  [AC_DEFINE([FSTYPE_AIX_STATFS], [1],
                     [Define if AIX statfs.])
                   fstype=AIX])
fi
# (more cases omitted here)
AC_MSG_RESULT([$fstype])
```

7 Results of Tests

Once `configure` has determined whether a feature exists, what can it do to record that information? There are four sorts of things it can do: define a C preprocessor symbol, set a variable in the output files, save the result in a cache file for future `configure` runs, and print a message letting the user know the result of the test.

7.1 Defining C Preprocessor Symbols

A common action to take in response to a feature test is to define a C preprocessor symbol indicating the results of the test. That is done by calling `AC_DEFINE` or `AC_DEFINE_UNQUOTED`.

By default, `AC_OUTPUT` places the symbols defined by these macros into the output variable `DEFS`, which contains an option '`-D`*symbol*`=`*value*' for each symbol defined. Unlike in Autoconf version 1, there is no variable `DEFS` defined while `configure` is running. To check whether Autoconf macros have already defined a certain C preprocessor symbol, test the value of the appropriate cache variable, as in this example:

```
AC_CHECK_FUNC([vprintf], [AC_DEFINE([HAVE_VPRINTF], [1],
                          [Define if vprintf exists.])])
if test "$ac_cv_func_vprintf" != yes; then
  AC_CHECK_FUNC([_doprnt], [AC_DEFINE([HAVE_DOPRNT], [1],
                            [Define if _doprnt exists.])])
fi
```

If `AC_CONFIG_HEADERS` has been called, then instead of creating `DEFS`, `AC_OUTPUT` creates a header file by substituting the correct values into `#define` statements in a template file. See Section 4.8 [Configuration Headers], page 31, for more information about this kind of output.

`AC_DEFINE` (*variable*, *value*, [*description*]) [Macro]
`AC_DEFINE` (*variable*) [Macro]

Define the C preprocessor variable *variable* to *value* (verbatim). *value* should not contain literal newlines, and if you are not using `AC_CONFIG_HEADERS` it should not contain any '`#`' characters, as `make` tends to eat them. To use a shell variable, use `AC_DEFINE_UNQUOTED` instead. *description* is only useful if you are using `AC_CONFIG_HEADERS`. In this case, *description* is put into the generated '`config.h.in`' as the comment before the macro define. The following example defines the C preprocessor variable `EQUATION` to be the string constant '`"$a > $b"`':

```
AC_DEFINE([EQUATION], ["$a > $b"],
  [Equation string.])
```

If neither *value* nor *description* are given, then *value* defaults to 1 instead of to the empty string. This is for backwards compatibility with older versions of Autoconf, but this usage is obsolescent and may be withdrawn in future versions of Autoconf.

If the *variable* is a literal string, it is passed to `m4_pattern_allow` (see Section 8.3.5 [Forbidden Patterns], page 120).

`AC_DEFINE_UNQUOTED` (*variable*, *value*, [*description*]) [Macro]

`AC_DEFINE_UNQUOTED` (*variable*) [Macro]

Like `AC_DEFINE`, but three shell expansions are performed—once—on *variable* and *value*: variable expansion (‘`$`’), command substitution (‘` `’), and backslash escaping (‘`\`’). Single and double quote characters in the value have no special meaning. Use this macro instead of `AC_DEFINE` when *variable* or *value* is a shell variable. Examples:

```
AC_DEFINE_UNQUOTED([config_machfile], ["$machfile"],
  [Configuration machine file.])
AC_DEFINE_UNQUOTED([GETGROUPS_T], [$ac_cv_type_getgroups],
  [getgroups return type.])
AC_DEFINE_UNQUOTED([$ac_tr_hdr], [1],
  [Translated header name.])
```

Due to a syntactical bizarreness of the Bourne shell, do not use semicolons to separate `AC_DEFINE` or `AC_DEFINE_UNQUOTED` calls from other macro calls or shell code; that can cause syntax errors in the resulting `configure` script. Use either blanks or newlines. That is, do this:

```
AC_CHECK_HEADER([elf.h],
  [AC_DEFINE([SVR4], [1], [System V Release 4]) LIBS="-lelf $LIBS"])
```

or this:

```
AC_CHECK_HEADER([elf.h],
  [AC_DEFINE([SVR4], [1], [System V Release 4])
   LIBS="-lelf $LIBS"])
```

instead of this:

```
AC_CHECK_HEADER([elf.h],
  [AC_DEFINE([SVR4], [1], [System V Release 4]); LIBS="-lelf $LIBS"])
```

7.2 Setting Output Variables

Another way to record the results of tests is to set *output variables*, which are shell variables whose values are substituted into files that `configure` outputs. The two macros below create new output variables. See Section 4.7.1 [Preset Output Variables], page 23, for a list of output variables that are always available.

`AC_SUBST` (*variable*, [*value*]) [Macro]

Create an output variable from a shell variable. Make `AC_OUTPUT` substitute the variable *variable* into output files (typically one or more makefiles). This means that `AC_OUTPUT` replaces instances of ‘`@`*variable*`@`’ in input files with the value that the shell variable *variable* has when `AC_OUTPUT` is called. The value can contain newlines. The substituted value is not rescanned for more output variables; occurrences of ‘`@`*variable*`@`’ in the value are inserted literally into the output file. (The algorithm uses the special marker `|#_!!_#|` internally, so the substituted value cannot contain `|#_!!_#|`.)

If *value* is given, in addition assign it to *variable*.

The string *variable* is passed to `m4_pattern_allow` (see Section 8.3.5 [Forbidden Patterns], page 120).

`AC_SUBST_FILE (variable)` [Macro]

Another way to create an output variable from a shell variable. Make `AC_OUTPUT` insert (without substitutions) the contents of the file named by shell variable *variable* into output files. This means that `AC_OUTPUT` replaces instances of '`@variable@`' in output files (such as '`Makefile.in`') with the contents of the file that the shell variable *variable* names when `AC_OUTPUT` is called. Set the variable to '`/dev/null`' for cases that do not have a file to insert. This substitution occurs only when the '`@variable@`' is on a line by itself, optionally surrounded by spaces and tabs. The substitution replaces the whole line, including the spaces, tabs, and the terminating newline.

This macro is useful for inserting makefile fragments containing special dependencies or other `make` directives for particular host or target types into makefiles. For example, '`configure.ac`' could contain:

```
AC_SUBST_FILE([host_frag])
host_frag=$srcdir/conf/sun4.mh
```

and then a '`Makefile.in`' could contain:

```
@host_frag@
```

The string *variable* is passed to `m4_pattern_allow` (see Section 8.3.5 [Forbidden Patterns], page 120).

Running `configure` in varying environments can be extremely dangerous. If for instance the user runs '`CC=bizarre-cc ./configure`', then the cache, '`config.h`', and many other output files depend upon `bizarre-cc` being the C compiler. If for some reason the user runs `./configure` again, or if it is run via '`./config.status --recheck`', (See Section 4.7.5 [Automatic Remaking], page 30, and see Chapter 16 [config.status Invocation], page 205), then the configuration can be inconsistent, composed of results depending upon two different compilers.

Environment variables that affect this situation, such as '`CC`' above, are called *precious variables*, and can be declared as such by `AC_ARG_VAR`.

`AC_ARG_VAR (variable, description)` [Macro]

Declare *variable* is a precious variable, and include its *description* in the variable section of '`./configure --help`'.

Being precious means that

- *variable* is substituted via `AC_SUBST`.
- The value of *variable* when `configure` was launched is saved in the cache, including if it was not specified on the command line but via the environment. Indeed, while `configure` can notice the definition of `CC` in '`./configure CC=bizarre-cc`', it is impossible to notice it in '`CC=bizarre-cc ./configure`', which, unfortunately, is what most users do.

  We emphasize that it is the *initial* value of *variable* which is saved, not that found during the execution of `configure`. Indeed, specifying '`./configure FOO=foo`' and letting '`./configure`' guess that `FOO` is `foo` can be two different things.
- *variable* is checked for consistency between two `configure` runs. For instance:

```
$ ./configure --silent --config-cache
$ CC=cc ./configure --silent --config-cache
configure: error: 'CC' was not set in the previous run
configure: error: changes in the environment can compromise \
the build
configure: error: run 'make distclean' and/or \
'rm config.cache' and start over
```

and similarly if the variable is unset, or if its content is changed.

– *variable* is kept during automatic reconfiguration (see Chapter 16 [config.status Invocation], page 205) as if it had been passed as a command line argument, including when no cache is used:

```
$ CC=/usr/bin/cc ./configure undeclared_var=raboof --silent
$ ./config.status --recheck
running /bin/sh ./configure undeclared_var=raboof --silent \
  CC=/usr/bin/cc  --no-create --no-recursion
```

7.3 Special Characters in Output Variables

Many output variables are intended to be evaluated both by `make` and by the shell. Some characters are expanded differently in these two contexts, so to avoid confusion these variables' values should not contain any of the following characters:

```
" # $ & ' ( ) * ; < > ? [ \ ^ ` |
```

Also, these variables' values should neither contain newlines, nor start with '`~`', nor contain white space or '`:`' immediately followed by '`~`'. The values can contain nonempty sequences of white space characters like tabs and spaces, but each such sequence might arbitrarily be replaced by a single space during substitution.

These restrictions apply both to the values that `configure` computes, and to the values set directly by the user. For example, the following invocations of `configure` are problematic, since they attempt to use special characters within `CPPFLAGS` and white space within `$(srcdir)`:

```
CPPFLAGS='-DOUCH="&\"#$*?"' '../My Source/ouch-1.0/configure'

'../My Source/ouch-1.0/configure' CPPFLAGS='-DOUCH="&\"#$*?"'
```

7.4 Caching Results

To avoid checking for the same features repeatedly in various `configure` scripts (or in repeated runs of one script), `configure` can optionally save the results of many checks in a *cache file* (see Section 7.4.2 [Cache Files], page 104). If a `configure` script runs with caching enabled and finds a cache file, it reads the results of previous runs from the cache and avoids rerunning those checks. As a result, `configure` can then run much faster than if it had to perform all of the checks every time.

`AC_CACHE_VAL` (*cache-id*, *commands-to-set-it*) [Macro]

Ensure that the results of the check identified by *cache-id* are available. If the results of the check were in the cache file that was read, and `configure` was not given the

'`--quiet`' or '`--silent`' option, print a message saying that the result was cached; otherwise, run the shell commands *commands-to-set-it*. If the shell commands are run to determine the value, the value is saved in the cache file just before `configure` creates its output files. See Section 7.4.1 [Cache Variable Names], page 104, for how to choose the name of the *cache-id* variable.

The *commands-to-set-it must have no side effects* except for setting the variable *cache-id*, see below.

`AC_CACHE_CHECK` (*message*, *cache-id*, *commands-to-set-it*) [Macro]
A wrapper for `AC_CACHE_VAL` that takes care of printing the messages. This macro provides a convenient shorthand for the most common way to use these macros. It calls `AC_MSG_CHECKING` for *message*, then `AC_CACHE_VAL` with the *cache-id* and *commands* arguments, and `AC_MSG_RESULT` with *cache-id*.

The *commands-to-set-it must have no side effects* except for setting the variable *cache-id*, see below.

It is common to find buggy macros using `AC_CACHE_VAL` or `AC_CACHE_CHECK`, because people are tempted to call `AC_DEFINE` in the *commands-to-set-it*. Instead, the code that *follows* the call to `AC_CACHE_VAL` should call `AC_DEFINE`, by examining the value of the cache variable. For instance, the following macro is broken:

```
AC_DEFUN([AC_SHELL_TRUE],
[AC_CACHE_CHECK([whether true(1) works], [ac_cv_shell_true_works],
                [ac_cv_shell_true_works=no
                 (true) 2>/dev/null && ac_cv_shell_true_works=yes
                 if test "$ac_cv_shell_true_works" = yes; then
                   AC_DEFINE([TRUE_WORKS], [1],
                             [Define if `true(1)' works properly.])
                 fi])
])
```

This fails if the cache is enabled: the second time this macro is run, `TRUE_WORKS` *will not be defined*. The proper implementation is:

```
AC_DEFUN([AC_SHELL_TRUE],
[AC_CACHE_CHECK([whether true(1) works], [ac_cv_shell_true_works],
                [ac_cv_shell_true_works=no
                 (true) 2>/dev/null && ac_cv_shell_true_works=yes])
 if test "$ac_cv_shell_true_works" = yes; then
   AC_DEFINE([TRUE_WORKS], [1],
             [Define if `true(1)' works properly.])
 fi
])
```

Also, *commands-to-set-it* should not print any messages, for example with `AC_MSG_CHECKING`; do that before calling `AC_CACHE_VAL`, so the messages are printed regardless of whether the results of the check are retrieved from the cache or determined by running the shell commands.

7.4.1 Cache Variable Names

The names of cache variables should have the following format:

*package-prefix*_cv_*value-type*_*specific-value*_[*additional-options*]

for example, '`ac_cv_header_stat_broken`' or '`ac_cv_prog_gcc_traditional`'. The parts of the variable name are:

package-prefix
: An abbreviation for your package or organization; the same prefix you begin local Autoconf macros with, except lowercase by convention. For cache values used by the distributed Autoconf macros, this value is '`ac`'.

`_cv_`
: Indicates that this shell variable is a cache value. This string *must* be present in the variable name, including the leading underscore.

value-type
: A convention for classifying cache values, to produce a rational naming system. The values used in Autoconf are listed in Section 9.2 [Macro Names], page 125.

specific-value
: Which member of the class of cache values this test applies to. For example, which function ('`alloca`'), program ('`gcc`'), or output variable ('`INSTALL`').

additional-options
: Any particular behavior of the specific member that this test applies to. For example, '`broken`' or '`set`'. This part of the name may be omitted if it does not apply.

The values assigned to cache variables may not contain newlines. Usually, their values are Boolean ('`yes`' or '`no`') or the names of files or functions; so this is not an important restriction.

7.4.2 Cache Files

A cache file is a shell script that caches the results of configure tests run on one system so they can be shared between configure scripts and configure runs. It is not useful on other systems. If its contents are invalid for some reason, the user may delete or edit it.

By default, `configure` uses no cache file, to avoid problems caused by accidental use of stale cache files.

To enable caching, `configure` accepts '`--config-cache`' (or '`-C`') to cache results in the file '`config.cache`'. Alternatively, '`--cache-file=`*file*' specifies that *file* be the cache file. The cache file is created if it does not exist already. When `configure` calls `configure` scripts in subdirectories, it uses the '`--cache-file`' argument so that they share the same cache. See Section 4.11 [Subdirectories], page 36, for information on configuring subdirectories with the `AC_CONFIG_SUBDIRS` macro.

'`config.status`' only pays attention to the cache file if it is given the '`--recheck`' option, which makes it rerun `configure`.

It is wrong to try to distribute cache files for particular system types. There is too much room for error in doing that, and too much administrative overhead in maintaining them. For any features that can't be guessed automatically, use the standard method of the canonical system type and linking files (see Chapter 13 [Manual Configuration], page 189).

The site initialization script can specify a site-wide cache file to use, instead of the usual per-program cache. In this case, the cache file gradually accumulates information whenever someone runs a new `configure` script. (Running `configure` merges the new cache results with the existing cache file.) This may cause problems, however, if the system configuration (e.g., the installed libraries or compilers) changes and the stale cache file is not deleted.

7.4.3 Cache Checkpointing

If your configure script, or a macro called from '`configure.ac`', happens to abort the configure process, it may be useful to checkpoint the cache a few times at key points using `AC_CACHE_SAVE`. Doing so reduces the amount of time it takes to rerun the configure script with (hopefully) the error that caused the previous abort corrected.

`AC_CACHE_LOAD` [Macro]
: Loads values from existing cache file, or creates a new cache file if a cache file is not found. Called automatically from `AC_INIT`.

`AC_CACHE_SAVE` [Macro]
: Flushes all cached values to the cache file. Called automatically from `AC_OUTPUT`, but it can be quite useful to call `AC_CACHE_SAVE` at key points in '`configure.ac`'.

For instance:

```
... AC_INIT, etc. ...
# Checks for programs.
AC_PROG_CC
AC_PROG_AWK
... more program checks ...
AC_CACHE_SAVE

# Checks for libraries.
AC_CHECK_LIB([nsl], [gethostbyname])
AC_CHECK_LIB([socket], [connect])
... more lib checks ...
AC_CACHE_SAVE

# Might abort...
AM_PATH_GTK([1.0.2], [], [AC_MSG_ERROR([GTK not in path])])
AM_PATH_GTKMM([0.9.5], [], [AC_MSG_ERROR([GTK not in path])])
... AC_OUTPUT, etc. ...
```

7.5 Printing Messages

`configure` scripts need to give users running them several kinds of information. The following macros print messages in ways appropriate for each kind. The arguments to all of them get enclosed in shell double quotes, so the shell performs variable and back-quote substitution on them.

These macros are all wrappers around the `echo` shell command. They direct output to the appropriate file descriptor (see Section 8.5 [File Descriptor Macros], page 122). `configure` scripts should rarely need to run `echo` directly to print messages for the user.

Using these macros makes it easy to change how and when each kind of message is printed; such changes need only be made to the macro definitions and all the callers change automatically.

To diagnose static issues, i.e., when `autoconf` is run, see Section 9.3 [Reporting Messages], page 126.

`AC_MSG_CHECKING (`*`feature-description`*`)` [Macro]

Notify the user that `configure` is checking for a particular feature. This macro prints a message that starts with '`checking `' and ends with '`...`' and no newline. It must be followed by a call to `AC_MSG_RESULT` to print the result of the check and the newline. The *feature-description* should be something like '`whether the Fortran compiler accepts C++ comments`' or '`for c89`'.

This macro prints nothing if `configure` is run with the '`--quiet`' or '`--silent`' option.

`AC_MSG_RESULT (`*`result-description`*`)` [Macro]

Notify the user of the results of a check. *result-description* is almost always the value of the cache variable for the check, typically '`yes`', '`no`', or a file name. This macro should follow a call to `AC_MSG_CHECKING`, and the *result-description* should be the completion of the message printed by the call to `AC_MSG_CHECKING`.

This macro prints nothing if `configure` is run with the '`--quiet`' or '`--silent`' option.

`AC_MSG_NOTICE (`*`message`*`)` [Macro]

Deliver the *message* to the user. It is useful mainly to print a general description of the overall purpose of a group of feature checks, e.g.,

```
AC_MSG_NOTICE([checking if stack overflow is detectable])
```

This macro prints nothing if `configure` is run with the '`--quiet`' or '`--silent`' option.

`AC_MSG_ERROR (`*`error-description`*`, [`*`exit-status`*`])` [Macro]

Notify the user of an error that prevents `configure` from completing. This macro prints an error message to the standard error output and exits `configure` with *exit-status* (1 by default). *error-description* should be something like '`invalid value $HOME for \$HOME`'.

The *error-description* should start with a lower-case letter, and "cannot" is preferred to "can't".

`AC_MSG_FAILURE (`*`error-description`*`, [`*`exit-status`*`])` [Macro]

This `AC_MSG_ERROR` wrapper notifies the user of an error that prevents `configure` from completing *and* that additional details are provided in '`config.log`'. This is typically used when abnormal results are found during a compilation.

`AC_MSG_WARN (`*`problem-description`*`)` [Macro]

Notify the `configure` user of a possible problem. This macro prints the message to the standard error output; `configure` continues running afterward, so macros that call `AC_MSG_WARN` should provide a default (back-up) behavior for the situations they warn about. *problem-description* should be something like '`ln -s seems to make hard links`'.

8 Programming in M4

Autoconf is written on top of two layers: *M4sugar*, which provides convenient macros for pure M4 programming, and *M4sh*, which provides macros dedicated to shell script generation.

As of this version of Autoconf, these two layers are still experimental, and their interface might change in the future. As a matter of fact, *anything that is not documented must not be used*.

8.1 M4 Quotation

The most common problem with existing macros is an improper quotation. This section, which users of Autoconf can skip, but which macro writers *must* read, first justifies the quotation scheme that was chosen for Autoconf and then ends with a rule of thumb. Understanding the former helps one to follow the latter.

8.1.1 Active Characters

To fully understand where proper quotation is important, you first need to know what the special characters are in Autoconf: '`#`' introduces a comment inside which no macro expansion is performed, '`,`' separates arguments, '`[`' and '`]`' are the quotes themselves, and finally '`(`' and '`)`' (which M4 tries to match by pairs).

In order to understand the delicate case of macro calls, we first have to present some obvious failures. Below they are "obvious-ified", but when you find them in real life, they are usually in disguise.

Comments, introduced by a hash and running up to the newline, are opaque tokens to the top level: active characters are turned off, and there is no macro expansion:

```
# define([def], ine)
⇒# define([def], ine)
```

Each time there can be a macro expansion, there is a quotation expansion, i.e., one level of quotes is stripped:

```
int tab[10];
⇒int tab10;
[int tab[10];]
⇒int tab[10];
```

Without this in mind, the reader might try hopelessly to use her macro `array`:

```
define([array], [int tab[10];])
array
⇒int tab10;
[array]
⇒array
```

How can you correctly output the intended results[1]?

[1] Using `defn`.

8.1.2 One Macro Call

Let's proceed on the interaction between active characters and macros with this small macro, which just returns its first argument:

```
define([car], [$1])
```

The two pairs of quotes above are not part of the arguments of `define`; rather, they are understood by the top level when it tries to find the arguments of `define`. Therefore, assuming `car` is not already defined, it is equivalent to write:

```
define(car, $1)
```

But, while it is acceptable for a '`configure.ac`' to avoid unnecessary quotes, it is bad practice for Autoconf macros which must both be more robust and also advocate perfect style.

At the top level, there are only two possibilities: either you quote or you don't:

```
car(foo, bar, baz)
⇒foo
[car(foo, bar, baz)]
⇒car(foo, bar, baz)
```

Let's pay attention to the special characters:

```
car(#)
error EOF in argument list
```

The closing parenthesis is hidden in the comment; with a hypothetical quoting, the top level understood it this way:

```
car([#)]
```

Proper quotation, of course, fixes the problem:

```
car([#])
⇒#
```

Here are more examples:

```
car(foo, bar)
⇒foo
car([foo, bar])
⇒foo, bar
car((foo, bar))
⇒(foo, bar)
car([(foo], [bar)])
⇒(foo
define([a], [b])
⇒
car(a)
⇒b
car([a])
⇒b
car([[a]])
⇒a
car([[[a]]])
```

```
⇒[a]
```

With this in mind, we can explore the cases where macros invoke macros...

8.1.3 Quotation and Nested Macros

The examples below use the following macros:

```
define([car], [$1])
define([active], [ACT, IVE])
define([array], [int tab[10]])
```

Each additional embedded macro call introduces other possible interesting quotations:

```
car(active)
⇒ACT
car([active])
⇒ACT, IVE
car([[active]])
⇒active
```

In the first case, the top level looks for the arguments of `car`, and finds '`active`'. Because M4 evaluates its arguments before applying the macro, '`active`' is expanded, which results in:

```
car(ACT, IVE)
⇒ACT
```

In the second case, the top level gives '`active`' as first and only argument of `car`, which results in:

```
active
⇒ACT, IVE
```

i.e., the argument is evaluated *after* the macro that invokes it. In the third case, `car` receives '`[active]`', which results in:

```
[active]
⇒active
```

exactly as we already saw above.

The example above, applied to a more realistic example, gives:

```
car(int tab[10];)
⇒int tab10;
car([int tab[10];])
⇒int tab10;
car([[int tab[10];]])
⇒int tab[10];
```

Huh? The first case is easily understood, but why is the second wrong, and the third right? To understand that, you must know that after M4 expands a macro, the resulting text is immediately subjected to macro expansion and quote removal. This means that the quote removal occurs twice—first before the argument is passed to the `car` macro, and second after the `car` macro expands to the first argument.

As the author of the Autoconf macro `car`, you then consider it to be incorrect that your users have to double-quote the arguments of `car`, so you "fix" your macro. Let's call it `qar` for quoted car:

```
define([qar], [[$1]])
```

and check that `qar` is properly fixed:

```
qar([int tab[10];])
⇒int tab[10];
```

Ahhh! That's much better.

But note what you've done: now that the arguments are literal strings, if the user wants to use the results of expansions as arguments, she has to use an *unquoted* macro call:

```
qar(active)
⇒ACT
```

where she wanted to reproduce what she used to do with `car`:

```
car([active])
⇒ACT, IVE
```

Worse yet: she wants to use a macro that produces a set of `cpp` macros:

```
define([my_includes], [#include <stdio.h>])
car([my_includes])
⇒#include <stdio.h>
qar(my_includes)
error EOF in argument list
```

This macro, `qar`, because it double quotes its arguments, forces its users to leave their macro calls unquoted, which is dangerous. Commas and other active symbols are interpreted by M4 before they are given to the macro, often not in the way the users expect. Also, because `qar` behaves differently from the other macros, it's an exception that should be avoided in Autoconf.

8.1.4 `changequote` is Evil

The temptation is often high to bypass proper quotation, in particular when it's late at night. Then, many experienced Autoconf hackers finally surrender to the dark side of the force and use the ultimate weapon: `changequote`.

The M4 builtin `changequote` belongs to a set of primitives that allow one to adjust the syntax of the language to adjust it to one's needs. For instance, by default M4 uses ‘`‘`’ and ‘`’`’ as quotes, but in the context of shell programming (and actually of most programming languages), that's about the worst choice one can make: because of strings and back-quoted expressions in shell code (such as ‘`‘this’`’ and ‘`‘that‘`’), because of literal characters in usual programming languages (as in ‘`’0’`’), there are many unbalanced ‘`‘`’ and ‘`’`’. Proper M4 quotation then becomes a nightmare, if not impossible. In order to make M4 useful in such a context, its designers have equipped it with `changequote`, which makes it possible to choose another pair of quotes. M4sugar, M4sh, Autoconf, and Autotest all have chosen to use ‘`[`’ and ‘`]`’. Not especially because they are unlikely characters, but *because they are characters unlikely to be unbalanced.*

There are other magic primitives, such as `changecom` to specify what syntactic forms are comments (it is common to see ‘`changecom(<!--, -->)`’ when M4 is used to produce HTML pages), `changeword` and `changesyntax` to change other syntactic details (such as the character to denote the *n*th argument, ‘`$`’ by default, the parenthesis around arguments, etc.).

These primitives are really meant to make M4 more useful for specific domains: they should be considered like command line options: '`--quotes`', '`--comments`', '`--words`', and '`--syntax`'. Nevertheless, they are implemented as M4 builtins, as it makes M4 libraries self contained (no need for additional options).

There lies the problem...

The problem is that it is then tempting to use them in the middle of an M4 script, as opposed to its initialization. This, if not carefully thought out, can lead to disastrous effects: *you are changing the language in the middle of the execution*. Changing and restoring the syntax is often not enough: if you happened to invoke macros in between, these macros are lost, as the current syntax is probably not the one they were implemented with.

8.1.5 Quadrigraphs

When writing an Autoconf macro you may occasionally need to generate special characters that are difficult to express with the standard Autoconf quoting rules. For example, you may need to output the regular expression '`[^[]`', which matches any character other than '`[`'. This expression contains unbalanced brackets so it cannot be put easily into an M4 macro.

You can work around this problem by using one of the following *quadrigraphs*:

'`@<:@`' '`[`'

'`@:>@`' '`]`'

'`@S|@`' '`$`'

'`@%:@`' '`#`'

'`@&t@`' Expands to nothing.

Quadrigraphs are replaced at a late stage of the translation process, after `m4` is run, so they do not get in the way of M4 quoting. For example, the string '`^@<:@`', independently of its quotation, appears as '`^[`' in the output.

The empty quadrigraph can be used:

- to mark trailing spaces explicitly

  Trailing spaces are smashed by `autom4te`. This is a feature.

- to produce other quadrigraphs

  For instance '`@<@&t@:@`' produces '`@<:@`'.

- to escape *occurrences* of forbidden patterns

  For instance you might want to mention `AC_FOO` in a comment, while still being sure that `autom4te` still catches unexpanded '`AC_*`'. Then write '`AC@&t@_FOO`'.

The name '`@&t@`' was suggested by Paul Eggert:

> I should give some credit to the '`@&t@`' pun. The '`&`' is my own invention, but the '`t`' came from the source code of the ALGOL68C compiler, written by Steve Bourne (of Bourne shell fame), and which used '`mt`' to denote the empty string. In C, it would have looked like something like:

```
char const mt[] = "";
```

but of course the source code was written in Algol 68.

I don't know where he got '`mt`' from: it could have been his own invention, and I suppose it could have been a common pun around the Cambridge University computer lab at the time.

8.1.6 Quotation Rule Of Thumb

To conclude, the quotation rule of thumb is:

One pair of quotes per pair of parentheses.

Never over-quote, never under-quote, in particular in the definition of macros. In the few places where the macros need to use brackets (usually in C program text or regular expressions), properly quote *the arguments*!

It is common to read Autoconf programs with snippets like:

```
AC_TRY_LINK(
changequote(<<, >>)dnl
<<#include <time.h>
#ifndef tzname /* For SGI.  */
extern char *tzname[]; /* RS6000 and others reject char **tzname.  */
#endif>>,
changequote([, ])dnl
[atoi (*tzname);], ac_cv_var_tzname=yes, ac_cv_var_tzname=no)
```

which is incredibly useless since `AC_TRY_LINK` is *already* double quoting, so you just need:

```
AC_TRY_LINK(
[#include <time.h>
#ifndef tzname /* For SGI.  */
extern char *tzname[]; /* RS6000 and others reject char **tzname.  */
#endif],
            [atoi (*tzname);],
            [ac_cv_var_tzname=yes],
            [ac_cv_var_tzname=no])
```

The M4-fluent reader might note that these two examples are rigorously equivalent, since M4 swallows both the '`changequote(<<, >>)`' and '`<<`' '`>>`' when it *collects* the arguments: these quotes are not part of the arguments!

Simplified, the example above is just doing this:

```
changequote(<<, >>)dnl
<<[]>>
changequote([, ])dnl
```

instead of simply:

```
[[]]
```

With macros that do not double quote their arguments (which is the rule), double-quote the (risky) literals:

```
AC_LINK_IFELSE([AC_LANG_PROGRAM(
[[#include <time.h>
#ifndef tzname /* For SGI.  */
```

```
extern char *tzname[]; /* RS6000 and others reject char **tzname.  */
#endif]],
                                    [atoi (*tzname);])],
               [ac_cv_var_tzname=yes],
               [ac_cv_var_tzname=no])
```

Please note that the macro `AC_TRY_LINK` is obsolete, so you really should be using `AC_LINK_IFELSE` instead.

See Section 8.1.5 [Quadrigraphs], page 111, for what to do if you run into a hopeless case where quoting does not suffice.

When you create a `configure` script using newly written macros, examine it carefully to check whether you need to add more quotes in your macros. If one or more words have disappeared in the M4 output, you need more quotes. When in doubt, quote.

However, it's also possible to put on too many layers of quotes. If this happens, the resulting `configure` script may contain unexpanded macros. The `autoconf` program checks for this problem by looking for the string '`AC_`' in '`configure`'. However, this heuristic does not work in general: for example, it does not catch overquoting in `AC_DEFINE` descriptions.

8.2 Using `autom4te`

The Autoconf suite, including M4sugar, M4sh, and Autotest, in addition to Autoconf per se, heavily rely on M4. All these different uses revealed common needs factored into a layer over M4: `autom4te`[2].

`autom4te` is a preprocessor that is like `m4`. It supports M4 extensions designed for use in tools like Autoconf.

8.2.1 Invoking `autom4te`

The command line arguments are modeled after M4's:

```
autom4te options files
```

where the *files* are directly passed to `m4`. By default, GNU M4 is found during configuration, but the environment variable `M4` can be set to tell `autom4te` where to look. In addition to the regular expansion, it handles the replacement of the quadrigraphs (see Section 8.1.5 [Quadrigraphs], page 111), and of '`__oline__`', the current line in the output. It supports an extended syntax for the *files*:

'*file*`.m4f`'
: This file is an M4 frozen file. Note that *all the previous files are ignored*. See the option '`--melt`' for the rationale.

'*file*`?`'
: If found in the library path, the *file* is included for expansion, otherwise it is ignored instead of triggering a failure.

Of course, it supports the Autoconf common subset of options:

'`--help`'
'`-h`'
: Print a summary of the command line options and exit.

[2] Yet another great name from Lars J. Aas.

‘--version’
‘-V’ Print the version number of Autoconf and exit.

‘--verbose’
‘-v’ Report processing steps.

‘--debug’
‘-d’ Don’t remove the temporary files and be even more verbose.

‘--include=*dir*’
‘-I *dir*’ Also look for input files in *dir*. Multiple invocations accumulate.

‘--output=*file*’
‘-o *file*’ Save output (script or trace) to *file*. The file ‘-’ stands for the standard output.

As an extension of m4, it includes the following options:

‘--warnings=*category*’
‘-W *category*’
Report the warnings related to *category* (which can actually be a comma separated list). See Section 9.3 [Reporting Messages], page 126, macro AC_DIAGNOSE, for a comprehensive list of categories. Special values include:

‘all’ report all the warnings

‘none’ report none

‘error’ treats warnings as errors

‘no-*category*’
disable warnings falling into *category*

Warnings about ‘syntax’ are enabled by default, and the environment variable WARNINGS, a comma separated list of categories, is honored. ‘autom4te -W *category*’ actually behaves as if you had run:

```
autom4te --warnings=syntax,$WARNINGS,category
```

For example, if you want to disable defaults and WARNINGS of autom4te, but enable the warnings about obsolete constructs, you would use ‘-W none,obsolete’.

autom4te displays a back trace for errors, but not for warnings; if you want them, just pass ‘-W error’.

‘--melt’
‘-M’ Do not use frozen files. Any argument *file*.m4f is replaced by *file*.m4. This helps tracing the macros which are executed only when the files are frozen, typically m4_define. For instance, running:

```
autom4te --melt 1.m4 2.m4f 3.m4 4.m4f input.m4
```

is roughly equivalent to running:

```
m4 1.m4 2.m4 3.m4 4.m4 input.m4
```

while

```
autom4te 1.m4 2.m4f 3.m4 4.m4f input.m4
```

is equivalent to:

```
m4 --reload-state=4.m4f input.m4
```

‘`--freeze`’
‘`-f`’ Produce a frozen state file. `autom4te` freezing is stricter than M4’s: it must produce no warnings, and no output other than empty lines (a line with white space is *not* empty) and comments (starting with ‘`#`’). Unlike `m4`’s similarly-named option, this option takes no argument:

```
autom4te 1.m4 2.m4 3.m4 --freeze --output=3.m4f
```

corresponds to

```
m4 1.m4 2.m4 3.m4 --freeze-state=3.m4f
```

‘`--mode=`*octal-mode*’
‘`-m` *octal-mode*’
Set the mode of the non-traces output to *octal-mode*; by default ‘`0666`’.

As another additional feature over `m4`, `autom4te` caches its results. GNU M4 is able to produce a regular output and traces at the same time. Traces are heavily used in the GNU Build System: `autoheader` uses them to build ‘`config.h.in`’, `autoreconf` to determine what GNU Build System components are used, `automake` to “parse” ‘`configure.ac`’ etc. To avoid recomputation, traces are cached while performing regular expansion, and conversely. This cache is (actually, the caches are) stored in the directory ‘`autom4te.cache`’. *It can safely be removed* at any moment (especially if for some reason `autom4te` considers it is trashed).

‘`--cache=`*directory*’
‘`-C` *directory*’
Specify the name of the directory where the result should be cached. Passing an empty value disables caching. Be sure to pass a relative file name, as for the time being, global caches are not supported.

‘`--no-cache`’
Don’t cache the results.

‘`--force`’
‘`-f`’ If a cache is used, consider it obsolete (but update it anyway).

Because traces are so important to the GNU Build System, `autom4te` provides high level tracing features as compared to M4, and helps exploiting the cache:

‘`--trace=`*macro*`[:`*format*`]`’
‘`-t` *macro*`[:`*format*`]`’
Trace the invocations of *macro* according to the *format*. Multiple ‘`--trace`’ arguments can be used to list several macros. Multiple ‘`--trace`’ arguments for a single macro are not cumulative; instead, you should just make *format* as long as needed.

The *format* is a regular string, with newlines if desired, and several special escape codes. It defaults to '`$f:$l:$n:$%`'. It can use the following special escapes:

'`$$`' The character '`$`'.

'`$f`' The file name from which *macro* is called.

'`$l`' The line number from which *macro* is called.

'`$d`' The depth of the *macro* call. This is an M4 technical detail that you probably don't want to know about.

'`$n`' The name of the *macro*.

'`$num`' The *num*th argument of the call to *macro*.

'`$@`'
'`$sep@`'
'`${separator}@`'
All the arguments passed to *macro*, separated by the character *sep* or the string *separator* ('`,`' by default). Each argument is quoted, i.e., enclosed in a pair of square brackets.

'`$*`'
'`$sep*`'
'`${separator}*`'
As above, but the arguments are not quoted.

'`$%`'
'`$sep%`'
'`${separator}%`'
As above, but the arguments are not quoted, all new line characters in the arguments are smashed, and the default separator is '`:`'.

The escape '`$%`' produces single-line trace outputs (unless you put newlines in the '`separator`'), while '`$@`' and '`$*`' do not.

See Section 3.4 [autoconf Invocation], page 12, for examples of trace uses.

'`--preselect=macro`'
'`-p macro`'
Cache the traces of *macro*, but do not enable traces. This is especially important to save CPU cycles in the future. For instance, when invoked, `autoconf` preselects all the macros that `autoheader`, `automake`, `autoreconf`, etc., trace, so that running `m4` is not needed to trace them: the cache suffices. This results in a huge speed-up.

Finally, `autom4te` introduces the concept of *Autom4te libraries*. They consists in a powerful yet extremely simple feature: sets of combined command line arguments:

'`--language=language`'
'`-l language`'
Use the *language* Autom4te library. Current languages include:

`M4sugar` create M4sugar output.

`M4sh` create M4sh executable shell scripts.

`Autotest` create Autotest executable test suites.

`Autoconf-without-aclocal-m4`
create Autoconf executable configure scripts without reading '`aclocal.m4`'.

`Autoconf` create Autoconf executable configure scripts. This language inherits all the characteristics of `Autoconf-without-aclocal-m4` and additionally reads '`aclocal.m4`'.

'`--prepend-include=`*dir*'
'`-B` *dir*' Prepend directory *dir* to the search path. This is used to include the language-specific files before any third-party macros.

As an example, if Autoconf is installed in its default location, '`/usr/local`', the command '`autom4te -l m4sugar foo.m4`' is strictly equivalent to the command:

```
autom4te --prepend-include /usr/local/share/autoconf \
  m4sugar/m4sugar.m4f --warnings syntax foo.m4
```

Recursive expansion applies here: the command '`autom4te -l m4sh foo.m4`' is the same as '`autom4te --language M4sugar m4sugar/m4sh.m4f foo.m4`', i.e.:

```
autom4te --prepend-include /usr/local/share/autoconf \
  m4sugar/m4sugar.m4f m4sugar/m4sh.m4f --mode 777 foo.m4
```

The definition of the languages is stored in '`autom4te.cfg`'.

8.2.2 Customizing `autom4te`

One can customize `autom4te` via '`~/.autom4te.cfg`' (i.e., as found in the user home directory), and '`./.autom4te.cfg`' (i.e., as found in the directory from which `autom4te` is run). The order is first reading '`autom4te.cfg`', then '`~/.autom4te.cfg`', then '`./.autom4te.cfg`', and finally the command line arguments.

In these text files, comments are introduced with `#`, and empty lines are ignored. Customization is performed on a per-language basis, wrapped in between a '`begin-language: "`*language*`"`', '`end-language: "`*language*`"`' pair.

Customizing a language stands for appending options (see Section 8.2.1 [autom4te Invocation], page 113) to the current definition of the language. Options, and more generally arguments, are introduced by '`args:` *arguments*'. You may use the traditional shell syntax to quote the *arguments*.

As an example, to disable Autoconf caches ('`autom4te.cache`') globally, include the following lines in '`~/.autom4te.cfg`':

```
## ------------------ ##
## User Preferences.  ##
## ------------------ ##

begin-language: "Autoconf-without-aclocal-m4"
args: --no-cache
end-language: "Autoconf-without-aclocal-m4"
```

8.3 Programming in M4sugar

M4 by itself provides only a small, but sufficient, set of all-purpose macros. M4sugar introduces additional generic macros. Its name was coined by Lars J. Aas: "Readability And Greater Understanding Stands 4 M4sugar".

8.3.1 Redefined M4 Macros

With a few exceptions, all the M4 native macros are moved in the '`m4_`' pseudo-namespace, e.g., M4sugar renames `define` as `m4_define` etc.

Some M4 macros are redefined, and are slightly incompatible with their native equivalent.

`dnl` [Macro]
: This macro kept its original name: no `m4_dnl` is defined.

`m4_defn (`*`macro`*`)` [Macro]
: Unlike the M4 builtin, this macro fails if *macro* is not defined. See `m4_undefine`.

`m4_exit (`*`exit-status`*`)` [Macro]
: This macro corresponds to `m4exit`.

`m4_if (`*`comment`*`)` [Macro]
`m4_if (`*`string-1`*`, `*`string-2`*`, `*`equal`*`, [`*`not-equal`*`])` [Macro]
`m4_if (`*`string-1`*`, `*`string-2`*`, `*`equal`*`, ...)` [Macro]
: This macro corresponds to `ifelse`.

`m4_include (`*`file`*`)` [Macro]
`m4_sinclude (`*`file`*`)` [Macro]
: Like the M4 builtins, but warn against multiple inclusions of *file*.

`m4_bpatsubst (`*`string`*`, `*`regexp`*`, [`*`replacement`*`])` [Macro]
: This macro corresponds to `patsubst`. The name `m4_patsubst` is kept for future versions of M4sh, on top of GNU M4 which will provide extended regular expression syntax via `epatsubst`.

`m4_popdef (`*`macro`*`)` [Macro]
: Unlike the M4 builtin, this macro fails if *macro* is not defined. See `m4_undefine`.

`m4_bregexp (`*`string`*`, `*`regexp`*`, [`*`replacement`*`])` [Macro]
: This macro corresponds to `regexp`. The name `m4_regexp` is kept for future versions of M4sh, on top of GNU M4 which will provide extended regular expression syntax via `eregexp`.

`m4_wrap (`*`text`*`)` [Macro]
: This macro corresponds to `m4wrap`.

  Posix requires arguments of multiple `m4wrap` calls to be reprocessed at EOF in the same order as the original calls. GNU M4 versions through 1.4.x, however, reprocess them in reverse order. Your code should not depend on the order.

  Also, Posix requires `m4wrap` to ignore its second and succeeding arguments, but GNU M4 versions through 1.4.x concatenate the arguments with intervening spaces. Your code should not pass more than one argument.

You are encouraged to end *text* with '`[]`', to avoid unexpected token pasting between consecutive invocations of `m4_wrap`, as in:

```
m4_define([foo], [bar])
m4_define([foofoo], [OUCH])
m4_wrap([foo])
m4_wrap([foo])
⇒OUCH
```

`m4_undefine` (*macro*) [Macro]

Unlike the M4 builtin, this macro fails if *macro* is not defined. Use

```
m4_ifdef([macro], [m4_undefine([macro])])
```

to recover the behavior of the builtin.

8.3.2 Looping constructs

The following macros implement loops in M4.

`m4_for` (*var*, *first*, *last*, [*step*], *expression*) [Macro]

Loop over the numeric values between *first* and *last* including bounds by increments of *step*. For each iteration, expand *expression* with the numeric value assigned to *var*. If *step* is omitted, it defaults to '`1`' or '`-1`' depending on the order of the limits. If given, *step* has to match this order.

`m4_foreach` (*var*, *list*, *expression*) [Macro]

Loop over the comma-separated M4 list *list*, assigning each value to *var*, and expand *expression*. The following example outputs two lines:

```
m4_foreach([myvar], [[foo], [bar, baz]],
           [echo myvar
])
```

`m4_foreach_w` (*var*, *list*, *expression*) [Macro]

Loop over the whitespace-separated list *list*, assigning each value to *var*, and expand *expression*.

The deprecated macro `AC_FOREACH` is an alias of `m4_foreach_w`.

8.3.3 Evaluation Macros

The following macros give some control over the order of the evaluation by adding or removing levels of quotes. They are meant for hard-core M4 programmers.

`m4_dquote` (*arg1*, ...) [Macro]

Return the arguments as a quoted list of quoted arguments.

`m4_quote` (*arg1*, ...) [Macro]

Return the arguments as a single entity, i.e., wrap them into a pair of quotes.

The following example aims at emphasizing the difference between (i), not using these macros, (ii), using `m4_quote`, and (iii), using `m4_dquote`.

```
$ cat example.m4
# Overquote, so that quotes are visible.
m4_define([show], [$[]1 = [$1], $[]@ = [$@]])
m4_divert(0)dnl
show(a, b)
show(m4_quote(a, b))
show(m4_dquote(a, b))
$ autom4te -l m4sugar example.m4
$1 = a, $@ = [a],[b]
$1 = a,b, $@ = [a,b]
$1 = [a],[b], $@ = [[a],[b]]
```

8.3.4 Text processing Macros

The following macros may be used to manipulate strings in M4. They are not intended for casual use.

`m4_re_escape` (*string*) [Macro]
: Backslash-escape all characters in *string* that are active in regexps.

`m4_tolower` (*string*) [Macro]
`m4_toupper` (*string*) [Macro]
: Return *string* with letters converted to upper or lower case, respectively.

`m4_split` (*string*, [*regexp*]) [Macro]
: Split *string* into an M4 list of elements quoted by '`[`' and '`]`', while keeping white space at the beginning and at the end. If *regexp* is given, use it instead of '`[\t ]+`' for splitting. If *string* is empty, the result is an empty list.

`m4_normalize` (*string*) [Macro]
: Remove leading and trailing spaces and tabs, sequences of backslash-then-newline, and replace multiple spaces and tabs with a single space.

`m4_append` (*macro-name*, *string*, [*separator*]) [Macro]
`m4_append_uniq` (*macro-name*, *string*, [*separator*]) [Macro]
: Redefine *macro-name* to its former contents with *separator* and *string* added at the end. If *macro-name* was undefined before (but not if it was defined but empty), then no *separator* is added. `m4_append` can be used to grow strings, and `m4_append_uniq` to grow strings without duplicating substrings.

8.3.5 Forbidden Patterns

M4sugar provides a means to define suspicious patterns, patterns describing tokens which should not be found in the output. For instance, if an Autoconf '`configure`' script includes tokens such as '`AC_DEFINE`', or '`dnl`', then most probably something went wrong (typically a macro was not evaluated because of overquotation).

M4sugar forbids all the tokens matching '`^m4_`' and '`^dnl$`'.

`m4_pattern_forbid` (*pattern*) [Macro]
: Declare that no token matching *pattern* must be found in the output. Comments are not checked; this can be a problem if, for instance, you have some macro left

unexpanded after an '`#include`'. No consensus is currently found in the Autoconf community, as some people consider it should be valid to name macros in comments (which doesn't make sense to the author of this documentation, as '`#`'-comments should document the output, not the input, documented by '`dnl`' comments).

Of course, you might encounter exceptions to these generic rules, for instance you might have to refer to '`$m4_flags`'.

`m4_pattern_allow (`*pattern*`)` [Macro]
Any token matching *pattern* is allowed, including if it matches an `m4_pattern_forbid` pattern.

8.4 Programming in M4sh

M4sh, pronounced "mash", is aiming at producing portable Bourne shell scripts. This name was coined by Lars J. Aas, who notes that, according to the Webster's Revised Unabridged Dictionary (1913):

> Mash \Mash\, n. [Akin to G. meisch, maisch, meische, maische, mash, wash, and prob. to AS. miscian to mix. See "Mix".]
>
> 1. A mass of mixed ingredients reduced to a soft pulpy state by beating or pressure. . .
> 2. A mixture of meal or bran and water fed to animals.
> 3. A mess; trouble. [Obs.] –Beau. & Fl.

For the time being, it is not mature enough to be widely used.

M4sh provides portable alternatives for some common shell constructs that unfortunately are not portable in practice.

`AS_BOURNE_COMPATIBLE` [Macro]
Set up the shell to be more compatible with the Bourne shell as standardized by Posix, if possible. This may involve setting environment variables, or setting options, or similar implementation-specific actions.

`AS_CASE (`*word*`, [`*pattern1*`], [`*if-matched1*`], ..., [`*default*`])` [Macro]
Expand into a shell '`case`' statement, where *word* is matched against one or more patterns. *if-matched* is run if the corresponding pattern matched *word*, else *default* is run.

`AS_DIRNAME (`*file-name*`)` [Macro]
Output the directory portion of *file-name*. For example, if `$file` is '`/one/two/three`', the command `dir=`AS_DIRNAME(["$file"])` sets `dir` to '`/one/two`'.

`AS_IF (`*test1*`, [`*run-if-true1*`], ..., [`*run-if-false*`])` [Macro]
Run shell code *test1*. If *test1* exits with a zero status then run shell code *run-if-true1*, else examine further tests. If no test exits with a zero status, run shell code *run-if-false*, with simplifications if either *run-if-true1* or *run-if-false1* is empty. For example,

```
AS_IF([test "$foo" = yes], [HANDLE_FOO([yes])],
      [test "$foo" != no], [HANDLE_FOO([maybe])],
      [echo foo not specified])
```

ensures any required macros of `HANDLE_FOO` are expanded before the first test.

`AS_MKDIR_P` (*file-name*) [Macro]

Make the directory *file-name*, including intervening directories as necessary. This is equivalent to '`mkdir -p` *file-name*', except that it is portable to older versions of `mkdir` that lack support for the '`-p`' option. Also, `AS_MKDIR_P` succeeds if *file-name* is a symbolic link to an existing directory, even though Posix is unclear whether '`mkdir -p`' should succeed in that case. If creation of *file-name* fails, exit the script.

Also see the `AC_PROG_MKDIR_P` macro (see Section 5.2.1 [Particular Programs], page 41).

`AS_SHELL_SANITIZE` [Macro]

Initialize the shell suitably for `configure` scripts. This has the effect of `AS_BOURNE_COMPATIBLE`, and sets some other environment variables for predictable results from configuration tests. For example, it sets `LC_ALL` to change to the default C locale. See Section 10.9 [Special Shell Variables], page 145.

`AS_TR_CPP` (*expression*) [Macro]

Transform *expression* into a valid right-hand side for a C `#define`. For example:

```
# This outputs "#define HAVE_CHAR_P 1".
type="char *"
echo "#define AS_TR_CPP([HAVE_$type]) 1"
```

`AS_TR_SH` (*expression*) [Macro]

Transform *expression* into a valid shell variable name. For example:

```
# This outputs "Have it!".
header="sys/some file.h"
AS_TR_SH([HAVE_$header])=yes
if test "$HAVE_sys_some_file_h" = yes; then echo "Have it!"; fi
```

`AS_SET_CATFILE` (*var*, *dir*, *file*) [Macro]

Set the shell variable *var* to *dir*/*file*, but optimizing the common cases (*dir* or *file* is '`.`', *file* is absolute, etc.).

8.5 File Descriptor Macros

The following macros define file descriptors used to output messages (or input values) from '`configure`' scripts. For example:

```
echo "$wombats found" >&AS_MESSAGE_LOG_FD
echo 'Enter desired kangaroo count:' >&AS_MESSAGE_FD
read kangaroos <&AS_ORIGINAL_STDIN_FD`
```

However doing so is seldom needed, because Autoconf provides higher level macros as described below.

`AS_MESSAGE_FD` [Macro]

The file descriptor for '`checking for...`' messages and results. Normally this directs messages to the standard output, however when `configure` is run with the '`-q`' option, messages sent to `AS_MESSAGE_FD` are discarded.

If you want to display some messages, consider using one of the printing macros (see Section 7.5 [Printing Messages], page 105) instead. Copies of messages output via these macros are also recorded in '`config.log`'.

`AS_MESSAGE_LOG_FD` [Macro]

The file descriptor for messages logged to '`config.log`'. Macros that run tools, like `AC_COMPILE_IFELSE` (see Section 6.4 [Running the Compiler], page 93), redirect all output to this descriptor. You may want to do so if you develop such a low-level macro.

`AS_ORIGINAL_STDIN_FD` [Macro]

The file descriptor for the original standard input.

When `configure` runs, it may accidentally execute an interactive command that has the same name as the non-interactive meant to be used or checked. If the standard input was the terminal, such interactive programs would cause `configure` to stop, pending some user input. Therefore `configure` redirects its standard input from '`/dev/null`' during its initialization. This is not normally a problem, since `configure` normally does not need user input.

In the extreme case where your '`configure`' script really needs to obtain some values from the original standard input, you can read them explicitly from `AS_ORIGINAL_STDIN_FD`.

9 Writing Autoconf Macros

When you write a feature test that could be applicable to more than one software package, the best thing to do is encapsulate it in a new macro. Here are some instructions and guidelines for writing Autoconf macros.

9.1 Macro Definitions

Autoconf macros are defined using the `AC_DEFUN` macro, which is similar to the M4 builtin `m4_define` macro. In addition to defining a macro, `AC_DEFUN` adds to it some code that is used to constrain the order in which macros are called (see Section 9.4.1 [Prerequisite Macros], page 127).

An Autoconf macro definition looks like this:

```
AC_DEFUN(macro-name, macro-body)
```

You can refer to any arguments passed to the macro as '`$1`', '`$2`', etc. See section "How to define new macros" in *GNU M4*, for more complete information on writing M4 macros.

Be sure to properly quote both the *macro-body* *and* the *macro-name* to avoid any problems if the macro happens to have been previously defined.

Each macro should have a header comment that gives its prototype, and a brief description. When arguments have default values, display them in the prototype. For example:

```
# AC_MSG_ERROR(ERROR, [EXIT-STATUS = 1])
# --------------------------------------
m4_define([AC_MSG_ERROR],
  [{ AS_MESSAGE([error: $1], [2])
     exit m4_default([$2], [1]); }])
```

Comments about the macro should be left in the header comment. Most other comments make their way into '`configure`', so just keep using '`#`' to introduce comments.

If you have some special comments about pure M4 code, comments that make no sense in '`configure`' and in the header comment, then use the builtin `dnl`: it causes M4 to discard the text through the next newline.

Keep in mind that `dnl` is rarely needed to introduce comments; `dnl` is more useful to get rid of the newlines following macros that produce no output, such as `AC_REQUIRE`.

9.2 Macro Names

All of the Autoconf macros have all-uppercase names starting with '`AC_`' to prevent them from accidentally conflicting with other text. All shell variables that they use for internal purposes have mostly-lowercase names starting with '`ac_`'. To ensure that your macros don't conflict with present or future Autoconf macros, you should prefix your own macro names and any shell variables they use with some other sequence. Possibilities include your initials, or an abbreviation for the name of your organization or software package.

Most of the Autoconf macros' names follow a structured naming convention that indicates the kind of feature check by the name. The macro names consist of several words, separated by underscores, going from most general to most specific. The names of their cache variables use the same convention (see Section 7.4.1 [Cache Variable Names], page 104, for more information on them).

The first word of the name after '`AC_`' usually tells the category of the feature being tested. Here are the categories used in Autoconf for specific test macros, the kind of macro that you are more likely to write. They are also used for cache variables, in all-lowercase. Use them where applicable; where they're not, invent your own categories.

`C`	C language builtin features.
`DECL`	Declarations of C variables in header files.
`FUNC`	Functions in libraries.
`GROUP`	Posix group owners of files.
`HEADER`	Header files.
`LIB`	C libraries.
`PATH`	Absolute names of files, including programs.
`PROG`	The base names of programs.
`MEMBER`	Members of aggregates.
`SYS`	Operating system features.
`TYPE`	C builtin or declared types.
`VAR`	C variables in libraries.

After the category comes the name of the particular feature being tested. Any further words in the macro name indicate particular aspects of the feature. For example, `AC_FUNC_FNMATCH_GNU` checks whether the `fnmatch` function supports GNU extensions.

An internal macro should have a name that starts with an underscore; Autoconf internals should therefore start with '`_AC_`'. Additionally, a macro that is an internal subroutine of another macro should have a name that starts with an underscore and the name of that other macro, followed by one or more words saying what the internal macro does. For example, `AC_PATH_X` has internal macros `_AC_PATH_X_XMKMF` and `_AC_PATH_X_DIRECT`.

9.3 Reporting Messages

When macros statically diagnose abnormal situations, benign or fatal, they should report them using these macros. For dynamic issues, i.e., when `configure` is run, see Section 7.5 [Printing Messages], page 105.

`AC_DIAGNOSE (`*category*`, `*message*`)` [Macro]

Report *message* as a warning (or as an error if requested by the user) if warnings of the *category* are turned on. You are encouraged to use standard categories, which currently include:

'`all`' messages that don't fall into one of the following categories. Use of an empty *category* is equivalent.

'`cross`' related to cross compilation issues.

'`obsolete`' use of an obsolete construct.

'`syntax`' dubious syntactic constructs, incorrectly ordered macro calls.

`AC_WARNING` (*message*) [Macro]
: Equivalent to '`AC_DIAGNOSE([syntax], message)`', but you are strongly encouraged to use a finer grained category.

`AC_FATAL` (*message*) [Macro]
: Report a severe error *message*, and have `autoconf` die.

When the user runs '`autoconf -W error`', warnings from `AC_DIAGNOSE` and `AC_WARNING` are reported as error, see Section 3.4 [autoconf Invocation], page 12.

9.4 Dependencies Between Macros

Some Autoconf macros depend on other macros having been called first in order to work correctly. Autoconf provides a way to ensure that certain macros are called if needed and a way to warn the user if macros are called in an order that might cause incorrect operation.

9.4.1 Prerequisite Macros

A macro that you write might need to use values that have previously been computed by other macros. For example, `AC_DECL_YYTEXT` examines the output of `flex` or `lex`, so it depends on `AC_PROG_LEX` having been called first to set the shell variable `LEX`.

Rather than forcing the user of the macros to keep track of the dependencies between them, you can use the `AC_REQUIRE` macro to do it automatically. `AC_REQUIRE` can ensure that a macro is only called if it is needed, and only called once.

`AC_REQUIRE` (*macro-name*) [Macro]
: If the M4 macro *macro-name* has not already been called, call it (without any arguments). Make sure to quote *macro-name* with square brackets. *macro-name* must have been defined using `AC_DEFUN` or else contain a call to `AC_PROVIDE` to indicate that it has been called.

  `AC_REQUIRE` must be used inside a macro defined by `AC_DEFUN`; it must not be called from the top level.

`AC_REQUIRE` is often misunderstood. It really implements dependencies between macros in the sense that if one macro depends upon another, the latter is expanded *before* the body of the former. To be more precise, the required macro is expanded before the outermost defined macro in the current expansion stack. In particular, '`AC_REQUIRE([FOO])`' is not replaced with the body of `FOO`. For instance, this definition of macros:

```
AC_DEFUN([TRAVOLTA],
[test "$body_temperature_in_celsius" -gt "38" &&
  dance_floor=occupied])
AC_DEFUN([NEWTON_JOHN],
[test "$hair_style" = "curly" &&
  dance_floor=occupied])

AC_DEFUN([RESERVE_DANCE_FLOOR],
[if date | grep '^Sat.*pm' >/dev/null 2>&1; then
  AC_REQUIRE([TRAVOLTA])
  AC_REQUIRE([NEWTON_JOHN])
fi])
```

with this 'configure.ac'

```
AC_INIT([Dance Manager], [1.0], [bug-dance@example.org])
RESERVE_DANCE_FLOOR
if test "$dance_floor" = occupied; then
  AC_MSG_ERROR([cannot pick up here, let's move])
fi
```

does not leave you with a better chance to meet a kindred soul at other times than Saturday night since it expands into:

```
test "$body_temperature_in_Celsius" -gt "38" &&
  dance_floor=occupied
test "$hair_style" = "curly" &&
  dance_floor=occupied
fi
if date | grep '^Sat.*pm' >/dev/null 2>&1; then


fi
```

This behavior was chosen on purpose: (i) it prevents messages in required macros from interrupting the messages in the requiring macros; (ii) it avoids bad surprises when shell conditionals are used, as in:

```
if ...; then
  AC_REQUIRE([SOME_CHECK])
fi
...
SOME_CHECK
```

The helper macros `AS_IF` and `AS_CASE` may be used to enforce expansion of required macros outside of shell conditional constructs. You are furthermore encouraged to put all `AC_REQUIRE` calls at the beginning of a macro. You can use `dnl` to avoid the empty lines they leave.

9.4.2 Suggested Ordering

Some macros should be run before another macro if both are called, but neither *requires* that the other be called. For example, a macro that changes the behavior of the C compiler should be called before any macros that run the C compiler. Many of these dependencies are noted in the documentation.

Autoconf provides the `AC_BEFORE` macro to warn users when macros with this kind of dependency appear out of order in a 'configure.ac' file. The warning occurs when creating `configure` from 'configure.ac', not when running `configure`.

For example, `AC_PROG_CPP` checks whether the C compiler can run the C preprocessor when given the '-E' option. It should therefore be called after any macros that change which C compiler is being used, such as `AC_PROG_CC`. So `AC_PROG_CC` contains:

```
AC_BEFORE([$0], [AC_PROG_CPP])dnl
```

This warns the user if a call to `AC_PROG_CPP` has already occurred when `AC_PROG_CC` is called.

`AC_BEFORE (`*`this-macro-name`*`, `*`called-macro-name`*`)` [Macro]
Make M4 print a warning message to the standard error output if *called-macro-name* has already been called. *this-macro-name* should be the name of the macro that is calling `AC_BEFORE`. The macro *called-macro-name* must have been defined using `AC_DEFUN` or else contain a call to `AC_PROVIDE` to indicate that it has been called.

9.4.3 One-Shot Macros

Some macros should be called only once, either because calling them multiple time is unsafe, or because it is bad style. For instance Autoconf ensures that `AC_CANONICAL_BUILD` and cousins (see Section 13.2 [Canonicalizing], page 190) are evaluated only once, because it makes no sense to run these expensive checks more than once. Such one-shot macros can be defined using `AC_DEFUN_ONCE`.

`AC_DEFUN_ONCE (`*`macro-name`*`, `*`macro-body`*`)` [Macro]
Declare macro *macro-name* like `AC_DEFUN` would (see Section 9.1 [Macro Definitions], page 125), and emit a warning any time the macro is called more than once.

Obviously it is not sensible to evaluate a macro defined by `AC_DEFUN_ONCE` in a macro defined by `AC_DEFUN`. Most of the time you want to use `AC_REQUIRE` (see Section 9.4.1 [Prerequisite Macros], page 127).

9.5 Obsoleting Macros

Configuration and portability technology has evolved over the years. Often better ways of solving a particular problem are developed, or ad-hoc approaches are systematized. This process has occurred in many parts of Autoconf. One result is that some of the macros are now considered *obsolete*; they still work, but are no longer considered the best thing to do, hence they should be replaced with more modern macros. Ideally, `autoupdate` should replace the old macro calls with their modern implementation.

Autoconf provides a simple means to obsolete a macro.

`AU_DEFUN (`*`old-macro`*`, `*`implementation`*`, [`*`message`*`])` [Macro]
Define *old-macro* as *implementation*. The only difference with `AC_DEFUN` is that the user is warned that *old-macro* is now obsolete.

If she then uses `autoupdate`, the call to *old-macro* is replaced by the modern *implementation*. *message* should include information on what to do after running `autoupdate`; `autoupdate` prints it as a warning, and includes it in the updated '`configure.ac`' file.

The details of this macro are hairy: if `autoconf` encounters an `AU_DEFUN`ed macro, all macros inside its second argument are expanded as usual. However, when `autoupdate` is run, only M4 and M4sugar macros are expanded here, while all other macros are disabled and appear literally in the updated '`configure.ac`'.

`AU_ALIAS (`*`old-name`*`, `*`new-name`*`)` [Macro]
Used if the *old-name* is to be replaced by a call to *new-macro* with the same parameters. This happens for example if the macro was renamed.

9.6 Coding Style

The Autoconf macros follow a strict coding style. You are encouraged to follow this style, especially if you intend to distribute your macro, either by contributing it to Autoconf itself, or via other means.

The first requirement is to pay great attention to the quotation. For more details, see Section 3.1.2 [Autoconf Language], page 9, and Section 8.1 [M4 Quotation], page 107.

Do not try to invent new interfaces. It is likely that there is a macro in Autoconf that resembles the macro you are defining: try to stick to this existing interface (order of arguments, default values, etc.). We *are* conscious that some of these interfaces are not perfect; nevertheless, when harmless, homogeneity should be preferred over creativity.

Be careful about clashes both between M4 symbols and between shell variables.

If you stick to the suggested M4 naming scheme (see Section 9.2 [Macro Names], page 125), you are unlikely to generate conflicts. Nevertheless, when you need to set a special value, *avoid using a regular macro name*; rather, use an "impossible" name. For instance, up to version 2.13, the macro `AC_SUBST` used to remember what *symbol* macros were already defined by setting `AC_SUBST_`*`symbol`*, which is a regular macro name. But since there is a macro named `AC_SUBST_FILE`, it was just impossible to '`AC_SUBST(FILE)`'! In this case, `AC_SUBST(`*`symbol`*`)` or `_AC_SUBST(`*`symbol`*`)` should have been used (yes, with the parentheses).

No Autoconf macro should ever enter the user-variable name space; i.e., except for the variables that are the actual result of running the macro, all shell variables should start with `ac_`. In addition, small macros or any macro that is likely to be embedded in other macros should be careful not to use obvious names.

Do not use `dnl` to introduce comments: most of the comments you are likely to write are either header comments which are not output anyway, or comments that should make their way into '`configure`'. There are exceptional cases where you do want to comment special M4 constructs, in which case `dnl` is right, but keep in mind that it is unlikely.

M4 ignores the leading blanks and newlines before each argument. Use this feature to indent in such a way that arguments are (more or less) aligned with the opening parenthesis of the macro being called. For instance, instead of

```
AC_CACHE_CHECK(for EMX OS/2 environment,
ac_cv_emxos2,
[AC_COMPILE_IFELSE([AC_LANG_PROGRAM(, [return __EMX__;])],
[ac_cv_emxos2=yes], [ac_cv_emxos2=no])])
```

write

```
AC_CACHE_CHECK([for EMX OS/2 environment], [ac_cv_emxos2],
[AC_COMPILE_IFELSE([AC_LANG_PROGRAM([], [return __EMX__;])],
                   [ac_cv_emxos2=yes],
                   [ac_cv_emxos2=no])])
```

or even

```
AC_CACHE_CHECK([for EMX OS/2 environment],
               [ac_cv_emxos2],
               [AC_COMPILE_IFELSE([AC_LANG_PROGRAM([],
                                                   [return __EMX__;])],
```

```
                                    [ac_cv_emxos2=yes],
                                    [ac_cv_emxos2=no])])
```

When using `AC_RUN_IFELSE` or any macro that cannot work when cross-compiling, provide a pessimistic value (typically '`no`').

Feel free to use various tricks to prevent auxiliary tools, such as syntax-highlighting editors, from behaving improperly. For instance, instead of:

```
m4_bpatsubst([$1], [$"])
```

use

```
m4_bpatsubst([$1], [$""])
```

so that Emacsen do not open an endless "string" at the first quote. For the same reasons, avoid:

```
test $[#] != 0
```

and use:

```
test $[@%:@] != 0
```

Otherwise, the closing bracket would be hidden inside a '`#`'-comment, breaking the bracket-matching highlighting from Emacsen. Note the preferred style to escape from M4: '`$[1]`', '`$[@]`', etc. Do not escape when it is unnecessary. Common examples of useless quotation are '`[$]$1`' (write '`$$1`'), '`[$]var`' (use '`$var`'), etc. If you add portability issues to the picture, you'll prefer '`${1+"$[@]"}`' to '`"[$]@"`', and you'll prefer do something better than hacking Autoconf `:-)`.

When using `sed`, don't use '`-e`' except for indenting purposes. With the `s` and `y` commands, the preferred separator is '`/`' unless '`/`' itself might appear in the pattern or replacement, in which case you should use '`|`', or optionally '`,`' if you know the pattern and replacement cannot contain a file name. If none of these characters will do, choose a printable character that cannot appear in the pattern or replacement. Characters from the set '`"#$&'()*;<=>¿|~`' are good choices if the pattern or replacement might contain a file name, since they have special meaning to the shell and are less likely to occur in file names.

See Section 9.1 [Macro Definitions], page 125, for details on how to define a macro. If a macro doesn't use `AC_REQUIRE`, is expected to never be the object of an `AC_REQUIRE` directive, and macros required by other macros inside arguments do not need to be expanded before this macro, then use `m4_define`. In case of doubt, use `AC_DEFUN`. All the `AC_REQUIRE` statements should be at the beginning of the macro, and each statement should be followed by `dnl`.

You should not rely on the number of arguments: instead of checking whether an argument is missing, test that it is not empty. It provides both a simpler and a more predictable interface to the user, and saves room for further arguments.

Unless the macro is short, try to leave the closing '`])`' at the beginning of a line, followed by a comment that repeats the name of the macro being defined. This introduces an additional newline in `configure`; normally, that is not a problem, but if you want to remove it you can use '`[]dnl`' on the last line. You can similarly use '`[]dnl`' after a macro call to remove its newline. '`[]dnl`' is recommended instead of '`dnl`' to ensure that M4 does not interpret the '`dnl`' as being attached to the preceding text or macro output. For example, instead of:

```
AC_DEFUN([AC_PATH_X],
[AC_MSG_CHECKING([for X])
AC_REQUIRE_CPP()
# ...omitted...
  AC_MSG_RESULT([libraries $x_libraries, headers $x_includes])
fi])
```

you would write:

```
AC_DEFUN([AC_PATH_X],
[AC_REQUIRE_CPP()[]dnl
AC_MSG_CHECKING([for X])
# ...omitted...
  AC_MSG_RESULT([libraries $x_libraries, headers $x_includes])
fi[]dnl
])# AC_PATH_X
```

If the macro is long, try to split it into logical chunks. Typically, macros that check for a bug in a function and prepare its `AC_LIBOBJ` replacement should have an auxiliary macro to perform this setup. Do not hesitate to introduce auxiliary macros to factor your code.

In order to highlight the recommended coding style, here is a macro written the old way:

```
dnl Check for EMX on OS/2.
dnl _AC_EMXOS2
AC_DEFUN(_AC_EMXOS2,
[AC_CACHE_CHECK(for EMX OS/2 environment, ac_cv_emxos2,
[AC_COMPILE_IFELSE([AC_LANG_PROGRAM(, return __EMX__;)],
ac_cv_emxos2=yes, ac_cv_emxos2=no)])
test "$ac_cv_emxos2" = yes && EMXOS2=yes])
```

and the new way:

```
# _AC_EMXOS2
# ----------
# Check for EMX on OS/2.
m4_define([_AC_EMXOS2],
[AC_CACHE_CHECK([for EMX OS/2 environment], [ac_cv_emxos2],
[AC_COMPILE_IFELSE([AC_LANG_PROGRAM([], [return __EMX__;])],
                   [ac_cv_emxos2=yes],
                   [ac_cv_emxos2=no])])
test "$ac_cv_emxos2" = yes && EMXOS2=yes[]dnl
])# _AC_EMXOS2
```

10 Portable Shell Programming

When writing your own checks, there are some shell-script programming techniques you should avoid in order to make your code portable. The Bourne shell and upward-compatible shells like the Korn shell and Bash have evolved over the years, but to prevent trouble, do not take advantage of features that were added after Unix version 7, circa 1977 (see Section 6.7 [Systemology], page 96).

You should not use shell functions, aliases, negated character classes, or other features that are not found in all Bourne-compatible shells; restrict yourself to the lowest common denominator. Even `unset` is not supported by all shells!

Some ancient systems have quite small limits on the length of the '`#!`' line; for instance, 32 bytes (not including the newline) on SunOS 4. A few ancient 4.2BSD based systems (such as Dynix circa 1984) required a single space between the '`#!`' and the '`/`'. However, these ancient systems are no longer of practical concern.

The set of external programs you should run in a `configure` script is fairly small. See section "Utilities in Makefiles" in *GNU Coding Standards*, for the list. This restriction allows users to start out with a fairly small set of programs and build the rest, avoiding too many interdependencies between packages.

Some of these external utilities have a portable subset of features; see Section 10.11 [Limitations of Usual Tools], page 158.

There are other sources of documentation about shells. The specification for the Posix Shell Command Language (`http://www.opengroup.org/susv3/utilities/xcu_chap02.html`), though more generous than the restrictive shell subset described above, is fairly portable nowadays. Also please see the Shell FAQs (`http://www.faqs.org/faqs/unix-faq/shell/`).

10.1 Shellology

There are several families of shells, most prominently the Bourne family and the C shell family which are deeply incompatible. If you want to write portable shell scripts, avoid members of the C shell family. The the Shell difference FAQ (`http://www.faqs.org/faqs/unix-faq/shell/shell-differences/`) includes a small history of Posix shells, and a comparison between several of them.

Below we describe some of the members of the Bourne shell family.

Ash
: Ash is often used on GNU/Linux and BSD systems as a light-weight Bourne-compatible shell. Ash 0.2 has some bugs that are fixed in the 0.3.x series, but portable shell scripts should work around them, since version 0.2 is still shipped with many GNU/Linux distributions.

  To be compatible with Ash 0.2:

  - don't use '`$?`' after expanding empty or unset variables, or at the start of an `eval`:

    ```
    foo=
    false
    $foo
    echo "Do not use it: $?"
    ```

```
false
eval 'echo "Do not use it: $?"'
```

– don't use command substitution within variable expansion:

```
cat ${FOO=`bar`}
```

– beware that single builtin substitutions are not performed by a subshell, hence their effect applies to the current shell! See Section 10.5 [Shell Substitutions], page 140, item "Command Substitution".

Bash To detect whether you are running Bash, test whether `BASH_VERSION` is set. To require Posix compatibility, run '`set -o posix`'. See section "Bash Posix Mode" in *The GNU Bash Reference Manual*, for details.

Bash 2.05 and later
Versions 2.05 and later of Bash use a different format for the output of the `set` builtin, designed to make evaluating its output easier. However, this output is not compatible with earlier versions of Bash (or with many other shells, probably). So if you use Bash 2.05 or higher to execute `configure`, you'll need to use Bash 2.05 for all other build tasks as well.

Ksh The Korn shell is compatible with the Bourne family and it mostly conforms to Posix. It has two major variants commonly called '`ksh88`' and '`ksh93`', named after the years of initial release. It is usually called `ksh`, but is called `sh` on some hosts if you set your path appropriately.

Solaris systems have three variants: `/usr/bin/ksh` is '`ksh88`'; it is standard on Solaris 2.0 and later. `/usr/xpg4/bin/sh` is a Posix-compliant variant of '`ksh88`'; it is standard on Solaris 9 and later. `/usr/dt/bin/dtksh` is '`ksh93`'. Variants that are not standard may be parts of optional packages. There is no extra charge for these packages, but they are not part of a minimal OS install and therefore some installations may not have it.

Starting with Tru64 Version 4.0, the Korn shell `/usr/bin/ksh` is also available as `/usr/bin/posix/sh`. If the environment variable `BIN_SH` is set to `xpg4`, subsidiary invocations of the standard shell conform to Posix.

Pdksh A public-domain clone of the Korn shell called `pdksh` is widely available: it has most of the '`ksh88`' features along with a few of its own. It usually sets `KSH_VERSION`, except if invoked as `/bin/sh` on OpenBSD, and similarly to Bash you can require Posix compatibility by running '`set -o posix`'. Unfortunately, with `pdksh` 5.2.14 (the latest stable version as of February 2006) Posix mode is buggy and causes `pdksh` to depart from Posix in at least one respect:

```
$ echo "`echo \"hello\"`"
hello
$ set -o posix
$ echo "`echo \"hello\"`"
"hello"
```

The last line of output contains spurious quotes. This is yet another reason why portable shell code should not contain "`` `...\"...\"...` "" constructs (see Section 10.5 [Shell Substitutions], page 140).

Zsh
: To detect whether you are running `zsh`, test whether `ZSH_VERSION` is set. By default `zsh` is *not* compatible with the Bourne shell: you must execute '`emulate sh`', and for `zsh` versions before 3.1.6-dev-18 you must also set `NULLCMD` to '`:`'. See section "Compatibility" in *The Z Shell Manual*, for details.

  The default Mac OS X `sh` was originally Zsh; it was changed to Bash in Mac OS X 10.2.

The following discussion between Russ Allbery and Robert Lipe is worth reading:

Russ Allbery:

> The GNU assumption that `/bin/sh` is the one and only shell leads to a permanent deadlock. Vendors don't want to break users' existing shell scripts, and there are some corner cases in the Bourne shell that are not completely compatible with a Posix shell. Thus, vendors who have taken this route will *never* (OK. . . "never say never") replace the Bourne shell (as `/bin/sh`) with a Posix shell.

Robert Lipe:

> This is exactly the problem. While most (at least most System V's) do have a Bourne shell that accepts shell functions most vendor `/bin/sh` programs are not the Posix shell.
>
> So while most modern systems do have a shell *somewhere* that meets the Posix standard, the challenge is to find it.

10.2 Here-Documents

Don't rely on '`\`' being preserved just because it has no special meaning together with the next symbol. In the native `sh` on OpenBSD 2.7 '`\"`' expands to '`"`' in here-documents with unquoted delimiter. As a general rule, if '`\\`' expands to '`\`' use '`\\`' to get '`\`'.

With OpenBSD 2.7's `sh`

```
$ cat <<EOF
> \" \\
> EOF
" \
```

and with Bash:

```
bash-2.04$ cat <<EOF
> \" \\
> EOF
\" \
```

Some shells mishandle large here-documents: for example, Solaris 10 `dtksh` and the UnixWare 7.1.1 Posix shell, which are derived from Korn shell version M-12/28/93d, mishandle braced variable expansion that crosses a 1024- or 4096-byte buffer boundary within a here-document. Only the part of the variable name after the boundary is used. For example, `${variable}` could be replaced by the expansion of `${ble}`. If the end of the variable name is aligned with the block boundary, the shell reports an error, as if you used `${}`. Instead of `${variable-default}`, the shell may expand `${riable-default}`, or even `${fault}`. This bug can often be worked around by omitting the braces: `$variable`. The

bug was fixed in 'ksh93g' (1998-04-30) but as of 2006 many operating systems were still shipping older versions with the bug.

Many older shells (including the Bourne shell) implement here-documents inefficiently. In particular, some shells can be extremely inefficient when a single statement contains many here-documents. For instance if your 'configure.ac' includes something like:

```
if <cross_compiling>; then
  assume this and that
else
  check this
  check that
  check something else
  ...
  on and on forever
  ...
fi
```

A shell parses the whole `if/fi` construct, creating temporary files for each here-document in it. Some shells create links for such here-documents on every `fork`, so that the clean-up code they had installed correctly removes them. It is creating the links that can take the shell forever.

Moving the tests out of the `if/fi`, or creating multiple `if/fi` constructs, would improve the performance significantly. Anyway, this kind of construct is not exactly the typical use of Autoconf. In fact, it's even not recommended, because M4 macros can't look into shell conditionals, so we may fail to expand a macro when it was expanded before in a conditional path, and the condition turned out to be false at runtime, and we end up not executing the macro at all.

10.3 File Descriptors

Don't redirect the same file descriptor several times, as you are doomed to failure under Ultrix.

```
ULTRIX V4.4 (Rev. 69) System #31: Thu Aug 10 19:42:23 GMT 1995
UWS V4.4 (Rev. 11)
$ eval 'echo matter >fullness' >void
illegal io
$ eval '(echo matter >fullness)' >void
illegal io
$ (eval '(echo matter >fullness)') >void
Ambiguous output redirect.
```

In each case the expected result is of course 'fullness' containing 'matter' and 'void' being empty.

Don't try to redirect the standard error of a command substitution: it must be done *inside* the command substitution: when running ': `cd /zorglub` 2>/dev/null' expect the error message to escape, while ': `cd /zorglub 2>/dev/null`' works properly.

It is worth noting that Zsh (but not Ash nor Bash) makes it possible in assignments though: 'foo=`cd /zorglub` 2>/dev/null'.

Most shells, if not all (including Bash, Zsh, Ash), output traces on stderr, even for subshells. This might result in undesirable content if you meant to capture the standard-error output of the inner command:

```
$ ash -x -c '(eval "echo foo >&2") 2>stderr'
$ cat stderr
+ eval echo foo >&2
+ echo foo
foo
$ bash -x -c '(eval "echo foo >&2") 2>stderr'
$ cat stderr
+ eval 'echo foo >&2'
++ echo foo
foo
$ zsh -x -c '(eval "echo foo >&2") 2>stderr'
# Traces on startup files deleted here.
$ cat stderr
+zsh:1> eval echo foo >&2
+zsh:1> echo foo
foo
```

You'll appreciate the various levels of detail...

One workaround is to grep out uninteresting lines, hoping not to remove good ones...

Don't try to move/delete open files, such as in '`exec >foo; mv foo bar`'; see Section 10.10 [Limitations of Builtins], page 150, `mv` for more details.

Don't rely on file descriptors 0, 1, and 2 remaining closed in a subsidiary program. If any of these descriptors is closed, the operating system may open an unspecified file for the descriptor in the new process image. Posix says this may be done only if the subsidiary program is set-user-ID or set-group-ID, but HP-UX 11.23 does it even for ordinary programs.

Don't rely on open file descriptors being open in child processes. In `ksh`, file descriptors above 2 which are opened using '`exec` *n*`>file`' are closed by a subsequent '`exec`' (such as that involved in the fork-and-exec which runs a program or script). Thus, using `sh`, we have:

```
$ cat ./descrips
#!/bin/sh -
echo hello >&5
$ exec 5>t
$ ./descrips
$ cat t
$
hello
```

But using ksh:

```
$ exec 5>t
$ ./descrips
hello
$ cat t
$
```

Within the process which runs the '`descrips`' script, file descriptor 5 is closed.

A few ancient systems reserved some file descriptors. By convention, file descriptor 3 was opened to '`/dev/tty`' when you logged into Eighth Edition (1985) through Tenth Edition Unix (1989). File descriptor 4 had a special use on the Stardent/Kubota Titan (circa 1990), though we don't now remember what it was. Both these systems are obsolete, so it's now safe to treat file descriptors 3 and 4 like any other file descriptors.

10.4 File System Conventions

Autoconf uses shell-script processing extensively, so the file names that it processes should not contain characters that are special to the shell. Special characters include space, tab, newline, NUL, and the following:

```
" # $ & ' ( ) * ; < = > ? [ \ ` |
```

Also, file names should not begin with '`~`' or '`-`', and should contain neither '`-`' immediately after '`/`' nor '`~`' immediately after '`:`'. On Posix-like platforms, directory names should not contain '`:`', as this runs afoul of '`:`' used as the path separator.

These restrictions apply not only to the files that you distribute, but also to the absolute file names of your source, build, and destination directories.

On some Posix-like platforms, '`!`' and '`^`' are special too, so they should be avoided.

Posix lets implementations treat leading '`//`' specially, but requires leading '`///`' and beyond to be equivalent to '`/`'. Most Unix variants treat '`//`' like '`/`'. However, some treat '`//`' as a "super-root" that can provide access to files that are not otherwise reachable from '`/`'. The super-root tradition began with Apollo Domain/OS, which died out long ago, but unfortunately Cygwin has revived it.

While `autoconf` and friends are usually run on some Posix variety, they can be used on other systems, most notably DOS variants. This impacts several assumptions regarding file names.

For example, the following code:

```
case $foo_dir in
  /*) # Absolute
     ;;
  *)
     foo_dir=$dots$foo_dir ;;
esac
```

fails to properly detect absolute file names on those systems, because they can use a drivespec, and usually use a backslash as directory separator. If you want to be portable to DOS variants (at the price of rejecting valid but oddball Posix file names like '`a:\b`'), you can check for absolute file names like this:

```
case $foo_dir in
  [\\/]* | ?:[\\/]* ) # Absolute
     ;;
  *)
     foo_dir=$dots$foo_dir ;;
esac
```

Make sure you quote the brackets if appropriate and keep the backslash as first character (see Section 10.10 [Limitations of Builtins], page 150).

Also, because the colon is used as part of a drivespec, these systems don't use it as path separator. When creating or accessing paths, you can use the `PATH_SEPARATOR` output variable instead. `configure` sets this to the appropriate value (':' or ';') when it starts up.

File names need extra care as well. While DOS variants that are Posixy enough to run `autoconf` (such as DJGPP) are usually able to handle long file names properly, there are still limitations that can seriously break packages. Several of these issues can be easily detected by the doschk (`ftp://ftp.gnu.org/gnu/non-gnu/doschk/doschk-1.1.tar.gz`) package.

A short overview follows; problems are marked with SFN/LFN to indicate where they apply: SFN means the issues are only relevant to plain DOS, not to DOS under Microsoft Windows variants, while LFN identifies problems that exist even under Microsoft Windows variants.

No multiple dots (SFN)
: DOS cannot handle multiple dots in file names. This is an especially important thing to remember when building a portable configure script, as `autoconf` uses a .in suffix for template files.

  This is perfectly OK on Posix variants:

  ```
  AC_CONFIG_HEADERS([config.h])
  AC_CONFIG_FILES([source.c foo.bar])
  AC_OUTPUT
  ```

  but it causes problems on DOS, as it requires '`config.h.in`', '`source.c.in`' and '`foo.bar.in`'. To make your package more portable to DOS-based environments, you should use this instead:

  ```
  AC_CONFIG_HEADERS([config.h:config.hin])
  AC_CONFIG_FILES([source.c:source.cin foo.bar:foobar.in])
  AC_OUTPUT
  ```

No leading dot (SFN)
: DOS cannot handle file names that start with a dot. This is usually not important for `autoconf`.

Case insensitivity (LFN)
: DOS is case insensitive, so you cannot, for example, have both a file called '`INSTALL`' and a directory called '`install`'. This also affects `make`; if there's a file called '`INSTALL`' in the directory, '`make install`' does nothing (unless the '`install`' target is marked as PHONY).

The 8+3 limit (SFN)
: Because the DOS file system only stores the first 8 characters of the file name and the first 3 of the extension, those must be unique. That means that '`foobar-part1.c`', '`foobar-part2.c`' and '`foobar-prettybird.c`' all resolve to the same file name ('`FOOBAR-P.C`'). The same goes for '`foo.bar`' and '`foo.bartender`'.

  The 8+3 limit is not usually a problem under Microsoft Windows, as it uses numeric tails in the short version of file names to make them unique. However,

a registry setting can turn this behavior off. While this makes it possible to share file trees containing long file names between SFN and LFN environments, it also means the above problem applies there as well.

Invalid characters (LFN)
: Some characters are invalid in DOS file names, and should therefore be avoided. In a LFN environment, these are '`/`', '`\`', '`?`', '`*`', '`:`', '`<`', '`>`', '`|`' and '`"`'. In a SFN environment, other characters are also invalid. These include '`+`', '`,`', '`[`' and '`]`'.

Invalid names (LFN)
: Some DOS file names are reserved, and cause problems if you try to use files with those names. These names include '`CON`', '`AUX`', '`COM1`', '`COM2`', '`COM3`', '`COM4`', '`LPT1`', '`LPT2`', '`LPT3`', '`NUL`', and '`PRN`'. File names are case insensitive, so even names like '`aux/config.guess`' are disallowed.

10.5 Shell Substitutions

Contrary to a persistent urban legend, the Bourne shell does not systematically split variables and back-quoted expressions, in particular on the right-hand side of assignments and in the argument of `case`. For instance, the following code:

```
case "$given_srcdir" in
.)  top_srcdir="`echo "$dots" | sed 's,/$,,'`" ;;
*)  top_srcdir="$dots$given_srcdir" ;;
esac
```

is more readable when written as:

```
case $given_srcdir in
.)  top_srcdir=`echo "$dots" | sed 's,/$,,'` ;;
*)  top_srcdir=$dots$given_srcdir ;;
esac
```

and in fact it is even *more* portable: in the first case of the first attempt, the computation of `top_srcdir` is not portable, since not all shells properly understand `"`...`"..."..."`...`"`. Worse yet, not all shells understand `"`...\"...\"...`"` the same way. There is just no portable way to use double-quoted strings inside double-quoted back-quoted expressions (pfew!).

`$@`
: One of the most famous shell-portability issues is related to '`"$@"`'. When there are no positional arguments, Posix says that '`"$@"`' is supposed to be equivalent to nothing, but the original Unix version 7 Bourne shell treated it as equivalent to '`""`' instead, and this behavior survives in later implementations like Digital Unix 5.0.

  The traditional way to work around this portability problem is to use '`${1+"$@"}`'. Unfortunately this method does not work with Zsh (3.x and 4.x), which is used on Mac OS X. When emulating the Bourne shell, Zsh performs word splitting on '`${1+"$@"}`':

  ```
  zsh $ emulate sh
  zsh $ for i in "$@"; do echo $i; done
  Hello World
  ```

```
!
zsh $ for i in ${1+"$@"}; do echo $i; done
Hello
World
!
```

Zsh handles plain '`"$@"`' properly, but we can't use plain '`"$@"`' because of the portability problems mentioned above. One workaround relies on Zsh's "global aliases" to convert '`${1+"$@"}`' into '`"$@"`' by itself:

```
test "${ZSH_VERSION+set}" = set && alias -g '${1+"$@"}'='"$@"'
```

A more conservative workaround is to avoid '`"$@"`' if it is possible that there may be no positional arguments. For example, instead of:

```
cat conftest.c "$@"
```

you can use this instead:

```
case $# in
0) cat conftest.c;;
*) cat conftest.c "$@";;
esac
```

Autoconf macros often use the `set` command to update '`$@`', so if you are writing shell code intended for `configure` you should not assume that the value of '`$@`' persists for any length of time.

`${10}` The 10th, 11th, ... positional parameters can be accessed only after a `shift`. The 7th Edition shell reported an error if given `${10}`, and Solaris 10 `/bin/sh` still acts that way:

```
$ set 1 2 3 4 5 6 7 8 9 10
$ echo ${10}
bad substitution
```

`${var:-value}`

Old BSD shells, including the Ultrix `sh`, don't accept the colon for any shell substitution, and complain and die.

`${var=literal}`

Be sure to quote:

```
: ${var='Some words'}
```

otherwise some shells, such as on Digital Unix V 5.0, die because of a "bad substitution".

Solaris `/bin/sh` has a frightening bug in its interpretation of this. Imagine you need set a variable to a string containing '`}`'. This '`}`' character confuses Solaris `/bin/sh` when the affected variable was already set. This bug can be exercised by running:

```
$ unset foo
$ foo=${foo='}'}
$ echo $foo
}
```

```
$ foo=${foo='}'   # no error; this hints to what the bug is
$ echo $foo
}
$ foo=${foo='}'}
$ echo $foo
}}
 ^ ugh!
```

It seems that '`}`' is interpreted as matching '`${`', even though it is enclosed in single quotes. The problem doesn't happen using double quotes.

`${`*var=expanded-value*`}`

On Ultrix, running

```
default="yu,yaa"
: ${var="$default"}
```

sets *var* to '`M-yM-uM-,M-yM-aM-a`', i.e., the 8th bit of each char is set. You don't observe the phenomenon using a simple '`echo $var`' since apparently the shell resets the 8th bit when it expands $var. Here are two means to make this shell confess its sins:

```
$ cat -v <<EOF
$var
EOF
```

and

```
$ set | grep '^var=' | cat -v
```

One classic incarnation of this bug is:

```
default="a b c"
: ${list="$default"}
for c in $list; do
  echo $c
done
```

You'll get '`a b c`' on a single line. Why? Because there are no spaces in '`$list`': there are '`M- `', i.e., spaces with the 8th bit set, hence no IFS splitting is performed!!!

One piece of good news is that Ultrix works fine with '`: ${list=$default}`'; i.e., if you *don't* quote. The bad news is then that QNX 4.25 then sets *list* to the *last* item of *default*!

The portable way out consists in using a double assignment, to switch the 8th bit twice on Ultrix:

```
list=${list="$default"}
```

. . . but beware of the '`}`' bug from Solaris (see above). For safety, use:

```
test "${var+set}" = set || var={value}
```

`` `commands` ``

Posix requires shells to trim all trailing newlines from command output before substituting it, so assignments like '`dir=`echo "$file" | tr a A`'` do not work as expected if '`$file`' ends in a newline.

While in general it makes no sense, do not substitute a single builtin with side effects, because Ash 0.2, trying to optimize, does not fork a subshell to perform the command.

For instance, if you wanted to check that `cd` is silent, do not use '`test -z "`*`cd /`*`"`' because the following can happen:

```
$ pwd
/tmp
$ test -z "`cd /`" && pwd
/
```

The result of '`foo=`*`exit 1`*`'` is left as an exercise to the reader.

The MSYS shell leaves a stray byte in the expansion of a double-quoted command substitution of a native program, if the end of the substution is not aligned with the end of the double quote. This may be worked around by inserting another pair of quotes:

```
$ echo "`printf 'foo\r\n'` bar" > broken
$ echo "`printf 'foo\r\n'`"" bar" | cmp - broken
- broken differ: char 4, line 1
```

`$(`*commands*`)`

This construct is meant to replace '`` `commands` ``', and it has most of the problems listed under '`` `commands` ``'.

This construct can be nested while this is impossible to do portably with back quotes. Unfortunately it is not yet universally supported. Most notably, even recent releases of Solaris don't support it:

```
$ showrev -c /bin/sh | grep version
Command version: SunOS 5.10 Generic 121004-01 Oct 2005
$ echo $(echo blah)
syntax error: `(' unexpected
```

nor does IRIX 6.5's Bourne shell:

```
$ uname -a
IRIX firebird-image 6.5 07151432 IP22
$ echo $(echo blah)
$(echo blah)
```

If you do use '`$(`*commands*`)`', make sure that the commands do not start with a parenthesis, as that would cause confusion with a different notation '`$((`*expression*`))`' that in modern shells is an arithmetic expression not a command. To avoid the confusion, insert a space between the two opening parentheses.

Avoid *commands* that contain unbalanced parentheses in here-documents, comments, or case statement patterns, as many shells mishandle them. For example, Bash 3.1, '`ksh88`', `pdksh` 5.2.14, and Zsh 4.2.6 all mishandle the following valid command:

```
echo $(case x in x) echo hello;; esac)
```

`^` Always quote '`^`', otherwise traditional shells such as `/bin/sh` on Solaris 10 treat this like '`|`'.

10.6 Assignments

When setting several variables in a row, be aware that the order of the evaluation is undefined. For instance '`foo=1 foo=2; echo $foo`' gives '`1`' with Solaris `/bin/sh`, but '`2`' with Bash. You must use '`;`' to enforce the order: '`foo=1; foo=2; echo $foo`'.

Don't rely on the following to find '`subdir/program`':

```
PATH=subdir$PATH_SEPARATOR$PATH program
```

as this does not work with Zsh 3.0.6. Use something like this instead:

```
(PATH=subdir$PATH_SEPARATOR$PATH; export PATH; exec program)
```

Don't rely on the exit status of an assignment: Ash 0.2 does not change the status and propagates that of the last statement:

```
$ false || foo=bar; echo $?
1
$ false || foo=`:`; echo $?
0
```

and to make things even worse, QNX 4.25 just sets the exit status to 0 in any case:

```
$ foo=`exit 1`; echo $?
0
```

To assign default values, follow this algorithm:

1. If the default value is a literal and does not contain any closing brace, use:

   ```
   : ${var='my literal'}
   ```

2. If the default value contains no closing brace, has to be expanded, and the variable being initialized is not intended to be IFS-split (i.e., it's not a list), then use:

   ```
   : ${var="$default"}
   ```

3. If the default value contains no closing brace, has to be expanded, and the variable being initialized is intended to be IFS-split (i.e., it's a list), then use:

   ```
   var=${var="$default"}
   ```

4. If the default value contains a closing brace, then use:

   ```
   test "${var+set}" = set || var="has a '}'"
   ```

In most cases '`var=${var="$default"}`' is fine, but in case of doubt, just use the last form. See Section 10.5 [Shell Substitutions], page 140, items '`${var:-value}`' and '`${var=value}`' for the rationale.

10.7 Parentheses in Shell Scripts

Beware of two opening parentheses in a row, as some shell implementations mishandle them. For example, '`pdksh`' 5.2.14 misparses the following code:

```
if ((true) || false); then
  echo ok
fi
```

To work around this problem, insert a space between the two opening parentheses. There is a similar problem and workaround with '`$((`'; see Section 10.5 [Shell Substitutions], page 140.

Posix requires support for `case` patterns with opening parentheses like this:

```
case $file_name in
(*.c) echo "C source code";;
esac
```

but the (in this example is not portable to many older Bourne shell implementations. It can be omitted safely.

10.8 Slashes in Shell Scripts

Unpatched Tru64 5.1 `sh` omits the last slash of command-line arguments that contain two trailing slashes:

```
$ echo / // /// //// .// //.
/ / // /// ./ //.
$ x=//
$ eval "echo \$x"
/
$ set -x
$ echo abc | tr -t ab //
+ echo abc
+ tr -t ab /
/bc
```

However, our understanding is that patches are available, so perhaps it's not worth worrying about working around this horrendous bug.

10.9 Special Shell Variables

Some shell variables should not be used, since they can have a deep influence on the behavior of the shell. In order to recover a sane behavior from the shell, some variables should be unset, but `unset` is not portable (see Section 10.10 [Limitations of Builtins], page 150) and a fallback value is needed.

As a general rule, shell variable names containing a lower-case letter are safe; you can define and use these variables without worrying about their effect on the underlying system, and without worrying about whether the shell changes them unexpectedly. (The exception is the shell variable `status`, as described below.)

Here is a list of names that are known to cause trouble. This list is not exhaustive, but you should be safe if you avoid the name `status` and names containing only upper-case letters and underscores.

`_` Many shells reserve '`$_`' for various purposes, e.g., the name of the last command executed.

`BIN_SH` In Tru64, if `BIN_SH` is set to `xpg4`, subsidiary invocations of the standard shell conform to Posix. Autoconf-generated scripts export this variable when they start up.

`CDPATH` When this variable is set it specifies a list of directories to search when invoking `cd` with a relative file name that did not start with '`./`' or '`../`'. Posix 1003.1-2001 says that if a nonempty directory name from `CDPATH` is used successfully, `cd` prints the resulting absolute file name. Unfortunately this output can break

idioms like ‘`abs=‘cd src && pwd‘`’ because `abs` receives the name twice. Also, many shells do not conform to this part of Posix; for example, `zsh` prints the result only if a directory name other than ‘`.`’ was chosen from `CDPATH`.

In practice the shells that have this problem also support `unset`, so you can work around the problem as follows:

```
(unset CDPATH) >/dev/null 2>&1 && unset CDPATH
```

You can also avoid output by ensuring that your directory name is absolute or anchored at ‘`./`’, as in ‘`abs=‘cd ./src && pwd‘`’.

Autoconf-generated scripts automatically unset `CDPATH` if possible, so you need not worry about this problem in those scripts.

`DUALCASE` In the MKS shell, case statements and file name generation are case-insensitive unless `DUALCASE` is nonzero. Autoconf-generated scripts export this variable when they start up.

`ENV`
`MAIL`
`MAILPATH`
`PS1`
`PS2`
`PS4` These variables should not matter for shell scripts, since they are supposed to affect only interactive shells. However, at least one shell (the pre-3.0 UWIN Korn shell) gets confused about whether it is interactive, which means that (for example) a `PS1` with a side effect can unexpectedly modify ‘`$?`’. To work around this bug, Autoconf-generated scripts do something like this:

```
(unset ENV) >/dev/null 2>&1 && unset ENV MAIL MAILPATH
PS1='$ '
PS2='> '
PS4='+ '
```

`IFS` Long ago, shell scripts inherited `IFS` from the environment, but this caused many problems so modern shells ignore any environment settings for `IFS`.

Don’t set the first character of `IFS` to backslash. Indeed, Bourne shells use the first character (backslash) when joining the components in ‘`"$@"`’ and some shells then reinterpret (!) the backslash escapes, so you can end up with backspace and other strange characters.

The proper value for `IFS` (in regular code, not when performing splits) is ‘⟨SPC⟩⟨TAB⟩⟨RET⟩’. The first character is especially important, as it is used to join the arguments in ‘`$*`’; however, note that traditional shells, but also bash-2.04, fail to adhere to this and join with a space anyway.

`LANG`
`LC_ALL`
`LC_COLLATE`
`LC_CTYPE`
`LC_MESSAGES`
`LC_MONETARY`
`LC_NUMERIC`
`LC_TIME`

Autoconf-generated scripts normally set all these variables to '`C`' because so much configuration code assumes the C locale and Posix requires that locale environment variables be set to '`C`' if the C locale is desired. However, some older, nonstandard systems (notably SCO) break if locale environment variables are set to '`C`', so when running on these systems Autoconf-generated scripts unset the variables instead.

`LANGUAGE`

`LANGUAGE` is not specified by Posix, but it is a GNU extension that overrides `LC_ALL` in some cases, so Autoconf-generated scripts set it too.

`LC_ADDRESS`
`LC_IDENTIFICATION`
`LC_MEASUREMENT`
`LC_NAME`
`LC_PAPER`
`LC_TELEPHONE`

These locale environment variables are GNU extensions. They are treated like their Posix brethren (`LC_COLLATE`, etc.) as described above.

`LINENO` Most modern shells provide the current line number in `LINENO`. Its value is the line number of the beginning of the current command. Autoconf attempts to execute `configure` with a shell that supports `LINENO`. If no such shell is available, it attempts to implement `LINENO` with a Sed prepass that replaces each instance of the string `$LINENO` (not followed by an alphanumeric character) with the line's number.

You should not rely on `LINENO` within `eval`, as the behavior differs in practice. Also, the possibility of the Sed prepass means that you should not rely on `$LINENO` when quoted, when in here-documents, or when in long commands that cross line boundaries. Subshells should be OK, though. In the following example, lines 1, 6, and 9 are portable, but the other instances of `LINENO` are not:

```
$ cat lineno
echo 1. $LINENO
cat <<EOF
3. $LINENO
4. $LINENO
EOF
( echo 6. $LINENO )
eval 'echo 7. $LINENO'
echo 8. '$LINENO'
echo 9. $LINENO '
10.' $LINENO
$ bash-2.05 lineno
1. 1
3. 2
4. 2
6. 6
7. 1
8. $LINENO
9. 9
10. 9
$ zsh-3.0.6 lineno
1. 1
3. 2
4. 2
6. 6
7. 7
8. $LINENO
9. 9
10. 9
$ pdksh-5.2.14 lineno
1. 1
3. 2
4. 2
6. 6
7. 0
8. $LINENO
9. 9
10. 9
```

```
$ sed '=' <lineno |
>   sed '
>     N
>     s,$,-,
>     t loop
>     :loop
>     s,^\([0-9]*\)\(.*\)[$]LINENO\([^a-zA-Z0-9_]\),\1\2\1\3,
>     t loop
>     s,-$,,
>     s,^[0-9]*\n,,
>   ' |
>   sh
1. 1
3. 3
4. 4
6. 6
7. 7
8. 8
9. 9
10. 10
```

`NULLCMD` When executing the command '`>foo`', `zsh` executes '`$NULLCMD >foo`' unless it is operating in Bourne shell compatibility mode and the `zsh` version is newer than 3.1.6-dev-18. If you are using an older `zsh` and forget to set `NULLCMD`, your script might be suspended waiting for data on its standard input.

`PATH_SEPARATOR`
On DJGPP systems, the `PATH_SEPARATOR` environment variable can be set to either '`:`' or '`;`' to control the path separator Bash uses to set up certain environment variables (such as `PATH`). You can set this variable to '`;`' if you want `configure` to use '`;`' as a separator; this might be useful if you plan to use non-Posix shells to execute files. See Section 10.4 [File System Conventions], page 138, for more information about `PATH_SEPARATOR`.

`PWD` Posix 1003.1-2001 requires that `cd` and `pwd` must update the `PWD` environment variable to point to the logical name of the current directory, but traditional shells do not support this. This can cause confusion if one shell instance maintains `PWD` but a subsidiary and different shell does not know about `PWD` and executes `cd`; in this case `PWD` points to the wrong directory. Use '`` `pwd` ``' rather than '`$PWD`'.

`RANDOM` Many shells provide `RANDOM`, a variable that returns a different integer each time it is used. Most of the time, its value does not change when it is not used, but on IRIX 6.5 the value changes all the time. This can be observed by using `set`. It is common practice to use `$RANDOM` as part of a file name, but code shouldn't rely on `$RANDOM` expanding to a nonempty string.

`status` This variable is an alias to '`$?`' for `zsh` (at least 3.1.6), hence read-only. Do not use it.

10.10 Limitations of Shell Builtins

No, no, we are serious: some shells do have limitations! :)

You should always keep in mind that any builtin or command may support options, and therefore differ in behavior with arguments starting with a dash. For instance, the innocent '`echo "$word"`' can give unexpected results when `word` starts with a dash. It is often possible to avoid this problem using '`echo "x$word"`', taking the '`x`' into account later in the pipe.

`.` Use `.` only with regular files (use '`test -f`'). Bash 2.03, for instance, chokes on '`. /dev/null`'. Also, remember that `.` uses `PATH` if its argument contains no slashes, so if you want to use `.` on a file '`foo`' in the current directory, you must use '`. ./foo`'.

`!` The Unix version 7 shell did not support negating the exit status of commands with `!`, and this feature is still absent from some shells (e.g., Solaris `/bin/sh`). Shell code like this:

```
if ! cmp file1 file2 >/dev/null 2>&1; then
  echo files differ or trouble
fi
```

is therefore not portable in practice. Typically it is easy to rewrite such code, e.g.:

```
cmp file1 file2 >/dev/null 2>&1 ||
  echo files differ or trouble
```

More generally, one can always rewrite '`! command`' as:

```
if command; then (exit 1); else :; fi
```

`break` The use of '`break 2`' etc. is safe.

`case` You don't need to quote the argument; no splitting is performed.

You don't need the final '`;;`', but you should use it.

Because of a bug in its `fnmatch`, Bash fails to properly handle backslashes in character classes:

```
bash-2.02$ case /tmp in [/\\]*) echo OK;; esac
bash-2.02$
```

This is extremely unfortunate, since you are likely to use this code to handle Posix or MS-DOS absolute file names. To work around this bug, always put the backslash first:

```
bash-2.02$ case '\TMP' in [\\/]*) echo OK;; esac
OK
bash-2.02$ case /tmp in [\\/]*) echo OK;; esac
OK
```

Many Bourne shells cannot handle closing brackets in character classes correctly.

Some shells also have problems with backslash escaping in case you do not want to match the backslash: both a backslash and the escaped character match this pattern. To work around this, specify the character class in a variable, so that quote removal does not apply afterwards, and the special characters don't have to be backslash-escaped:

```
$ case '\' in [\<]) echo OK;; esac
OK
$ scanset='[<]'; case '\' in $scanset) echo OK;; esac
$
```

Even with this, Solaris `ksh` matches a backslash if the set contains any of the characters '`|`', '`&`', '`(`', or '`)`'.

Conversely, Tru64 `ksh` (circa 2003) erroneously always matches a closing parenthesis if not specified in a character class:

```
$ case foo in *\)*) echo fail ;; esac
fail
$ case foo in *')'*) echo fail ;; esac
fail
```

Some shells, such as Ash 0.3.8, are confused by an empty `case`/`esac`:

```
ash-0.3.8 $ case foo in esac;
error Syntax error: ";" unexpected (expecting ")")
```

Many shells still do not support parenthesized cases, which is a pity for those of us using tools that rely on balanced parentheses. For instance, Solaris `/bin/sh`:

```
$ case foo in (foo) echo foo;; esac
error syntax error: '(' unexpected
```

`cd` Posix 1003.1-2001 requires that `cd` must support the '`-L`' ("logical") and '`-P`' ("physical") options, with '`-L`' being the default. However, traditional shells do not support these options, and their `cd` command has the '`-P`' behavior.

Portable scripts should assume neither option is supported, and should assume neither behavior is the default. This can be a bit tricky, since the Posix default behavior means that, for example, '`ls ..`' and '`cd ..`' may refer to different directories if the current logical directory is a symbolic link. It is safe to use `cd` *`dir`* if *dir* contains no '`..`' components. Also, Autoconf-generated scripts check for this problem when computing variables like `ac_top_srcdir` (see Section 4.5 [Configuration Actions], page 20), so it is safe to `cd` to these variables.

See See Section 10.9 [Special Shell Variables], page 145, for portability problems involving `cd` and the `CDPATH` environment variable. Also please see the discussion of the `pwd` command.

`echo` The simple `echo` is probably the most surprising source of portability troubles. It is not possible to use '`echo`' portably unless both options and escape sequences are omitted. New applications which are not aiming at portability should use '`printf`' instead of '`echo`'.

Don't expect any option. See Section 4.7.1 [Preset Output Variables], page 23, `ECHO_N` etc. for a means to simulate '`-n`'.

Do not use backslashes in the arguments, as there is no consensus on their handling. For '`echo '\n' | wc -l`', the `sh` of Solaris outputs 2, but Bash and Zsh (in `sh` emulation mode) output 1. The problem is truly `echo`: all the shells understand ''`\n`'' as the string composed of a backslash and an '`n`'.

Because of these problems, do not pass a string containing arbitrary characters to `echo`. For example, '`echo "$foo"`' is safe if you know that *foo*'s value cannot

contain backslashes and cannot start with '-', but otherwise you should use a here-document like this:

```
cat <<EOF
$foo
EOF
```

`eval` The `eval` command is useful in limited circumstances, e.g., using commands like '`eval table_$key=\$value`' and '`eval value=table_$key`' to simulate a hash table when the key is known to be alphanumeric. However, `eval` is tricky to use on arbitrary arguments, even when it is implemented correctly.

It is obviously unwise to use '`eval $cmd`' if the string value of '`cmd`' was derived from an untrustworthy source. But even if the string value is valid, '`eval $cmd`' might not work as intended, since it causes field splitting and file name expansion to occur twice, once for the `eval` and once for the command itself. It is therefore safer to use '`eval "$cmd"`'. For example, if *cmd* has the value '`cat test?.c`', '`eval $cmd`' might expand to the equivalent of '`cat test;.c`' if there happens to be a file named '`test;.c`' in the current directory; and this in turn mistakenly attempts to invoke `cat` on the file '`test`' and then execute the command `.c`. To avoid this problem, use '`eval "$cmd"`' rather than '`eval $cmd`'.

However, suppose that you want to output the text of the evaluated command just before executing it. Assuming the previous example, '`echo "Executing: $cmd"`' outputs '`Executing: cat test?.c`', but this output doesn't show the user that '`test;.c`' is the actual name of the copied file. Conversely, '`eval "echo Executing: $cmd"`' works on this example, but it fails with '`cmd='cat foo >bar'`', since it mistakenly replaces the contents of '`bar`' by the string '`cat foo`'. No simple, general, and portable solution to this problem is known.

You should also be wary of common bugs in `eval` implementations. In some shell implementations (e.g., older `ash`, OpenBSD 3.8 `sh`, `pdksh` v5.2.14 99/07/13.2, and `zsh` 4.2.5), the arguments of '`eval`' are evaluated in a context where '`$?`' is 0, so they exhibit behavior like this:

```
$ false; eval 'echo $?'
0
```

The correct behavior here is to output a nonzero value, but portable scripts should not rely on this.

You should not rely on `LINENO` within `eval`. See Section 10.9 [Special Shell Variables], page 145.

`exit` The default value of `exit` is supposed to be `$?`; unfortunately, some shells, such as the DJGPP port of Bash 2.04, just perform '`exit 0`'.

```
bash-2.04$ foo=`exit 1` || echo fail
fail
bash-2.04$ foo=`(exit 1)` || echo fail
fail
bash-2.04$ foo=`(exit 1); exit` || echo fail
bash-2.04$
```

Using '`exit $?`' restores the expected behavior.

Some shell scripts, such as those generated by `autoconf`, use a trap to clean up before exiting. If the last shell command exited with nonzero status, the trap also exits with nonzero status so that the invoker can tell that an error occurred.

Unfortunately, in some shells, such as Solaris `/bin/sh`, an exit trap ignores the `exit` command's argument. In these shells, a trap cannot determine whether it was invoked by plain `exit` or by `exit 1`. Instead of calling `exit` directly, use the `AC_MSG_ERROR` macro that has a workaround for this problem.

`export` The builtin `export` dubs a shell variable *environment variable*. Each update of exported variables corresponds to an update of the environment variables. Conversely, each environment variable received by the shell when it is launched should be imported as a shell variable marked as exported.

Alas, many shells, such as Solaris `/bin/sh`, IRIX 6.3, IRIX 5.2, AIX 4.1.5, and Digital Unix 4.0, forget to `export` the environment variables they receive. As a result, two variables coexist: the environment variable and the shell variable. The following code demonstrates this failure:

```
#!/bin/sh
echo $FOO
FOO=bar
echo $FOO
exec /bin/sh $0
```

when run with '`FOO=foo`' in the environment, these shells print alternately '`foo`' and '`bar`', although they should print only '`foo`' and then a sequence of '`bar`'s.

Therefore you should `export` again each environment variable that you update.

`false` Don't expect `false` to exit with status 1: in native Solaris '`/bin/false`' exits with status 255.

`for` To loop over positional arguments, use:

```
for arg
do
  echo "$arg"
done
```

You may *not* leave the `do` on the same line as `for`, since some shells improperly grok:

```
for arg; do
  echo "$arg"
done
```

If you want to explicitly refer to the positional arguments, given the '`$@`' bug (see Section 10.5 [Shell Substitutions], page 140), use:

```
for arg in ${1+"$@"}; do
  echo "$arg"
done
```

But keep in mind that Zsh, even in Bourne shell emulation mode, performs word splitting on '`${1+"$@"}`'; see Section 10.5 [Shell Substitutions], page 140, item '`$@`', for more.

`if` Using '`!`' is not portable. Instead of:

```
if ! cmp -s file file.new; then
  mv file.new file
fi
```

use:

```
if cmp -s file file.new; then :; else
  mv file.new file
fi
```

There are shells that do not reset the exit status from an `if`:

```
$ if (exit 42); then true; fi; echo $?
42
```

whereas a proper shell should have printed '`0`'. This is especially bad in makefiles since it produces false failures. This is why properly written makefiles, such as Automake's, have such hairy constructs:

```
if test -f "$file"; then
  install "$file" "$dest"
else
  :
fi
```

`printf` A format string starting with a '`-`' can cause problems. Bash (e.g., 2.05b) interprets it as an options argument and gives an error. And '`--`' to mark the end of options is not good in the NetBSD Almquist shell (e.g., 0.4.6) which takes that literally as the format string. Putting the '`-`' in a '`%c`' or '`%s`' is probably the easiest way to avoid doubt,

```
printf %s -foo
```

`read` Not all shells support '`-r`' (Solaris `/bin/sh` for example).

`pwd` With modern shells, plain `pwd` outputs a "logical" directory name, some of whose components may be symbolic links. These directory names are in contrast to "physical" directory names, whose components are all directories.

Posix 1003.1-2001 requires that `pwd` must support the '`-L`' ("logical") and '`-P`' ("physical") options, with '`-L`' being the default. However, traditional shells do not support these options, and their `pwd` command has the '`-P`' behavior.

Portable scripts should assume neither option is supported, and should assume neither behavior is the default. Also, on many hosts '`/bin/pwd`' is equivalent to '`pwd -P`', but Posix does not require this behavior and portable scripts should not rely on it.

Typically it's best to use plain `pwd`. On modern hosts this outputs logical directory names, which have the following advantages:

- Logical names are what the user specified.

- Physical names may not be portable from one installation host to another due to network file system gymnastics.
- On modern hosts '`pwd -P`' may fail due to lack of permissions to some parent directory, but plain `pwd` cannot fail for this reason.

Also please see the discussion of the `cd` command.

`set` With the FreeBSD 6.0 shell, the `set` command (without any options) does not sort its output.

The `set` builtin faces the usual problem with arguments starting with a dash. Modern shells such as Bash or Zsh understand '`--`' to specify the end of the options (any argument after '`--`' is a parameter, even '`-x`' for instance), but many traditional shells (e.g., Solaris 10 `/bin/sh`) simply stop option processing as soon as a non-option argument is found. Therefore, use '`dummy`' or simply '`x`' to end the option processing, and use `shift` to pop it out:

```
set x $my_list; shift
```

Avoid '`set -`', e.g., '`set - $my_list`'. Posix no longer requires support for this command, and in traditional shells '`set - $my_list`' resets the '`-v`' and '`-x`' options, which makes scripts harder to debug.

Some nonstandard shells do not recognize more than one option (e.g., '`set -e -x`' assigns '`-x`' to the command line). It is better to combine them:

```
set -ex
```

The BSD shell has had several problems with the '`-e`' option, partly because BSD `make` traditionally used '`-e`' even though this was incompatible with Posix (see Section 11.2 [Failure in Make Rules], page 171). Older versions of the BSD shell (circa 1990) mishandled '`&&`', '`||`', '`if`', and '`case`' when '`-e`' was in effect, causing the shell to exit unexpectedly in some cases. This was particularly a problem with makefiles, and led to circumlocutions like '`sh -c 'test -f file || touch file'`', where the seemingly-unnecessary '`sh -c '...'`' wrapper works around the bug.

Even relatively-recent versions of the BSD shell (e.g., OpenBSD 3.4) wrongly exit with '`-e`' if a command within '`&&`' fails inside a compound statement. For example:

```
#! /bin/sh
set -e
foo=''
test -n "$foo" && exit 1
echo one
if :; then
  test -n "$foo" && exit 1
fi
echo two
```

does not print '`two`'. One workaround is to use '`if test -n "$foo"; then exit 1; fi`' rather than '`test -n "$foo" && exit 1`'. Another possibility is to warn BSD users not to use '`sh -e`'.

`shift` Not only is `shift`ing a bad idea when there is nothing left to shift, but in addition it is not portable: the shell of MIPS RISC/OS 4.52 refuses to do it.

Don't use '`shift 2`' etc.; it was not in the 7th Edition Bourne shell, and it is also absent in many pre-Posix shells.

`source` This command is not portable, as Posix does not require it; use `.` instead.

`test` The `test` program is the way to perform many file and string tests. It is often invoked by the alternate name '`[`', but using that name in Autoconf code is asking for trouble since it is an M4 quote character.

If you need to make multiple checks using `test`, combine them with the shell operators '`&&`' and '`||`' instead of using the `test` operators '`-a`' and '`-o`'. On System V, the precedence of '`-a`' and '`-o`' is wrong relative to the unary operators; consequently, Posix does not specify them, so using them is nonportable. If you combine '`&&`' and '`||`' in the same statement, keep in mind that they have equal precedence.

It is safe to use '`!`' as a `test` operator. For example, '`if test ! -d foo; ...`' is portable even though '`if ! test -d foo; ...`' is not.

`test` (files)

To enable `configure` scripts to support cross-compilation, they shouldn't do anything that tests features of the build system instead of the host system. But occasionally you may find it necessary to check whether some arbitrary file exists. To do so, use '`test -f`' or '`test -r`'. Do not use '`test -x`', because 4.3BSD does not have it. Do not use '`test -e`' either, because Solaris `/bin/sh` lacks it. To test for symbolic links on systems that have them, use '`test -h`' rather than '`test -L`'; either form conforms to Posix 1003.1-2001, but older shells like Solaris 8 `/bin/sh` support only '`-h`'.

`test` (strings)

Avoid '`test "`*`string`*`"`', in particular if *string* might start with a dash, since `test` might interpret its argument as an option (e.g., '*`string`* `= "-n"`').

Contrary to a common belief, '`test -n `*`string`*' and '`test -z `*`string`*' **are** portable. Nevertheless many shells (such as Solaris, AIX 3.2, UNICOS 10.0.0.6, Digital Unix 4, etc.) have bizarre precedence and may be confused if *string* looks like an operator:

```
$ test -n =
test: argument expected
```

If there are risks, use '`test "x`*`string`*`" = x`' or '`test "x`*`string`*`" != x`' instead.

It is common to find variations of the following idiom:

```
test -n "`echo $ac_feature | sed 's/[-a-zA-Z0-9_]//g'`" &&
  action
```

to take an action when a token matches a given pattern. Such constructs should always be avoided by using:

```
echo "$ac_feature" | grep '[^-a-zA-Z0-9_]' >/dev/null 2>&1 &&
  action
```

Use `case` where possible since it is faster, being a shell builtin:

```
case $ac_feature in
  *[!-a-zA-Z0-9_]*) action;;
esac
```

Alas, negated character classes are probably not portable, although no shell is known to not support the Posix syntax '`[!...]`' (when in interactive mode, `zsh` is confused by the '`[!...]`' syntax and looks for an event in its history because of '`!`'). Many shells do not support the alternative syntax '`[^...]`' (Solaris, Digital Unix, etc.).

One solution can be:

```
expr "$ac_feature" : '.*[^-a-zA-Z0-9_]' >/dev/null &&
  action
```

or better yet

```
expr "X$ac_feature" : '.*[^-a-zA-Z0-9_]' >/dev/null &&
  action
```

'`expr "X`*foo*`" : "X`*bar*`"`' is more robust than '`echo "X`*foo*`" | grep "^X`*bar*`"`', because it avoids problems when '*foo*' contains backslashes.

`trap` It is safe to trap at least the signals 1, 2, 13, and 15. You can also trap 0, i.e., have the `trap` run when the script ends (either via an explicit `exit`, or the end of the script).

Posix says that '`trap - 1 2 13 15`' resets the traps for the specified signals to their default values, but many common shells (e.g., Solaris `/bin/sh`) misinterpret this and attempt to execute a "command" named `-` when the specified conditions arise. There is no portable workaround, except for '`trap - 0`', for which '`trap '' 0`' is a portable substitute.

Although Posix is not absolutely clear on this point, it is widely admitted that when entering the trap '`$?`' should be set to the exit status of the last command run before the trap. The ambiguity can be summarized as: "when the trap is launched by an `exit`, what is the *last* command run: that before `exit`, or `exit` itself?"

Bash considers `exit` to be the last command, while Zsh and Solaris `/bin/sh` consider that when the trap is run it is *still* in the `exit`, hence it is the previous exit status that the trap receives:

```
$ cat trap.sh
trap 'echo $?' 0
(exit 42); exit 0
$ zsh trap.sh
42
$ bash trap.sh
0
```

The portable solution is then simple: when you want to '`exit 42`', run '`(exit 42); exit 42`', the first `exit` being used to set the exit status to 42 for Zsh, and the second to trigger the trap and pass 42 as exit status for Bash.

The shell in FreeBSD 4.0 has the following bug: '`$?`' is reset to 0 by empty lines if the code is inside `trap`.

```
$ trap 'false

echo $?' 0
$ exit
0
```

Fortunately, this bug only affects `trap`.

`true` Don't worry: as far as we know `true` is portable. Nevertheless, it's not always a builtin (e.g., Bash 1.x), and the portable shell community tends to prefer using `:`. This has a funny side effect: when asked whether `false` is more portable than `true` Alexandre Oliva answered:

> In a sense, yes, because if it doesn't exist, the shell will produce an exit status of failure, which is correct for `false`, but not for `true`.

`unset` You cannot assume the support of `unset`. Nevertheless, because it is extremely useful to disable embarrassing variables such as `PS1`, you can test for its existence and use it *provided* you give a neutralizing value when `unset` is not supported:

```
if (unset FOO) >/dev/null 2>&1; then
  unset=unset
else
  unset=false
fi
$unset PS1 || PS1='$ '
```

See Section 10.9 [Special Shell Variables], page 145, for some neutralizing values. Also, see Section 10.10 [Limitations of Builtins], page 150, documentation of `export`, for the case of environment variables.

10.11 Limitations of Usual Tools

The small set of tools you can expect to find on any machine can still include some limitations you should be aware of.

Awk Don't leave white space before the opening parenthesis in a user function call. Posix does not allow this and GNU Awk rejects it:

```
$ gawk 'function die () { print "Aaaaarg!"  }
        BEGIN { die () }'
gawk: cmd. line:2:         BEGIN { die () }
gawk: cmd. line:2:                       ^ parse error
$ gawk 'function die () { print "Aaaaarg!"  }
        BEGIN { die() }'
Aaaaarg!
```

If you want your program to be deterministic, don't depend on `for` on arrays:

```
$ cat for.awk
END {
  arr["foo"] = 1
  arr["bar"] = 1
```

```
  for (i in arr)
    print i
}
$ gawk -f for.awk </dev/null
foo
bar
$ nawk -f for.awk </dev/null
bar
foo
```

Some Awk implementations, such as HP-UX 11.0's native one, mishandle anchors:

```
$ echo xfoo | $AWK '/foo|^bar/ { print }'
$ echo bar | $AWK '/foo|^bar/ { print }'
bar
$ echo xfoo | $AWK '/^bar|foo/ { print }'
xfoo
$ echo bar | $AWK '/^bar|foo/ { print }'
bar
```

Either do not depend on such patterns (i.e., use '`/^(.*foo|bar)/`', or use a simple test to reject such implementations.

AIX version 5.2 has an arbitrary limit of 399 on the the length of regular expressions and literal strings in an Awk program.

Traditional Awk implementations derived from Unix version 7, such as Solaris `/bin/awk`, have many limitations and do not conform to Posix. Nowadays `AC_PROG_AWK` (see Section 5.2.1 [Particular Programs], page 41) finds you an Awk that doesn't have these problems, but if for some reason you prefer not to use `AC_PROG_AWK` you may need to address them.

Traditional Awk does not support multidimensional arrays or user-defined functions.

Traditional Awk does not support the '`-v`' option. You can use assignments after the program instead, e.g., `$AWK '{print v $1}' v=x`; however, don't forget that such assignments are not evaluated until they are encountered (e.g., after any `BEGIN` action).

Traditional Awk does not support the keywords `delete` or `do`.

Traditional Awk does not support the expressions `a?b:c`, `!a`, `a^b`, or `a^=b`.

Traditional Awk does not support the predefined `CONVFMT` variable.

Traditional Awk supports only the predefined functions `exp`, `int`, `length`, `log`, `split`, `sprintf`, `sqrt`, and `substr`.

Traditional Awk `getline` is not at all compatible with Posix; avoid it.

Traditional Awk `split` supports only two arguments.

Traditional Awk has a limit of 99 fields in a record. You may be able to circumvent this problem by using `split`.

`basename` Not all hosts have a working `basename`. You can use `expr` instead.

`cat` Don't rely on any option.

`cc` The command '`cc -c foo.c`' traditionally produces an object file named '`foo.o`'. Most compilers allow '`-c`' to be combined with '`-o`' to specify a different object file name, but Posix does not require this combination and a few compilers lack support for it. See Section 5.10.3 [C Compiler], page 72, for how GNU Make tests for this feature with `AC_PROG_CC_C_O`.

When a compilation such as '`cc -o foo foo.c`' fails, some compilers (such as CDS on Reliant Unix) leave a '`foo.o`'.

HP-UX `cc` doesn't accept '`.S`' files to preprocess and assemble. '`cc -c foo.S`' appears to succeed, but in fact does nothing.

The default executable, produced by '`cc foo.c`', can be

- '`a.out`' — usual Posix convention.
- '`b.out`' — i960 compilers (including `gcc`).
- '`a.exe`' — DJGPP port of `gcc`.
- '`a_out.exe`' — GNV `cc` wrapper for DEC C on OpenVMS.
- '`foo.exe`' — various MS-DOS compilers.

The C compiler's traditional name is `cc`, but other names like `gcc` are common. Posix 1003.1-2001 specifies the name `c99`, but older Posix editions specified `c89` and anyway these standard names are rarely used in practice. Typically the C compiler is invoked from makefiles that use '`$(CC)`', so the value of the '`CC`' make variable selects the compiler name.

`chmod` Avoid usages like '`chmod -w file`'; use '`chmod a-w file`' instead, for two reasons. First, plain '`-w`' does not necessarily make the file unwritable, since it does not affect mode bits that correspond to bits in the file mode creation mask. Second, Posix says that the '`-w`' might be interpreted as an implementation-specific option, not as a mode; Posix suggests using '`chmod -- -w file`' to avoid this confusion, but unfortunately '`--`' does not work on some older hosts.

`cmp` `cmp` performs a raw data comparison of two files, while `diff` compares two text files. Therefore, if you might compare DOS files, even if only checking whether two files are different, use `diff` to avoid spurious differences due to differences of newline encoding.

`cp` Avoid the '`-r`' option, since Posix 1003.1-2004 marks it as obsolescent and its behavior on special files is implementation-defined. Use '`-R`' instead. On GNU hosts the two options are equivalent, but on Solaris hosts (for example) `cp -r` reads from pipes instead of replicating them.

Some `cp` implementations (e.g., BSD/OS 4.2) do not allow trailing slashes at the end of nonexistent destination directories. To avoid this problem, omit the trailing slashes. For example, use '`cp -R source /tmp/newdir`' rather than '`cp -R source /tmp/newdir/`' if '`/tmp/newdir`' does not exist.

The ancient SunOS 4 `cp` does not support '`-f`', although its `mv` does.

Traditionally, file timestamps had 1-second resolution, and '`cp -p`' copied the timestamps exactly. However, many modern file systems have timestamps

with 1-nanosecond resolution. Unfortunately, '`cp -p`' implementations truncate timestamps when copying files, so this can result in the destination file appearing to be older than the source. The exact amount of truncation depends on the resolution of the system calls that `cp` uses; traditionally this was `utime`, which has 1-second resolution, but some newer `cp` implementations use `utimes`, which has 1-microsecond resolution. These newer implementations include GNU Core Utilities 5.0.91 or later, and Solaris 8 (sparc) patch 109933-02 or later. Unfortunately as of January 2006 there is still no system call to set timestamps to the full nanosecond resolution.

Bob Proulx notes that '`cp -p`' always *tries* to copy ownerships. But whether it actually does copy ownerships or not is a system dependent policy decision implemented by the kernel. If the kernel allows it then it happens. If the kernel does not allow it then it does not happen. It is not something `cp` itself has control over.

In Unix System V any user can chown files to any other user, and System V also has a non-sticky '`/tmp`'. That probably derives from the heritage of System V in a business environment without hostile users. BSD changed this to be a more secure model where only root can `chown` files and a sticky '`/tmp`' is used. That undoubtedly derives from the heritage of BSD in a campus environment.

GNU/Linux and Solaris by default follow BSD, but can be configured to allow a System V style `chown`. On the other hand, HP-UX follows System V, but can be configured to use the modern security model and disallow `chown`. Since it is an administrator-configurable parameter you can't use the name of the kernel as an indicator of the behavior.

`date` Some versions of `date` do not recognize special '`%`' directives, and unfortunately, instead of complaining, they just pass them through, and exit with success:

```
$ uname -a
OSF1 medusa.sis.pasteur.fr V5.1 732 alpha
$ date "+%s"
%s
```

`diff` Option '`-u`' is nonportable.

Some implementations, such as Tru64's, fail when comparing to '`/dev/null`'. Use an empty file instead.

`dirname` Not all hosts have a working `dirname`, and you should instead use `AS_DIRNAME` (see Section 8.4 [Programming in M4sh], page 121). For example:

```
dir=`dirname "$file"`       # This is not portable.
dir=`AS_DIRNAME(["$file"])` # This is more portable.
```

`egrep` Posix 1003.1-2001 no longer requires `egrep`, but many older hosts do not yet support the Posix replacement `grep -E`. Also, some traditional implementations do not work on long input lines. To work around these problems, invoke `AC_PROG_EGREP` and then use `$EGREP`.

Portable extended regular expressions should use '`\`' only to escape characters in the string '`$()*+.?[\^{|`'. For example, '`\}`' is not portable, even though it typically matches '`}`'.

The empty alternative is not portable. Use '`?`' instead. For instance with Digital Unix v5.0:

```
> printf "foo\n|foo\n" | $EGREP '^(|foo|bar)$'
|foo
> printf "bar\nbar|\n" | $EGREP '^(foo|bar|)$'
bar|
> printf "foo\nfoo|\n|bar\nbar\n" | $EGREP '^(foo||bar)$'
foo
|bar
```

`$EGREP` also suffers the limitations of `grep`.

`expr` No `expr` keyword starts with '`X`', so use '`expr X"`*word*`" : 'X`*regex*`'`' to keep `expr` from misinterpreting *word*.

Don't use `length`, `substr`, `match` and `index`.

`expr` ('`|`') You can use '`|`'. Although Posix does require that '`expr '' `' return the empty string, it does not specify the result when you '`|`' together the empty string (or zero) with the empty string. For example:

```
expr '' \| ''
```

Posix 1003.2-1992 returns the empty string for this case, but traditional Unix returns '`0`' (Solaris is one such example). In Posix 1003.1-2001, the specification was changed to match traditional Unix's behavior (which is bizarre, but it's too late to fix this). Please note that the same problem does arise when the empty string results from a computation, as in:

```
expr bar : foo \| foo : bar
```

Avoid this portability problem by avoiding the empty string.

`expr` ('`:`') Portable `expr` regular expressions should use '`\`' to escape only characters in the string '`$()*.0123456789[\^n{}`'. For example, alternation, '`\|`', is common but Posix does not require its support, so it should be avoided in portable scripts. Similarly, '`\+`' and '`\?`' should be avoided.

Portable `expr` regular expressions should not begin with '`^`'. Patterns are automatically anchored so leading '`^`' is not needed anyway.

The Posix standard is ambiguous as to whether '`expr 'a' : '\(b\)'`' outputs '`0`' or the empty string. In practice, it outputs the empty string on most platforms, but portable scripts should not assume this. For instance, the QNX 4.25 native `expr` returns '`0`'.

One might think that a way to get a uniform behavior would be to use the empty string as a default value:

```
expr a : '\(b\)' \| ''
```

Unfortunately this behaves exactly as the original expression; see the `expr` ('`|`') entry for more information.

Ancient `expr` implementations (e.g., SunOS 4 `expr` and Solaris 8 `/usr/ucb/expr`) have a silly length limit that causes `expr` to fail if the matched substring is longer than 120 bytes. In this case, you might want to fall back on '`echo|sed`' if `expr` fails. Nowadays this is of practical importance

only for the rare installer who mistakenly puts '`/usr/ucb`' before '`/usr/bin`' in `PATH`.

On Mac OS X 10.4, `expr` mishandles the pattern '`[^-]`' in some cases. For example, the command

```
expr Xpowerpc-apple-darwin8.1.0 : 'X[^-]*-[^-]*-\(.*\)'
```

outputs '`apple-darwin8.1.0`' rather than the correct '`darwin8.1.0`'. This particular case can be worked around by substituting '`[^--]`' for '`[^-]`'.

Don't leave, there is some more!

The QNX 4.25 `expr`, in addition of preferring '`0`' to the empty string, has a funny behavior in its exit status: it's always 1 when parentheses are used!

```
$ val=`expr 'a' : 'a'`; echo "$?: $val"
0: 1
$ val=`expr 'a' : 'b'`; echo "$?: $val"
1: 0

$ val=`expr 'a' : '\(a\)'`; echo "?: $val"
1: a
$ val=`expr 'a' : '\(b\)'`; echo "?: $val"
1: 0
```

In practice this can be a big problem if you are ready to catch failures of `expr` programs with some other method (such as using `sed`), since you may get twice the result. For instance

```
$ expr 'a' : '\(a\)' || echo 'a' | sed 's/^\(a\)$/\1/'
```

outputs '`a`' on most hosts, but '`aa`' on QNX 4.25. A simple workaround consists of testing `expr` and using a variable set to `expr` or to `false` according to the result.

Tru64 `expr` incorrectly treats the result as a number, if it can be interpreted that way:

```
$ expr 00001 : '.*\(...\)'
1
```

`fgrep` Posix 1003.1-2001 no longer requires `fgrep`, but many older hosts do not yet support the Posix replacement `grep -F`. Also, some traditional implementations do not work on long input lines. To work around these problems, invoke `AC_PROG_FGREP` and then use `$FGREP`.

`find` The option '`-maxdepth`' seems to be GNU specific. Tru64 v5.1, NetBSD 1.5 and Solaris `find` commands do not understand it.

The replacement of '`{}`' is guaranteed only if the argument is exactly `{}`, not if it's only a part of an argument. For instance on DU, and HP-UX 10.20 and HP-UX 11:

```
$ touch foo
$ find . -name foo -exec echo "{}-{}" \;
{}-{}
```

while GNU `find` reports '`./foo-./foo`'.

`grep` Portable scripts can rely on the `grep` options '`-c`', '`-l`', '`-n`', and '`-v`', but should avoid other options. For example, don't use '`-w`', as Posix does not require it and Irix 6.5.16m's `grep` does not support it. Also, portable scripts should not combine '`-c`' with '`-l`', as Posix does not allow this.

Some of the options required by Posix are not portable in practice. Don't use '`grep -q`' to suppress output, because many `grep` implementations (e.g., Solaris) do not support '`-q`'. Don't use '`grep -s`' to suppress output either, because Posix says '`-s`' does not suppress output, only some error messages; also, the '`-s`' option of traditional `grep` behaved like '`-q`' does in most modern implementations. Instead, redirect the standard output and standard error (in case the file doesn't exist) of `grep` to '`/dev/null`'. Check the exit status of `grep` to determine whether it found a match.

Some traditional `grep` implementations do not work on long input lines. On AIX the default `grep` silently truncates long lines on the input before matching.

Also, many implementations do not support multiple regexps with '`-e`': they either reject '`-e`' entirely (e.g., Solaris) or honor only the last pattern (e.g., IRIX 6.5 and NeXT). To work around these problems, invoke `AC_PROG_GREP` and then use `$GREP`.

Another possible workaround for the multiple '`-e`' problem is to separate the patterns by newlines, for example:

```
grep 'foo
bar' in.txt
```

except that this fails with traditional `grep` implementations and with OpenBSD 3.8 `grep`.

Traditional `grep` implementations (e.g., Solaris) do not support the '`-E`' or '`-F`' options. To work around these problems, invoke `AC_PROG_EGREP` and then use `$EGREP`, and similarly for `AC_PROG_FGREP` and `$FGREP`. Even if you are willing to require support for Posix `grep`, your script should not use both '`-E`' and '`-F`', since Posix does not allow this combination.

Portable `grep` regular expressions should use '`\`' only to escape characters in the string '`$()*.0123456789[\^{}`'. For example, alternation, '`\|`', is common but Posix does not require its support in basic regular expressions, so it should be avoided in portable scripts. Solaris `grep` does not support it. Similarly, '`\+`' and '`\?`' should be avoided.

`join` Solaris 8 `join` has bugs when the second operand is standard input, and when standard input is a pipe. For example, the following shell script causes Solaris 8 `join` to loop forever:

```
cat >file <<'EOF'
1 x
2 y
EOF
cat file | join file -
```

Use '`join - file`' instead.

`ln` Don't rely on `ln` having a '`-f`' option. Symbolic links are not available on old systems; use '`$(LN_S)`' as a portable substitute.

For versions of the DJGPP before 2.04, `ln` emulates symbolic links to executables by generating a stub that in turn calls the real program. This feature also works with nonexistent files like in the Posix spec. So '`ln -s file link`' generates '`link.exe`', which attempts to call '`file.exe`' if run. But this feature only works for executables, so '`cp -p`' is used instead for these systems. DJGPP versions 2.04 and later have full support for symbolic links.

`ls` The portable options are '`-acdilrtu`'. Current practice is for '`-l`' to output both owner and group, even though ancient versions of `ls` omitted the group.

On ancient hosts, '`ls foo`' sent the diagnostic '`foo not found`' to standard output if '`foo`' did not exist. Hence a shell command like '`sources=`ls *.c 2>/dev/null``' did not always work, since it was equivalent to '`sources='*.c not found'`' in the absence of '`.c`' files. This is no longer a practical problem, since current `ls` implementations send diagnostics to standard error.

`mkdir` No `mkdir` option is portable to older systems. Instead of '`mkdir -p` *`file-name`*', you should use use `AS_MKDIR_P(`*`file-name`*`)` (see Section 8.4 [Programming in M4sh], page 121) or `AC_PROG_MKDIR_P` (see Section 5.2.1 [Particular Programs], page 41).

Posix does not clearly specify whether '`mkdir -p foo`' should succeed when '`foo`' is a symbolic link to an already-existing directory. The GNU Core Utilities 5.1.0 `mkdir` succeeds, but Solaris `mkdir` fails.

Traditional `mkdir -p` implementations suffer from race conditions. For example, if you invoke `mkdir -p a/b` and `mkdir -p a/c` at the same time, both processes might detect that '`a`' is missing, one might create '`a`', then the other might try to create '`a`' and fail with a `File exists` diagnostic. The GNU Core Utilities ('`fileutils`' version 4.1), FreeBSD 5.0, NetBSD 2.0.2, and OpenBSD 2.4 are known to be race-free when two processes invoke `mkdir -p` simultaneously, but earlier versions are vulnerable. Solaris `mkdir` is still vulnerable as of Solaris 10, and other traditional Unix systems are probably vulnerable too. This possible race is harmful in parallel builds when several Make rules call `mkdir -p` to construct directories. You may use `install-sh -d` as a safe replacement, provided this script is recent enough; the copy shipped with Autoconf 2.60 and Automake 1.10 is OK, but copies from older versions are vulnerable.

`mktemp` Shell scripts can use temporary files safely with `mktemp`, but it does not exist on all systems. A portable way to create a safe temporary file name is to create a temporary directory with mode 700 and use a file inside this directory. Both methods prevent attackers from gaining control, though `mktemp` is far less likely to fail gratuitously under attack.

Here is sample code to create a new temporary directory safely:

```
# Create a temporary directory $tmp in $TMPDIR (default /tmp).
# Use mktemp if possible; otherwise fall back on mkdir,
# with $RANDOM to make collisions less likely.
: ${TMPDIR=/tmp}
```

```
{
  tmp=‘
    (umask 077 && mktemp -d "$TMPDIR/fooXXXXXX") 2>/dev/null
  ‘ &&
  test -n "$tmp" && test -d "$tmp"
} || {
  tmp=$TMPDIR/foo$$-$RANDOM
  (umask 077 && mkdir "$tmp")
} || exit $?
```

`mv` The only portable options are ‘`-f`’ and ‘`-i`’.

Moving individual files between file systems is portable (it was in Unix version 6), but it is not always atomic: when doing ‘`mv new existing`’, there's a critical section where neither the old nor the new version of ‘`existing`’ actually exists.

On some systems moving files from ‘`/tmp`’ can sometimes cause undesirable (but perfectly valid) warnings, even if you created these files. This is because ‘`/tmp`’ belongs to a group that ordinary users are not members of, and files created in ‘`/tmp`’ inherit the group of ‘`/tmp`’. When the file is copied, `mv` issues a diagnostic without failing:

```
$ touch /tmp/foo
$ mv /tmp/foo .
error mv: ./foo: set owner/group (was: 100/0): Operation not permitted
$ echo $?
0
$ ls foo
foo
```

This annoying behavior conforms to Posix, unfortunately.

Moving directories across mount points is not portable, use `cp` and `rm`.

Moving/Deleting open files isn't portable. The following can't be done on DOS variants:

```
exec > foo
mv foo bar
```

nor can

```
exec > foo
rm -f foo
```

`od`

In Mac OS X 10.3, `od` does not support the standard Posix options ‘`-A`’, ‘`-j`’, ‘`-N`’, or ‘`-t`’, or the XSI option ‘`-s`’. The only supported Posix option is ‘`-v`’, and the only supported XSI options are those in ‘`-bcdox`’. The BSD `hexdump` program can be used instead.

This problem no longer exists in Mac OS X 10.4.3.

`sed` Patterns should not include the separator (unless escaped), even as part of a character class. In conformance with Posix, the Cray `sed` rejects ‘`s/[^/]*$//`’: use ‘`s,[^/]*$,,`’.

Avoid empty patterns within parentheses (i.e., ‘`\(\)`’). Posix does not require support for empty patterns, and Unicos 9 `sed` rejects them.

Unicos 9 `sed` loops endlessly on patterns like '`.*\n.*`'.

Sed scripts should not use branch labels longer than 8 characters and should not contain comments. HP-UX sed has a limit of 99 commands (not counting '`:`' commands) and 48 labels, which can not be circumvented by using more than one script file. It can execute up to 19 reads with the '`r`' command per cycle. Solaris `/usr/ucb/sed` rejects usages that exceed an limit of about 6000 bytes for the internal representation of commands.

Avoid redundant '`;`', as some `sed` implementations, such as NetBSD 1.4.2's, incorrectly try to interpret the second '`;`' as a command:

```
$ echo a | sed 's/x/x/;;s/x/x/'
sed: 1: "s/x/x/;;s/x/x/": invalid command code ;
```

Input should not have unreasonably long lines, since some `sed` implementations have an input buffer limited to 4000 bytes.

Portable `sed` regular expressions should use '`\`' only to escape characters in the string '`$()*.0123456789[\^n{}`'. For example, alternation, '`\|`', is common but Posix does not require its support, so it should be avoided in portable scripts. Solaris `sed` does not support alternation; e.g., '`sed '/a\|b/d'`' deletes only lines that contain the literal string '`a|b`'. Similarly, '`\+`' and '`\?`' should be avoided.

Anchors ('`^`' and '`$`') inside groups are not portable.

Nested parenthesization in patterns (e.g., '`\(\(a*\)b*\)\)`') is quite portable to current hosts, but was not supported by some ancient `sed` implementations like SVR3.

Some `sed` implementations, e.g., Solaris, restrict the special role of the asterisk to one-character regular expressions. This may lead to unexpected behavior:

```
$ echo '1*23*4' | /usr/bin/sed 's/\(.\)*/x/g'
x2x4
$ echo '1*23*4' | /usr/xpg4/bin/sed 's/\(.\)*/x/g'
x
```

The '`-e`' option is portable. Some people prefer to use it:

```
sed -e 'command-1' \
    -e 'command-2'
```

as opposed to the equivalent:

```
sed '
  command-1
  command-2
'
```

The following usage is sometimes equivalent:

```
sed 'command-1;command-2'
```

but Posix says that this use of a semicolon has undefined effect if *command-1*'s verb is '`{`', '`a`', '`b`', '`c`', '`i`', '`r`', '`t`', '`w`', '`:`', or '`#`', so you should use semicolon only with simple scripts that do not use these verbs.

Commands inside `{ }` brackets are further restricted. Posix says that they cannot be preceded by addresses, '`!`', or '`;`', and that each command must be

followed immediately by a newline, without any intervening blanks or semicolons. The closing bracket must be alone on a line, other than white space preceding or following it.

Contrary to yet another urban legend, you may portably use '`&`' in the replacement part of the `s` command to mean "what was matched". All descendants of Unix version 7 `sed` (at least; we don't have first hand experience with older `sed` implementations) have supported it.

Posix requires that you must not have any white space between '`!`' and the following command. It is OK to have blanks between the address and the '`!`'. For instance, on Solaris:

```
$ echo "foo" | sed -n '/bar/ ! p'
error Unrecognized command: /bar/ ! p
$ echo "foo" | sed -n '/bar/! p'
error Unrecognized command: /bar/! p
$ echo "foo" | sed -n '/bar/ !p'
foo
```

Posix also says that you should not combine '`!`' and '`;`'. If you use '`!`', it is best to put it on a command that is delimited by newlines rather than '`;`'.

Also note that Posix requires that the '`b`', '`t`', '`r`', and '`w`' commands be followed by exactly one space before their argument. On the other hand, no white space is allowed between '`:`' and the subsequent label name.

`sed` ('`t`') Some old systems have `sed` that "forget" to reset their '`t`' flag when starting a new cycle. For instance on MIPS RISC/OS, and on IRIX 5.3, if you run the following `sed` script (the line numbers are not actual part of the texts):

```
s/keep me/kept/g  # a
t end             # b
s/.*/deleted/g    # c
:end              # d
```

on

```
delete me         # 1
delete me         # 2
keep me           # 3
delete me         # 4
```

you get

```
deleted
delete me
kept
deleted
```

instead of

```
deleted
deleted
kept
deleted
```

Why? When processing line 1, (c) matches, therefore sets the '`t`' flag, and the output is produced. When processing line 2, the '`t`' flag is still set (this is the bug). Command (a) fails to match, but `sed` is not supposed to clear the '`t`' flag when a substitution fails. Command (b) sees that the flag is set, therefore it clears it, and jumps to (d), hence you get '`delete me`' instead of '`deleted`'. When processing line (3), '`t`' is clear, (a) matches, so the flag is set, hence (b) clears the flags and jumps. Finally, since the flag is clear, line 4 is processed properly.

There are two things one should remember about '`t`' in `sed`. Firstly, always remember that '`t`' jumps if *some* substitution succeeded, not only the immediately preceding substitution. Therefore, always use a fake '`t clear`' followed by a '`:clear`' on the next line, to reset the '`t`' flag where needed.

Secondly, you cannot rely on `sed` to clear the flag at each new cycle.

One portable implementation of the script above is:

```
t clear
:clear
s/keep me/kept/g
t end
s/.*/deleted/g
:end
```

`touch` If you specify the desired timestamp (e.g., with the '`-r`' option), `touch` typically uses the `utime` or `utimes` system call, which can result in the same kind of timestamp truncation problems that '`cp -p`' has.

On ancient BSD systems, `touch` or any command that results in an empty file does not update the timestamps, so use a command like `echo` as a workaround. Also, GNU `touch` 3.16r (and presumably all before that) fails to work on SunOS 4.1.3 when the empty file is on an NFS-mounted 4.2 volume. However, these problems are no longer of practical concern.

11 Portable Make Programming

Writing portable makefiles is an art. Since a makefile's commands are executed by the shell, you must consider the shell portability issues already mentioned. However, other issues are specific to `make` itself.

11.1 $< in Ordinary Make Rules

Posix says that the '`$<`' construct in makefiles can be used only in inference rules and in the '`.DEFAULT`' rule; its meaning in ordinary rules is unspecified. Solaris `make` for instance replaces it with the empty string. OpenBSD (3.0 and later) `make` diagnoses these uses and errors out.

11.2 Failure in Make Rules

Since 1992 Posix has required that `make` must invoke each command with the equivalent of a '`sh -c`' subshell. However, many `make` implementations, including BSD make through 2004, use '`sh -e -c`' instead, and the '`-e`' option causes the subshell to exit immediately if a subsidiary simple-command fails. For example, the command '`touch T; rm -f U`' always attempts to remove '`U`' with Posix make, but incompatible `make` implementations skip the `rm` if the `touch` fails. One way to work around this is to reword the affected simple-commands so that they always succeed, e.g., '`touch T || :; rm -f U`'. However, even this approach can run into common bugs in BSD implementations of the '`-e`' option of `sh` and `set` (see Section 10.10 [Limitations of Builtins], page 150), so if you are worried about porting to buggy BSD shells it may be simpler to migrate complicated `make` actions into separate scripts.

11.3 Special Characters in Make Macro Names

Posix limits macro names to nonempty strings containing only ASCII letters and digits, '`.`', and '`_`'. Many `make` implementations allow a wider variety of characters, but portable makefiles should avoid them. It is portable to start a name with a special character, e.g., '`$(.FOO)`'.

Some ancient `make` implementations don't support leading underscores in macro names. An example is NEWS-OS 4.2R.

```
$ cat Makefile
_am_include = #
_am_quote =
all:; @echo this is test
$ make
Make: Must be a separator on rules line 2.  Stop.
$ cat Makefile2
am_include = #
am_quote =
all:; @echo this is test
$ make -f Makefile2
this is test
```

However, this problem is no longer of practical concern.

11.4 Backslash-Newline-Newline in Make Macro Values

On some versions of HP-UX, `make` reads multiple newlines following a backslash, continuing to the next non-empty line. For example,

```
FOO = one \

BAR = two

test:
        : FOO is "$(FOO)"
        : BAR is "$(BAR)"
```

shows `FOO` equal to `one BAR = two`. Other implementations sensibly let a backslash continue only to the immediately following line.

11.5 Backslash-Newline in Make Comments

According to Posix, Make comments start with `#` and continue until an unescaped newline is reached.

```
$ cat Makefile
# A = foo \
      bar \
      baz

all:
        @echo ok
$ make   # GNU make
ok
```

However this is not always the case. Some implementations discard everything from `#` through the end of the line, ignoring any trailing backslash.

```
$ pmake  # BSD make
"Makefile", line 3: Need an operator
Fatal errors encountered -- cannot continue
```

Therefore, if you want to comment out a multi-line definition, prefix each line with `#`, not only the first.

```
# A = foo \
#     bar \
#     baz
```

11.6 Long Lines in Makefiles

OSF/1 4.0d's `make` cannot process makefiles with lines longer than 38912 bytes. It exits with a `Line too long` diagnostic. A later version, Tru64 5.1's `make` has been reported to crash with lines around 20 kB.

11.7 `make macro=value` and Submakes

A command-line variable definition such as `foo=bar` overrides any definition of `foo` in a makefile. Some `make` implementations (such as GNU `make`) propagate this override to

subsidiary invocations of `make`. Some other implementations do not pass the substitution along to submakes.

```
$ cat Makefile
foo = foo
one:
        @echo $(foo)
        $(MAKE) two
two:
        @echo $(foo)
$ make foo=bar            # GNU make 3.79.1
bar
make two
make[1]: Entering directory ‘/home/adl’
bar
make[1]: Leaving directory ‘/home/adl’
$ pmake foo=bar           # BSD make
bar
pmake two
foo
```

You have a few possibilities if you do want the `foo=bar` override to propagate to submakes. One is to use the ‘`-e`’ option, which causes all environment variables to have precedence over the makefile macro definitions, and declare foo as an environment variable:

```
$ env foo=bar make -e
```

The ‘`-e`’ option is propagated to submakes automatically, and since the environment is inherited between `make` invocations, the `foo` macro is overridden in submakes as expected.

This syntax (`foo=bar make -e`) is portable only when used outside of a makefile, for instance from a script or from the command line. When run inside a `make` rule, GNU `make` 3.80 and prior versions forget to propagate the ‘`-e`’ option to submakes.

Moreover, using ‘`-e`’ could have unexpected side effects if your environment contains some other macros usually defined by the makefile. (See also the note about `make -e` and `SHELL` below.)

Another way to propagate overrides to submakes is to do it manually, from your makefile:

```
foo = foo
one:
        @echo $(foo)
        $(MAKE) foo=$(foo) two
two:
        @echo $(foo)
```

You need to foresee all macros that a user might want to override if you do that.

11.8 The Make Macro MAKEFLAGS

Posix requires `make` to use `MAKEFLAGS` to affect the current and recursive invocations of make, but allows implementations several formats for the variable. It is tricky to parse `$MAKEFLAGS` to determine whether ‘`-s`’ for silent execution or ‘`-k`’ for continued execution are

in effect. For example, you cannot assume that the first space-separated word in `$MAKEFLAGS` contains single-letter options, since in the Cygwin version of GNU `make` it is either '`--unix`' or '`--win32`' with the second word containing single-letter options.

```
$ cat Makefile
all:
        @echo MAKEFLAGS = $(MAKEFLAGS)
$ make
MAKEFLAGS = --unix
$ make -k
MAKEFLAGS = --unix -k
```

11.9 The Make Macro SHELL

Posix-compliant `make` internally uses the `$(SHELL)` macro to spawn shell processes and execute Make rules. This is a builtin macro supplied by `make`, but it can be modified by a makefile or by a command-line argument.

Not all `make` implementations define this `SHELL` macro. OSF/Tru64 `make` is an example; this implementation always uses `/bin/sh`. So it's a good idea to always define `SHELL` in your makefiles. If you use Autoconf, do

```
SHELL = @SHELL@
```

Do not force `SHELL = /bin/sh` because that is not correct everywhere. For instance DJGPP lacks `/bin/sh`, and when its GNU `make` port sees such a setting it enters a special emulation mode where features like pipes and redirections are emulated on top of DOS's `command.com`. Unfortunately this emulation is incomplete; for instance it does not handle command substitutions. On DJGPP `SHELL` should point to Bash.

Posix-compliant `make` should never acquire the value of $(SHELL) from the environment, even when `make -e` is used (otherwise, think about what would happen to your rules if `SHELL=/bin/tcsh`).

However not all `make` implementations have this exception. For instance it's not surprising that OSF/Tru64 `make` doesn't protect `SHELL`, since it doesn't use it.

```
$ cat Makefile
SHELL = /bin/sh
FOO = foo
all:
        @echo $(SHELL)
        @echo $(FOO)
$ env SHELL=/bin/tcsh FOO=bar make -e   # OSF1 V4.0 Make
/bin/tcsh
bar
$ env SHELL=/bin/tcsh FOO=bar gmake -e  # GNU make
/bin/sh
bar
```

11.10 Comments in Make Rules

Never put comments in a rule.

Some `make` treat anything starting with a tab as a command for the current rule, even if the tab is immediately followed by a `#`. The `make` from Tru64 Unix V5.1 is one of them. The following makefile runs `# foo` through the shell.

```
all:
        # foo
```

11.11 The 'obj/' Subdirectory and Make

Never name one of your subdirectories 'obj/' if you don't like surprises.

If an 'obj/' directory exists, BSD `make` enters it before reading the makefile. Hence the makefile in the current directory is not read.

```
$ cat Makefile
all:
        echo Hello
$ cat obj/Makefile
all:
        echo World
$ make      # GNU make
echo Hello
Hello
$ pmake     # BSD make
echo World
World
```

11.12 Exit Status of `make -k`

Do not rely on the exit status of `make -k`. Some implementations reflect whether they encountered an error in their exit status; other implementations always succeed.

```
$ cat Makefile
all:
        false
$ make -k; echo exit status: $?    # GNU make
false
make: *** [all] Error 1
exit status: 2
$ pmake -k; echo exit status: $?   # BSD make
false
*** Error code 1 (continuing)
exit status: 0
```

11.13 `VPATH` and Make

Posix does not specify the semantics of `VPATH`. Typically, `make` supports `VPATH`, but its implementation is not consistent.

Autoconf and Automake support makefiles whose usages of `VPATH` are portable to recent-enough popular implementations of `make`, but to keep the resulting makefiles portable, a package's makefile prototypes must take the following issues into account. These issues are

complicated and are often poorly understood, and installers who use `VPATH` should expect to find many bugs in this area. If you use `VPATH`, the simplest way to avoid these portability bugs is to stick with GNU `make`, since it is the most commonly-used `make` among Autoconf users.

Here are some known issues with some `VPATH` implementations.

11.13.1 `VPATH` and Double-colon Rules

With ancient versions of Sun `make`, any assignment to `VPATH` causes `make` to execute only the first set of double-colon rules. However, this problem is no longer of practical concern.

11.13.2 `$<` Not Supported in Explicit Rules

Using `$<` in explicit rules is not portable. The prerequisite file must be named explicitly in the rule. If you want to find the prerequisite via a `VPATH` search, you have to code the whole thing manually. See Section 4.7.4 [Build Directories], page 29.

11.13.3 Automatic Rule Rewriting

Some `make` implementations, such as Solaris `make` and OSF1/Tru64 `make`, search for prerequisites in `VPATH` and then rewrite each occurrence as a plain word in the rule. For instance:

```
# This isn't portable to GNU make.
VPATH = ../pkg/src
f.c: if.c
        cp if.c f.c
```

executes `cp ../pkg/src/if.c f.c` if '`if.c`' is found in '`../pkg/src`'.

However, this rule leads to real problems in practice. For example, if the source directory contains an ordinary file named '`test`' that is used in a dependency, Solaris `make` rewrites commands like '`if test -r foo; ...`' to '`if ../pkg/src/test -r foo; ...`', which is typically undesirable. To avoid this problem, portable makefiles should never mention a source file whose name is that of a shell keyword like '`until`' or a shell command like `cat` or `gcc` or `test`.

Because of these problems GNU `make` and many other `make` implementations do not rewrite commands, so portable makefiles should search `VPATH` manually. It is tempting to write this:

```
# This isn't portable to Solaris make.
VPATH = ../pkg/src
f.c: if.c
       cp `test -f if.c || echo $(VPATH)/`if.c f.c
```

However, the "prerequisite rewriting" still applies here. So if '`if.c`' is in '`../pkg/src`', Solaris `make` and OSF1/Tru64 `make` executes

```
cp `test -f ../pkg/src/if.c || echo ../pkg/src/`if.c f.c
```

which reduces to

```
cp if.c f.c
```

and thus fails. Oops.

A simple workaround, and good practice anyway, is to use '`$?`' and '`$@`' when possible:

```
VPATH = ../pkg/src
f.c: if.c
        cp $? $@
```

but this does not generalize well to commands with multiple prerequisites. A more general workaround is to rewrite the rule so that the prerequisite '`if.c`' never appears as a plain word. For example, these three rules would be safe, assuming '`if.c`' is in '`../pkg/src`' and the other files are in the working directory:

```
VPATH = ../pkg/src
f.c: if.c f1.c
        cat `test -f ./if.c || echo $(VPATH)/`if.c f1.c >$@
g.c: if.c g1.c
        cat `test -f 'if.c' || echo $(VPATH)/`if.c g1.c >$@
h.c: if.c h1.c
        cat `test -f "if.c" || echo $(VPATH)/`if.c h1.c >$@
```

Things get worse when your prerequisites are in a macro.

```
VPATH = ../pkg/src
HEADERS = f.h g.h h.h
install-HEADERS: $(HEADERS)
        for i in $(HEADERS); do \
          $(INSTALL) -m 644 \
            `test -f $$i || echo $(VPATH)/`$$i \
            $(DESTDIR)$(includedir)/$$i; \
        done
```

The above `install-HEADERS` rule is not Solaris-proof because `for i in $(HEADERS);` is expanded to `for i in f.h g.h h.h;` where `f.h` and `g.h` are plain words and are hence subject to `VPATH` adjustments.

If the three files are in '`../pkg/src`', the rule is run as:

```
for i in ../pkg/src/f.h ../pkg/src/g.h h.h; do \
  install -m 644 \
     `test -f $i || echo ../pkg/src/`$i \
     /usr/local/include/$i; \
done
```

where the two first `install` calls fail. For instance, consider the `f.h` installation:

```
install -m 644 \
  `test -f ../pkg/src/f.h || \
    echo ../pkg/src/ \
  `../pkg/src/f.h \
  /usr/local/include/../pkg/src/f.h;
```

It reduces to:

```
install -m 644 \
  ../pkg/src/f.h \
  /usr/local/include/../pkg/src/f.h;
```

Note that the manual `VPATH` search did not cause any problems here; however this command installs '`f.h`' in an incorrect directory.

Trying to quote `$(HEADERS)` in some way, as we did for `foo.c` a few makefiles ago, does not help:

```
install-HEADERS: $(HEADERS)
        headers='$(HEADERS)'; \
        for i in $$headers; do \
          $(INSTALL) -m 644 \
            `test -f $$i || echo $(VPATH)/`$$i \
            $(DESTDIR)$(includedir)/$$i; \
        done
```

Now, `headers='$(HEADERS)'` macroexpands to:

```
headers='f.h g.h h.h'
```

but `g.h` is still a plain word. (As an aside, the idiom `headers='$(HEADERS)'; for i in $$headers;` is a good idea if `$(HEADERS)` can be empty, because some shells diagnose a syntax error on `for i in;`.)

One workaround is to strip this unwanted '`../pkg/src/`' prefix manually:

```
VPATH = ../pkg/src
HEADERS = f.h g.h h.h
install-HEADERS: $(HEADERS)
        headers='$(HEADERS)'; \
        for i in $$headers; do \
          i=`expr "$$i" : '$(VPATH)/\(.*\)'`; \
          $(INSTALL) -m 644 \
            `test -f $$i || echo $(VPATH)/`$$i \
            $(DESTDIR)$(includedir)/$$i; \
        done
```

Automake does something similar. However the above hack works only if the files listed in `HEADERS` are in the current directory or a subdirectory; they should not be in an enclosing directory. If we had `HEADERS = ../f.h`, the above fragment would fail in a VPATH build with OSF1/Tru64 `make`. The reason is that not only does OSF1/Tru64 `make` rewrite dependencies, but it also simplifies them. Hence `../f.h` becomes `../pkg/f.h` instead of `../pkg/src/../f.h`. This obviously defeats any attempt to strip a leading '`../pkg/src/`' component.

The following example makes the behavior of OSF1/Tru64 `make` more apparent.

```
$ cat Makefile
VPATH = sub
all: ../foo
        echo ../foo
$ ls
Makefile foo
$ make
echo foo
foo
```

Dependency '`../foo`' was found in '`sub/../foo`', but OSF1/Tru64 `make` simplified it as '`foo`'. (Note that the '`sub/`' directory does not even exist, this just means that the simplification occurred before the file was checked for.)

For the record here is how SunOS 4 `make` behaves on this example.

```
$ make
make: Fatal error: Don't know how to make target `../foo'
$ mkdir sub
$ make
echo sub/../foo
sub/../foo
```

11.13.4 OSF/Tru64 `make` Creates Prerequisite Directories Magically

When a prerequisite is a subdirectory of `VPATH`, Tru64 `make` creates it in the current directory.

```
$ mkdir -p foo/bar build
$ cd build
$ cat >Makefile <<END
VPATH = ..
all: foo/bar
END
$ make
mkdir foo
mkdir foo/bar
```

This can yield unexpected results if a rule uses a manual `VPATH` search as presented before.

```
VPATH = ..
all : foo/bar
        command `test -d foo/bar || echo ../`foo/bar
```

The above `command` is run on the empty '`foo/bar`' directory that was created in the current directory.

11.13.5 Make Target Lookup

GNU `make` uses a complex algorithm to decide when it should use files found via a `VPATH` search. See section "How Directory Searches are Performed" in *The GNU Make Manual*.

If a target needs to be rebuilt, GNU `make` discards the file name found during the `VPATH` search for this target, and builds the file locally using the file name given in the makefile. If a target does not need to be rebuilt, GNU `make` uses the file name found during the `VPATH` search.

Other `make` implementations, like NetBSD `make`, are easier to describe: the file name found during the `VPATH` search is used whether the target needs to be rebuilt or not. Therefore new files are created locally, but existing files are updated at their `VPATH` location.

OpenBSD and FreeBSD `make`, however, never perform a `VPATH` search for a dependency that has an explicit rule. This is extremely annoying.

When attempting a `VPATH` build for an autoconfiscated package (e.g., `mkdir build && cd build && ../configure`), this means GNU `make` builds everything locally in the '`build`' directory, while BSD `make` builds new files locally and updates existing files in the source directory.

```
$ cat Makefile
VPATH = ..
```

```
all: foo.x bar.x
foo.x bar.x: newer.x
        @echo Building $@
$ touch ../bar.x
$ touch ../newer.x
$ make        # GNU make
Building foo.x
Building bar.x
$ pmake       # NetBSD make
Building foo.x
Building ../bar.x
$ fmake       # FreeBSD make, OpenBSD make
Building foo.x
Building bar.x
$ tmake       # Tru64 make
Building foo.x
Building bar.x
$ touch ../bar.x
$ make        # GNU make
Building foo.x
$ pmake       # NetBSD make
Building foo.x
$ fmake       # FreeBSD make, OpenBSD make
Building foo.x
Building bar.x
$ tmake       # Tru64 make
Building foo.x
Building bar.x
```

Note how NetBSD `make` updates '`../bar.x`' in its VPATH location, and how FreeBSD, OpenBSD, and Tru64 `make` always update '`bar.x`', even when '`../bar.x`' is up to date.

Another point worth mentioning is that once GNU `make` has decided to ignore a `VPATH` file name (e.g., it ignored '`../bar.x`' in the above example) it continues to ignore it when the target occurs as a prerequisite of another rule.

The following example shows that GNU `make` does not look up '`bar.x`' in `VPATH` before performing the `.x.y` rule, because it ignored the `VPATH` result of '`bar.x`' while running the `bar.x: newer.x` rule.

```
$ cat Makefile
VPATH = ..
all: bar.y
bar.x: newer.x
        @echo Building $@
.SUFFIXES: .x .y
.x.y:
        cp $< $@
$ touch ../bar.x
$ touch ../newer.x
```

```
$ make        # GNU make
Building bar.x
cp bar.x bar.y
cp: cannot stat ‘bar.x’: No such file or directory
make: *** [bar.y] Error 1
$ pmake       # NetBSD make
Building ../bar.x
cp ../bar.x bar.y
$ rm bar.y
$ fmake       # FreeBSD make, OpenBSD make
echo Building bar.x
cp bar.x bar.y
cp: cannot stat ‘bar.x’: No such file or directory
*** Error code 1
$ tmake       # Tru64 make
Building bar.x
cp: bar.x: No such file or directory
*** Exit 1
```

Note that if you drop away the command from the `bar.x: newer.x` rule, GNU `make` magically starts to work: it knows that `bar.x` hasn't been updated, therefore it doesn't discard the result from `VPATH` (‘`../bar.x`’) in succeeding uses. Tru64 also works, but FreeBSD and OpenBSD still don't.

```
$ cat Makefile
VPATH = ..
all: bar.y
bar.x: newer.x
.SUFFIXES: .x .y
.x.y:
        cp $< $@
$ touch ../bar.x
$ touch ../newer.x
$ make        # GNU make
cp ../bar.x bar.y
$ rm bar.y
$ pmake       # NetBSD make
cp ../bar.x bar.y
$ rm bar.y
$ fmake       # FreeBSD make, OpenBSD make
cp bar.x bar.y
cp: cannot stat ‘bar.x’: No such file or directory
*** Error code 1
$ tmake       # Tru64 make
cp ../bar.x bar.y
```

It seems the sole solution that would please every `make` implementation is to never rely on `VPATH` searches for targets. In other words, `VPATH` should be reserved to unbuilt sources.

11.14 Single Suffix Rules and Separated Dependencies

A *Single Suffix Rule* is basically a usual suffix (inference) rule (‘`.from.to:`’), but which *destination* suffix is empty (‘`.from:`’).

Separated dependencies simply refers to listing the prerequisite of a target, without defining a rule. Usually one can list on the one hand side, the rules, and on the other hand side, the dependencies.

Solaris `make` does not support separated dependencies for targets defined by single suffix rules:

```
$ cat Makefile
.SUFFIXES: .in
foo: foo.in
.in:
        cp $< $@
$ touch foo.in
$ make
$ ls
Makefile  foo.in
```

while GNU Make does:

```
$ gmake
cp foo.in foo
$ ls
Makefile  foo       foo.in
```

Note it works without the ‘`foo: foo.in`’ dependency.

```
$ cat Makefile
.SUFFIXES: .in
.in:
        cp $< $@
$ make foo
cp foo.in foo
```

and it works with double suffix inference rules:

```
$ cat Makefile
foo.out: foo.in
.SUFFIXES: .in .out
.in.out:
        cp $< $@
$ make
cp foo.in foo.out
```

As a result, in such a case, you have to write target rules.

11.15 Timestamp Resolution and Make

Traditionally, file timestamps had 1-second resolution, and `make` used those timestamps to determine whether one file was newer than the other. However, many modern file systems have timestamps with 1-nanosecond resolution. Some `make` implementations look at the entire timestamp; others ignore the fractional part, which can lead to incorrect results.

Normally this is not a problem, but in some extreme cases you may need to use tricks like '`sleep 1`' to work around timestamp truncation bugs.

Commands like '`cp -p`' and '`touch -r`' typically do not copy file timestamps to their full resolutions (see Section 10.11 [Limitations of Usual Tools], page 158). Hence you should be wary of rules like this:

```
dest: src
        cp -p src dest
```

as '`dest`' often appears to be older than '`src`' after the timestamp is truncated, and this can cause `make` to do needless rework the next time it is invoked. To work around this problem, you can use a timestamp file, e.g.:

```
dest-stamp: src
        cp -p src dest
        date >dest-stamp
```

12 Portable C and C++ Programming

C and C++ programs often use low-level features of the underlying system, and therefore are often more difficult to make portable to other platforms.

Several standards have been developed to help make your programs more portable. If you write programs with these standards in mind, you can have greater confidence that your programs work on a wide variety of systems. See section "Language Standards Supported by GCC" in *Using the GNU Compiler Collection (GCC)*, for a list of C-related standards. Many programs also assume the Posix standard (`http://www.opengroup.org/susv3`).

Some old code is written to be portable to K&R C, which predates any C standard. K&R C compilers are no longer of practical interest, though, and the rest of section assumes at least C89, the first C standard.

Program portability is a huge topic, and this section can only briefly introduce common pitfalls. See section "Portability between System Types" in *GNU Coding Standards*, for more information.

12.1 Varieties of Unportability

Autoconf tests and ordinary programs often need to test what is allowed on a system, and therefore they may need to deliberately exceed the boundaries of what the standards allow, if only to see whether an optional feature is present. When you write such a program, you should keep in mind the difference between constraints, unspecified behavior, and undefined behavior.

In C, a *constraint* is a rule that the compiler must enforce. An example constraint is that C programs must not declare a bit-field with negative width. Tests can therefore reliably assume that programs with negative-width bit-fields are rejected by a compiler that conforms to the standard.

Unspecified behavior is valid behavior, where the standard allows multiple possibilities. For example, the order of evaluation of function arguments is unspecified. Some unspecified behavior is *implementation-defined*, i.e., documented by the implementation, but since Autoconf tests cannot read the documentation they cannot distinguish between implementation-defined and other unspecified behavior. It is common for Autoconf tests to probe implementations to determine otherwise-unspecified behavior.

Undefined behavior is invalid behavior, where the standard allows the implementation to do anything it pleases. For example, dereferencing a null pointer leads to undefined behavior. If possible, test programs should avoid undefined behavior, since a program with undefined behavior might succeed on a test that should fail.

The above rules apply to programs that are intended to conform to the standard. However, strictly-conforming programs are quite rare, since the standards are so limiting. A major goal of Autoconf is to support programs that use implementation features not described by the standard, and it is fairly common for test programs to violate the above rules, if the programs work well enough in practice.

12.2 Integer Overflow

In C, signed integer overflow leads to undefined behavior. However, many programs and Autoconf tests assume that signed integer overflow after addition, subtraction, or multiplication silently wraps around modulo a power of two, using two's complement arithmetic, so long as you cast the resulting value to an integer type or store it into an integer variable. Such programs are portable to the vast majority of modern platforms. However, signed integer division is not always harmless: for example, on CPUs of the i386 family, dividing `INT_MIN` by `-1` yields a SIGFPE signal which by default terminates the program. Worse, taking the remainder of these two values typically yields the same signal on these CPUs, even though the C standard requires `INT_MIN % -1` to yield zero because the expression does not overflow.

GCC users might consider using the '`-ftrapv`' option if they are worried about porting their code to the rare platforms where signed integer overflow does not wrap around after addition, subtraction, or multiplication.

Unsigned integer overflow reliably wraps around modulo the word size. This is guaranteed by the C standard and is portable in practice.

12.3 Properties of Null Pointers

Most modern hosts reliably fail when you attempt to dereference a null pointer.

On almost all modern hosts, null pointers use an all-bits-zero internal representation, so you can reliably use `memset` with 0 to set all the pointers in an array to null values.

If `p` is a null pointer to an object type, the C expression `p + 0` always evaluates to `p` on modern hosts, even though the standard says that it has undefined behavior.

12.4 Buffer Overruns and Subscript Errors

Buffer overruns and subscript errors are the most common dangerous errors in C programs. They result in undefined behavior because storing outside an array typically modifies storage that is used by some other object, and most modern systems lack runtime checks to catch these errors. Programs should not rely on buffer overruns being caught.

There is one exception to the usual rule that a portable program cannot address outside an array. In C, it is valid to compute the address just past an object, e.g., `&a[N]` where `a` has `N` elements, so long as you do not dereference the resulting pointer. But it is not valid to compute the address just before an object, e.g., `&a[-1]`; nor is it valid to compute two past the end, e.g., `&a[N+1]`. On most platforms `&a[-1] < &a[0] && &a[N] < &a[N+1]`, but this is not reliable in general, and it is usually easy enough to avoid the potential portability problem, e.g., by allocating an extra unused array element at the start or end.

Valgrind (`http://valgrind.org/`) can catch many overruns. GCC users might also consider using the '`-fmudflap`' option to catch overruns.

Buffer overruns are usually caused by off-by-one errors, but there are more subtle ways to get them.

Using `int` values to index into an array or compute array sizes causes problems on typical 64-bit hosts where an array index might be 2^31 or larger. Index values of type `size_t` avoid this problem, but cannot be negative. Index values of type `ptrdiff_t` are signed, and are wide enough in practice.

If you add or multiply two numbers to calculate an array size, e.g., `malloc (x * sizeof y + z)`, havoc ensues if the addition or multiplication overflows.

Many implementations of the `alloca` function silently misbehave and can generate buffer overflows if given sizes that are too large. The size limits are implementation dependent, but are at least 4000 bytes on all platforms that we know about.

The standard functions `asctime`, `asctime_r`, `ctime`, `ctime_r`, and `gets` are prone to buffer overflows, and portable code should not use them unless the inputs are known to be within certain limits. The time-related functions can overflow their buffers if given timestamps out of range (e.g., a year less than -999 or greater than 9999). Time-related buffer overflows cannot happen with recent-enough versions of the GNU C library, but are possible with other implementations. The `gets` function is the worst, since it almost invariably overflows its buffer when presented with an input line larger than the buffer.

12.5 Floating Point Portability

Almost all modern systems use IEEE-754 floating point, and it is safe to assume IEEE-754 in most portable code these days. For more information, please see David Goldberg's classic paper What Every Computer Scientist Should Know About Floating-Point Arithmetic (`http://www.validlab.com/goldberg/paper.pdf`).

12.6 Exiting Portably

A C or C++ program can exit with status N by returning N from the `main` function. Portable programs are supposed to exit either with status 0 or `EXIT_SUCCESS` to succeed, or with status `EXIT_FAILURE` to fail, but in practice it is portable to fail by exiting with status 1, and test programs that assume Posix can fail by exiting with status values from 1 through 255. Programs on SunOS 2.0 (1985) through 3.5.2 (1988) incorrectly exited with zero status when `main` returned nonzero, but ancient systems like these are no longer of practical concern.

A program can also exit with status N by passing N to the `exit` function, and a program can fail by calling the `abort` function. If a program is specialized to just some platforms, it can fail by calling functions specific to those platforms, e.g., `_exit` (Posix) and `_Exit` (C99). However, like other functions, an exit function should be declared, typically by including a header. For example, if a C program calls `exit`, it should include '`stdlib.h`' either directly or via the default includes (see Section 5.1.2 [Default Includes], page 39).

A program can fail due to undefined behavior such as dereferencing a null pointer, but this is not recommended as undefined behavior allows an implementation to do whatever it pleases and this includes exiting successfully.

13 Manual Configuration

A few kinds of features can't be guessed automatically by running test programs. For example, the details of the object-file format, or special options that need to be passed to the compiler or linker. You can check for such features using ad-hoc means, such as having `configure` check the output of the `uname` program, or looking for libraries that are unique to particular systems. However, Autoconf provides a uniform method for handling unguessable features.

13.1 Specifying the System Type

Like other GNU `configure` scripts, Autoconf-generated `configure` scripts can make decisions based on a canonical name for the system type, which has the form: '*cpu-vendor-os*', where *os* can be '*system*' or '*kernel-system*'

`configure` can usually guess the canonical name for the type of system it's running on. To do so it runs a script called `config.guess`, which infers the name using the `uname` command or symbols predefined by the C preprocessor.

Alternately, the user can specify the system type with command line arguments to `configure`. Doing so is necessary when cross-compiling. In the most complex case of cross-compiling, three system types are involved. The options to specify them are:

'`--build=`*build-type*'
: the type of system on which the package is being configured and compiled. It defaults to the result of running `config.guess`.

'`--host=`*host-type*'
: the type of system on which the package runs. By default it is the same as the build machine. Specifying it enables the cross-compilation mode.

'`--target=`*target-type*'
: the type of system for which any compiler tools in the package produce code (rarely needed). By default, it is the same as host.

If you mean to override the result of `config.guess`, use '`--build`', not '`--host`', since the latter enables cross-compilation. For historical reasons, passing '`--host`' also changes the build type. Therefore, whenever you specify '`--host`', be sure to specify '`--build`' too; this will be fixed in the future. So, to enter cross-compilation mode, use a command like this

```
./configure --build=i686-pc-linux-gnu --host=m68k-coff
```

Note that if you do not specify '`--host`', `configure` fails if it can't run the code generated by the specified compiler. For example, configuring as follows fails:

```
./configure CC=m68k-coff-gcc
```

In the future, when cross-compiling Autoconf will *not* accept tools (compilers, linkers, assemblers) whose name is not prefixed with the host type. The only case when this may be useful is when you really are not cross-compiling, but only building for a least-common-denominator architecture: an example is building for `i386-pc-linux-gnu` while running on an `i686-pc-linux-gnu` architecture. In this case, some particular pairs might be similar enough to let you get away with the system compilers, but in general the compiler might

make bogus assumptions on the host: if you know what you are doing, please create symbolic links from the host compiler to the build compiler.

`configure` recognizes short aliases for many system types; for example, '`decstation`' can be used instead of '`mips-dec-ultrix4.2`'. `configure` runs a script called `config.sub` to canonicalize system type aliases.

This section deliberately omits the description of the obsolete interface; see Section 17.6.3 [Hosts and Cross-Compilation], page 224.

13.2 Getting the Canonical System Type

The following macros make the system type available to `configure` scripts.

The variables '`build_alias`', '`host_alias`', and '`target_alias`' are always exactly the arguments of '`--build`', '`--host`', and '`--target`'; in particular, they are left empty if the user did not use them, even if the corresponding `AC_CANONICAL` macro was run. Any configure script may use these variables anywhere. These are the variables that should be used when in interaction with the user.

If you need to recognize some special environments based on their system type, run the following macros to get canonical system names. These variables are not set before the macro call.

If you use these macros, you must distribute `config.guess` and `config.sub` along with your source code. See Section 4.4 [Output], page 19, for information about the `AC_CONFIG_AUX_DIR` macro which you can use to control in which directory `configure` looks for those scripts.

`AC_CANONICAL_BUILD` [Macro]

Compute the canonical build-system type variable, `build`, and its three individual parts `build_cpu`, `build_vendor`, and `build_os`.

If '`--build`' was specified, then `build` is the canonicalization of `build_alias` by `config.sub`, otherwise it is determined by the shell script `config.guess`.

`AC_CANONICAL_HOST` [Macro]

Compute the canonical host-system type variable, `host`, and its three individual parts `host_cpu`, `host_vendor`, and `host_os`.

If '`--host`' was specified, then `host` is the canonicalization of `host_alias` by `config.sub`, otherwise it defaults to `build`.

`AC_CANONICAL_TARGET` [Macro]

Compute the canonical target-system type variable, `target`, and its three individual parts `target_cpu`, `target_vendor`, and `target_os`.

If '`--target`' was specified, then `target` is the canonicalization of `target_alias` by `config.sub`, otherwise it defaults to `host`.

Note that there can be artifacts due to the backward compatibility code. See See Section 17.6.3 [Hosts and Cross-Compilation], page 224, for more.

13.3 Using the System Type

In '`configure.ac`' the system type is generally used by one or more `case` statements to select system-specifics. Shell wildcards can be used to match a group of system types.

For example, an extra assembler code object file could be chosen, giving access to a CPU cycle counter register. `$(CYCLE_OBJ)` in the following would be used in a makefile to add the object to a program or library.

```
case $host in
  alpha*-*-*) CYCLE_OBJ=rpcc.o ;;
  i?86-*-*)   CYCLE_OBJ=rdtsc.o ;;
  *)          CYCLE_OBJ= ;;
esac
AC_SUBST([CYCLE_OBJ])
```

`AC_CONFIG_LINKS` (see Section 4.10 [Configuration Links], page 36) is another good way to select variant source files, for example optimized code for some CPUs. The configured CPU type doesn't always indicate exact CPU types, so some runtime capability checks may be necessary too.

```
case $host in
  alpha*-*-*)   AC_CONFIG_LINKS([dither.c:alpha/dither.c]) ;;
  powerpc*-*-*) AC_CONFIG_LINKS([dither.c:powerpc/dither.c]) ;;
  *-*-*)        AC_CONFIG_LINKS([dither.c:generic/dither.c]) ;;
esac
```

The host system type can also be used to find cross-compilation tools with `AC_CHECK_TOOL` (see Section 5.2.2 [Generic Programs], page 43).

The above examples all show '`$host`', since this is where the code is going to run. Only rarely is it necessary to test '`$build`' (which is where the build is being done).

Whenever you're tempted to use '`$host`' it's worth considering whether some sort of probe would be better. New system types come along periodically or previously missing features are added. Well-written probes can adapt themselves to such things, but hard-coded lists of names can't. Here are some guidelines,

- Availability of libraries and library functions should always be checked by probing.
- Variant behavior of system calls is best identified with runtime tests if possible, but bug workarounds or obscure difficulties might have to be driven from '`$host`'.
- Assembler code is inevitably highly CPU-specific and is best selected according to '`$host_cpu`'.
- Assembler variations like underscore prefix on globals or ELF versus COFF type directives are however best determined by probing, perhaps even examining the compiler output.

'`$target`' is for use by a package creating a compiler or similar. For ordinary packages it's meaningless and should not be used. It indicates what the created compiler should generate code for, if it can cross-compile. '`$target`' generally selects various hard-coded CPU and system conventions, since usually the compiler or tools under construction themselves determine how the target works.

14 Site Configuration

`configure` scripts support several kinds of local configuration decisions. There are ways for users to specify where external software packages are, include or exclude optional features, install programs under modified names, and set default values for `configure` options.

14.1 Controlling Help Output

Users consult '`configure --help`' to learn of configuration decisions specific to your package. By default, `configure` breaks this output into sections for each type of option; within each section, help strings appear in the order '`configure.ac`' defines them:

```
Optional Features:
  ...
  --enable-bar            include bar

Optional Packages:
  ...
  --with-foo              use foo
```

`AC_PRESERVE_HELP_ORDER` [Macro]

Request an alternate '`--help`' format, in which options of all types appear together, in the order defined. Call this macro before any `AC_ARG_ENABLE` or `AC_ARG_WITH`.

```
Optional Features and Packages:
  ...
  --enable-bar            include bar
  --with-foo              use foo
```

14.2 Working With External Software

Some packages require, or can optionally use, other software packages that are already installed. The user can give `configure` command line options to specify which such external software to use. The options have one of these forms:

`--with-`*package*`[=`*arg*`]`
`--without-`*package*

For example, '`--with-gnu-ld`' means work with the GNU linker instead of some other linker. '`--with-x`' means work with The X Window System.

The user can give an argument by following the package name with '`=`' and the argument. Giving an argument of '`no`' is for packages that are used by default; it says to *not* use the package. An argument that is neither '`yes`' nor '`no`' could include a name or number of a version of the other package, to specify more precisely which other package this program is supposed to work with. If no argument is given, it defaults to '`yes`'. '`--without-`*package*' is equivalent to '`--with-`*package*`=no`'.

`configure` scripts do not complain about '`--with-`*package*' options that they do not support. This behavior permits configuring a source tree containing multiple packages with a top-level `configure` script when the packages support different options, without spurious error messages about options that some of the packages support. An unfortunate side effect

is that option spelling errors are not diagnosed. No better approach to this problem has been suggested so far.

For each external software package that may be used, '`configure.ac`' should call `AC_ARG_WITH` to detect whether the `configure` user asked to use it. Whether each package is used or not by default, and which arguments are valid, is up to you.

`AC_ARG_WITH` (*package*, *help-string*, [*action-if-given*], [*action-if-not-given*]) [Macro]

If the user gave `configure` the option '`--with-`*package*' or '`--without-`*package*', run shell commands *action-if-given*. If neither option was given, run shell commands *action-if-not-given*. The name *package* indicates another software package that this program should work with. It should consist only of alphanumeric characters and dashes.

The option's argument is available to the shell commands *action-if-given* in the shell variable `withval`, which is actually just the value of the shell variable `with_`*package*, with any '`-`' characters changed into '`_`'. You may use that variable instead, if you wish.

The argument *help-string* is a description of the option that looks like this:

```
--with-readline         support fancy command line editing
```

help-string may be more than one line long, if more detail is needed. Just make sure the columns line up in '`configure --help`'. Avoid tabs in the help string. You'll need to enclose the help string in '`[`' and '`]`' in order to produce the leading blanks.

You should format your *help-string* with the macro `AS_HELP_STRING` (see Section 14.4 [Pretty Help Strings], page 197).

The following example shows how to use the `AC_ARG_WITH` macro in a common situation. You want to let the user decide whether to enable support for an external library (e.g., the readline library); if the user specified neither '`--with-readline`' nor '`--without-readline`', you want to enable support for readline only if the library is available on the system.

```
AC_ARG_WITH([readline],
  [AS_HELP_STRING([--with-readline],
    [support fancy command line editing @<:@default=check@:>@])],
  [],
  [with_readline=check])

LIBREADLINE=
AS_IF([test "x$with_readline" != xno],
  [AC_CHECK_LIB([readline], [main],
    [AC_SUBST([LIBREADLINE], ["-lreadline -lncurses"])
     AC_DEFINE([HAVE_LIBREADLINE], [1],
               [Define if you have libreadline])
    ],
    [if test "x$with_readline" != xcheck; then
       AC_MSG_FAILURE(
         [--with-readline was given, but test for readline failed])
```

```
     fi
    ], -lncurses)])
```

The next example shows how to use `AC_ARG_WITH` to give the user the possibility to enable support for the readline library, in case it is still experimental and not well tested, and is therefore disabled by default.

```
AC_ARG_WITH([readline],
  [AS_HELP_STRING([--with-readline],
    [enable experimental support for readline])],
  [],
  [with_readline=no])

LIBREADLINE=
AS_IF([test "x$with_readline" != xno],
  [AC_CHECK_LIB([readline], [main],
    [AC_SUBST([LIBREADLINE], ["-lreadline -lncurses"])
     AC_DEFINE([HAVE_LIBREADLINE], [1],
               [Define if you have libreadline])
    ],
    [AC_MSG_FAILURE(
       [--with-readline was given, but test for readline failed])],
    [-lncurses])])
```

The last example shows how to use `AC_ARG_WITH` to give the user the possibility to disable support for the readline library, given that it is an important feature and that it should be enabled by default.

```
AC_ARG_WITH([readline],
  [AS_HELP_STRING([--without-readline],
    [disable support for readline])],
  [],
  [with_readline=yes])

LIBREADLINE=
AS_IF([test "x$with_readline" != xno],
  [AC_CHECK_LIB([readline], [main],
    [AC_SUBST([LIBREADLINE], ["-lreadline -lncurses"])
     AC_DEFINE([HAVE_LIBREADLINE], [1],
               [Define if you have libreadline])
    ],
    [AC_MSG_FAILURE(
       [readline test failed (--without-readline to disable)])],
    [-lncurses])])
```

These three examples can be easily adapted to the case where `AC_ARG_ENABLE` should be preferred to `AC_ARG_WITH` (see Section 14.3 [Package Options], page 196).

`AC_WITH` (*package*, *action-if-given*, [*action-if-not-given*]) [Macro]

This is an obsolete version of `AC_ARG_WITH` that does not support providing a help string.

14.3 Choosing Package Options

If a software package has optional compile-time features, the user can give `configure` command line options to specify whether to compile them. The options have one of these forms:

```
--enable-feature[=arg]
--disable-feature
```

These options allow users to choose which optional features to build and install. '`--enable-feature`' options should never make a feature behave differently or cause one feature to replace another. They should only cause parts of the program to be built rather than left out.

The user can give an argument by following the feature name with '`=`' and the argument. Giving an argument of '`no`' requests that the feature *not* be made available. A feature with an argument looks like '`--enable-debug=stabs`'. If no argument is given, it defaults to '`yes`'. '`--disable-feature`' is equivalent to '`--enable-feature=no`'.

`configure` scripts do not complain about '`--enable-feature`' options that they do not support. This behavior permits configuring a source tree containing multiple packages with a top-level `configure` script when the packages support different options, without spurious error messages about options that some of the packages support. An unfortunate side effect is that option spelling errors are not diagnosed. No better approach to this problem has been suggested so far.

For each optional feature, '`configure.ac`' should call `AC_ARG_ENABLE` to detect whether the `configure` user asked to include it. Whether each feature is included or not by default, and which arguments are valid, is up to you.

`AC_ARG_ENABLE` (*feature*, *help-string*, [*action-if-given*], [*action-if-not-given*]) [Macro]

If the user gave `configure` the option '`--enable-feature`' or '`--disable-feature`', run shell commands *action-if-given*. If neither option was given, run shell commands *action-if-not-given*. The name *feature* indicates an optional user-level facility. It should consist only of alphanumeric characters and dashes.

The option's argument is available to the shell commands *action-if-given* in the shell variable `enableval`, which is actually just the value of the shell variable `enable_feature`, with any '`-`' characters changed into '`_`'. You may use that variable instead, if you wish. The *help-string* argument is like that of `AC_ARG_WITH` (see Section 14.2 [External Software], page 193).

You should format your *help-string* with the macro `AS_HELP_STRING` (see Section 14.4 [Pretty Help Strings], page 197).

See the examples suggested with the definition of `AC_ARG_WITH` (see Section 14.2 [External Software], page 193) to get an idea of possible applications of `AC_ARG_ENABLE`.

`AC_ENABLE` (*feature*, *action-if-given*, [*action-if-not-given*]) [Macro]

This is an obsolete version of `AC_ARG_ENABLE` that does not support providing a help string.

14.4 Making Your Help Strings Look Pretty

Properly formatting the '`help strings`' which are used in `AC_ARG_WITH` (see Section 14.2 [External Software], page 193) and `AC_ARG_ENABLE` (see Section 14.3 [Package Options], page 196) can be challenging. Specifically, you want your own '`help strings`' to line up in the appropriate columns of '`configure --help`' just like the standard Autoconf '`help strings`' do. This is the purpose of the `AS_HELP_STRING` macro.

`AS_HELP_STRING` (*left-hand-side*, *right-hand-side*) [Macro]

Expands into an help string that looks pretty when the user executes '`configure --help`'. It is typically used in `AC_ARG_WITH` (see Section 14.2 [External Software], page 193) or `AC_ARG_ENABLE` (see Section 14.3 [Package Options], page 196). The following example makes this clearer.

```
AC_ARG_WITH([foo],
  [AS_HELP_STRING([--with-foo],
     [use foo (default is no)])],
  [use_foo=$withval],
  [use_foo=no])
```

The second argument of `AS_HELP_STRING` is not a literal, and should not be double quoted. See Section 3.1.2 [Autoconf Language], page 9, for a more detailed explanation. Then the last few lines of '`configure --help`' appear like this:

```
--enable and --with options recognized:
  --with-foo              use foo (default is no)
```

The `AS_HELP_STRING` macro is particularly helpful when the *left-hand-side* and/or *right-hand-side* are composed of macro arguments, as shown in the following example.

```
AC_DEFUN([MY_ARG_WITH],
  [AC_ARG_WITH([$1],
     [AS_HELP_STRING([--with-$1], [use $1 (default is $2)])],
     [use_[]$1=$withval],
     [use_[]$1=$2])])
```

14.5 Configuring Site Details

Some software packages require complex site-specific information. Some examples are host names to use for certain services, company names, and email addresses to contact. Since some configuration scripts generated by Metaconfig ask for such information interactively, people sometimes wonder how to get that information in Autoconf-generated configuration scripts, which aren't interactive.

Such site configuration information should be put in a file that is edited *only by users*, not by programs. The location of the file can either be based on the `prefix` variable, or be a standard location such as the user's home directory. It could even be specified by an environment variable. The programs should examine that file at runtime, rather than at compile time. Runtime configuration is more convenient for users and makes the configuration process simpler than getting the information while configuring. See section "Variables for Installation Directories" in *GNU Coding Standards*, for more information on where to put data files.

14.6 Transforming Program Names When Installing

Autoconf supports changing the names of programs when installing them. In order to use these transformations, '`configure.ac`' must call the macro `AC_ARG_PROGRAM`.

`AC_ARG_PROGRAM` [Macro]

Place in output variable `program_transform_name` a sequence of `sed` commands for changing the names of installed programs.

If any of the options described below are given to `configure`, program names are transformed accordingly. Otherwise, if `AC_CANONICAL_TARGET` has been called and a '`--target`' value is given, the target type followed by a dash is used as a prefix. Otherwise, no program name transformation is done.

14.6.1 Transformation Options

You can specify name transformations by giving `configure` these command line options:

'`--program-prefix=`*prefix*'
: prepend *prefix* to the names;

'`--program-suffix=`*suffix*'
: append *suffix* to the names;

'`--program-transform-name=`*expression*'
: perform `sed` substitution *expression* on the names.

14.6.2 Transformation Examples

These transformations are useful with programs that can be part of a cross-compilation development environment. For example, a cross-assembler running on a Sun 4 configured with '`--target=i960-vxworks`' is normally installed as '`i960-vxworks-as`', rather than '`as`', which could be confused with a native Sun 4 assembler.

You can force a program name to begin with '`g`', if you don't want GNU programs installed on your system to shadow other programs with the same name. For example, if you configure GNU `diff` with '`--program-prefix=g`', then when you run '`make install`' it is installed as '`/usr/local/bin/gdiff`'.

As a more sophisticated example, you could use

```
--program-transform-name='s/^/g/; s/^gg/g/; s/^gless/less/'
```

to prepend '`g`' to most of the program names in a source tree, excepting those like `gdb` that already have one and those like `less` and `lesskey` that aren't GNU programs. (That is assuming that you have a source tree containing those programs that is set up to use this feature.)

One way to install multiple versions of some programs simultaneously is to append a version number to the name of one or both. For example, if you want to keep Autoconf version 1 around for awhile, you can configure Autoconf version 2 using '`--program-suffix=2`' to install the programs as '`/usr/local/bin/autoconf2`', '`/usr/local/bin/autoheader2`', etc. Nevertheless, pay attention that only the binaries are renamed, therefore you'd have problems with the library files which might overlap.

14.6.3 Transformation Rules

Here is how to use the variable `program_transform_name` in a '`Makefile.in`':

```
PROGRAMS = cp ls rm
transform = @program_transform_name@
install:
        for p in $(PROGRAMS); do \
          $(INSTALL_PROGRAM) $$p $(DESTDIR)$(bindir)/`echo $$p | \
                                                sed '$(transform)'`; \
        done

uninstall:
        for p in $(PROGRAMS); do \
          rm -f $(DESTDIR)$(bindir)/`echo $$p | sed '$(transform)'`; \
        done
```

It is guaranteed that `program_transform_name` is never empty, and that there are no useless separators. Therefore you may safely embed `program_transform_name` within a sed program using '`;`':

```
transform = @program_transform_name@
transform_exe = s/$(EXEEXT)$$//;$(transform);s/$$/$(EXEEXT)/
```

Whether to do the transformations on documentation files (Texinfo or `man`) is a tricky question; there seems to be no perfect answer, due to the several reasons for name transforming. Documentation is not usually particular to a specific architecture, and Texinfo files do not conflict with system documentation. But they might conflict with earlier versions of the same files, and `man` pages sometimes do conflict with system documentation. As a compromise, it is probably best to do name transformations on `man` pages but not on Texinfo manuals.

14.7 Setting Site Defaults

Autoconf-generated `configure` scripts allow your site to provide default values for some configuration values. You do this by creating site- and system-wide initialization files.

If the environment variable `CONFIG_SITE` is set, `configure` uses its value as the name of a shell script to read. Otherwise, it reads the shell script '*`prefix`*`/share/config.site`' if it exists, then '*`prefix`*`/etc/config.site`' if it exists. Thus, settings in machine-specific files override those in machine-independent ones in case of conflict.

Site files can be arbitrary shell scripts, but only certain kinds of code are really appropriate to be in them. Because `configure` reads any cache file after it has read any site files, a site file can define a default cache file to be shared between all Autoconf-generated `configure` scripts run on that system (see Section 7.4.2 [Cache Files], page 104). If you set a default cache file in a site file, it is a good idea to also set the output variable `CC` in that site file, because the cache file is only valid for a particular compiler, but many systems have several available.

You can examine or override the value set by a command line option to `configure` in a site file; options set shell variables that have the same names as the options, with any dashes turned into underscores. The exceptions are that '`--without-`' and '`--disable-`'

options are like giving the corresponding '`--with-`' or '`--enable-`' option and the value '`no`'. Thus, '`--cache-file=localcache`' sets the variable `cache_file` to the value '`localcache`'; '`--enable-warnings=no`' or '`--disable-warnings`' sets the variable `enable_warnings` to the value '`no`'; '`--prefix=/usr`' sets the variable `prefix` to the value '`/usr`'; etc.

Site files are also good places to set default values for other output variables, such as `CFLAGS`, if you need to give them non-default values: anything you would normally do, repetitively, on the command line. If you use non-default values for *prefix* or *exec_prefix* (wherever you locate the site file), you can set them in the site file if you specify it with the `CONFIG_SITE` environment variable.

You can set some cache values in the site file itself. Doing this is useful if you are cross-compiling, where it is impossible to check features that require running a test program. You could "prime the cache" by setting those values correctly for that system in '*prefix*`/etc/config.site`'. To find out the names of the cache variables you need to set, look for shell variables with '`_cv_`' in their names in the affected `configure` scripts, or in the Autoconf M4 source code for those macros.

The cache file is careful to not override any variables set in the site files. Similarly, you should not override command-line options in the site files. Your code should check that variables such as `prefix` and `cache_file` have their default values (as set near the top of `configure`) before changing them.

Here is a sample file '`/usr/share/local/gnu/share/config.site`'. The command '`configure --prefix=/usr/share/local/gnu`' would read this file (if `CONFIG_SITE` is not set to a different file).

```
# config.site for configure
#
# Change some defaults.
test "$prefix" = NONE && prefix=/usr/share/local/gnu
test "$exec_prefix" = NONE && exec_prefix=/usr/local/gnu
test "$sharedstatedir" = '$prefix/com' && sharedstatedir=/var
test "$localstatedir" = '$prefix/var' && localstatedir=/var

# Give Autoconf 2.x generated configure scripts a shared default
# cache file for feature test results, architecture-specific.
if test "$cache_file" = /dev/null; then
  cache_file="$prefix/var/config.cache"
  # A cache file is only valid for one C compiler.
  CC=gcc
fi
```

15 Running `configure` Scripts

Below are instructions on how to configure a package that uses a `configure` script, suitable for inclusion as an '`INSTALL`' file in the package. A plain-text version of '`INSTALL`' which you may use comes with Autoconf.

15.1 Basic Installation

Briefly, the shell commands '`./configure; make; make install`' should configure, build, and install this package. The following more-detailed instructions are generic; see the '`README`' file for instructions specific to this package.

The `configure` shell script attempts to guess correct values for various system-dependent variables used during compilation. It uses those values to create a '`Makefile`' in each directory of the package. It may also create one or more '`.h`' files containing system-dependent definitions. Finally, it creates a shell script '`config.status`' that you can run in the future to recreate the current configuration, and a file '`config.log`' containing compiler output (useful mainly for debugging `configure`).

It can also use an optional file (typically called '`config.cache`' and enabled with '`--cache-file=config.cache`' or simply '`-C`') that saves the results of its tests to speed up reconfiguring. Caching is disabled by default to prevent problems with accidental use of stale cache files.

If you need to do unusual things to compile the package, please try to figure out how `configure` could check whether to do them, and mail diffs or instructions to the address given in the '`README`' so they can be considered for the next release. If you are using the cache, and at some point '`config.cache`' contains results you don't want to keep, you may remove or edit it.

The file '`configure.ac`' (or '`configure.in`') is used to create '`configure`' by a program called `autoconf`. You need '`configure.ac`' if you want to change it or regenerate '`configure`' using a newer version of `autoconf`.

The simplest way to compile this package is:

1. `cd` to the directory containing the package's source code and type '`./configure`' to configure the package for your system.

   Running `configure` might take a while. While running, it prints some messages telling which features it is checking for.

2. Type '`make`' to compile the package.

3. Optionally, type '`make check`' to run any self-tests that come with the package.

4. Type '`make install`' to install the programs and any data files and documentation.

5. You can remove the program binaries and object files from the source code directory by typing '`make clean`'. To also remove the files that `configure` created (so you can compile the package for a different kind of computer), type '`make distclean`'. There is also a '`make maintainer-clean`' target, but that is intended mainly for the package's developers. If you use it, you may have to get all sorts of other programs in order to regenerate files that came with the distribution.

15.2 Compilers and Options

Some systems require unusual options for compilation or linking that the `configure` script does not know about. Run '`./configure --help`' for details on some of the pertinent environment variables.

You can give `configure` initial values for configuration parameters by setting variables in the command line or in the environment. Here is an example:

```
./configure CC=c99 CFLAGS=-g LIBS=-lposix
```

See Section 15.8 [Defining Variables], page 203, for more details.

15.3 Compiling For Multiple Architectures

You can compile the package for more than one kind of computer at the same time, by placing the object files for each architecture in their own directory. To do this, you can use GNU `make`. `cd` to the directory where you want the object files and executables to go and run the `configure` script. `configure` automatically checks for the source code in the directory that `configure` is in and in '`..`'.

With a non-GNU `make`, it is safer to compile the package for one architecture at a time in the source code directory. After you have installed the package for one architecture, use '`make distclean`' before reconfiguring for another architecture.

15.4 Installation Names

By default, '`make install`' installs the package's commands under '`/usr/local/bin`', include files under '`/usr/local/include`', etc. You can specify an installation prefix other than '`/usr/local`' by giving `configure` the option '`--prefix=`*`prefix`*'.

You can specify separate installation prefixes for architecture-specific files and architecture-independent files. If you pass the option '`--exec-prefix=`*`prefix`*' to `configure`, the package uses *prefix* as the prefix for installing programs and libraries. Documentation and other data files still use the regular prefix.

In addition, if you use an unusual directory layout you can give options like '`--bindir=`*`dir`*' to specify different values for particular kinds of files. Run '`configure --help`' for a list of the directories you can set and what kinds of files go in them.

If the package supports it, you can cause programs to be installed with an extra prefix or suffix on their names by giving `configure` the option '`--program-prefix=`*`PREFIX`*' or '`--program-suffix=`*`SUFFIX`*'.

15.5 Optional Features

Some packages pay attention to '`--enable-`*`feature`*' options to `configure`, where *feature* indicates an optional part of the package. They may also pay attention to '`--with-`*`package`*' options, where *package* is something like '`gnu-as`' or '`x`' (for the X Window System). The '`README`' should mention any '`--enable-`' and '`--with-`' options that the package recognizes.

For packages that use the X Window System, `configure` can usually find the X include and library files automatically, but if it doesn't, you can use the `configure` options '`--x-includes=`*`dir`*' and '`--x-libraries=`*`dir`*' to specify their locations.

15.6 Specifying the System Type

There may be some features `configure` cannot figure out automatically, but needs to determine by the type of machine the package will run on. Usually, assuming the package is built to be run on the *same* architectures, `configure` can figure that out, but if it prints a message saying it cannot guess the machine type, give it the '`--build=`*`type`*' option. *type* can either be a short name for the system type, such as '`sun4`', or a canonical name which has the form:

```
cpu-company-system
```

where *system* can have one of these forms:

```
os kernel-os
```

See the file '`config.sub`' for the possible values of each field. If '`config.sub`' isn't included in this package, then this package doesn't need to know the machine type.

If you are *building* compiler tools for cross-compiling, you should use the option '`--target=`*`type`*' to select the type of system they will produce code for.

If you want to *use* a cross compiler, that generates code for a platform different from the build platform, you should specify the *host* platform (i.e., that on which the generated programs will eventually be run) with '`--host=`*`type`*'.

15.7 Sharing Defaults

If you want to set default values for `configure` scripts to share, you can create a site shell script called '`config.site`' that gives default values for variables like `CC`, `cache_file`, and `prefix`. `configure` looks for '*`prefix`*`/share/config.site`' if it exists, then '*`prefix`*`/etc/config.site`' if it exists. Or, you can set the `CONFIG_SITE` environment variable to the location of the site script. A warning: not all `configure` scripts look for a site script.

15.8 Defining Variables

Variables not defined in a site shell script can be set in the environment passed to `configure`. However, some packages may run configure again during the build, and the customized values of these variables may be lost. In order to avoid this problem, you should set them in the `configure` command line, using '`VAR=value`'. For example:

```
./configure CC=/usr/local2/bin/gcc
```

causes the specified `gcc` to be used as the C compiler (unless it is overridden in the site shell script).

Unfortunately, this technique does not work for `CONFIG_SHELL` due to an Autoconf bug. Until the bug is fixed you can use this workaround:

```
CONFIG_SHELL=/bin/bash /bin/bash ./configure CONFIG_SHELL=/bin/bash
```

15.9 `configure` Invocation

`configure` recognizes the following options to control how it operates.

'`--help`'
'`-h`' Print a summary of the options to `configure`, and exit.

‘`--version`’
‘`-V`’ Print the version of Autoconf used to generate the `configure` script, and exit.

‘`--cache-file=`*file*’
Enable the cache: use and save the results of the tests in *file*, traditionally ‘`config.cache`’. *file* defaults to ‘`/dev/null`’ to disable caching.

‘`--config-cache`’
‘`-C`’ Alias for ‘`--cache-file=config.cache`’.

‘`--quiet`’
‘`--silent`’
‘`-q`’ Do not print messages saying which checks are being made. To suppress all normal output, redirect it to ‘`/dev/null`’ (any error messages will still be shown).

‘`--srcdir=`*dir*’
Look for the package's source code in directory *dir*. Usually `configure` can determine that directory automatically.

`configure` also accepts some other, not widely useful, options. Run ‘`configure --help`’ for more details.

16 Recreating a Configuration

The `configure` script creates a file named '`config.status`', which actually configures, *instantiates*, the template files. It also records the configuration options that were specified when the package was last configured in case reconfiguring is needed.

Synopsis:

```
./config.status option... [file...]
```

It configures the *files*; if none are specified, all the templates are instantiated. The files must be specified without their dependencies, as in

```
./config.status foobar
```

not

```
./config.status foobar:foo.in:bar.in
```

The supported options are:

'`--help`'
'`-h`' Print a summary of the command line options, the list of the template files, and exit.

'`--version`'
'`-V`' Print the version number of Autoconf and exit.

'`--silent`'
'`--quiet`'
'`-q`' Do not print progress messages.

'`--debug`'
'`-d`' Don't remove the temporary files.

'`--file=`*file*`[:`*template*`]`'
Require that *file* be instantiated as if '`AC_CONFIG_FILES(`*file*`:`*template*`)`' was used. Both *file* and *template* may be '`-`' in which case the standard output and/or standard input, respectively, is used. If a *template* file name is relative, it is first looked for in the build tree, and then in the source tree. See Section 4.5 [Configuration Actions], page 20, for more details.

This option and the following ones provide one way for separately distributed packages to share the values computed by `configure`. Doing so can be useful if some of the packages need a superset of the features that one of them, perhaps a common library, does. These options allow a '`config.status`' file to create files other than the ones that its '`configure.ac`' specifies, so it can be used for a different package.

'`--header=`*file*`[:`*template*`]`'
Same as '`--file`' above, but with '`AC_CONFIG_HEADERS`'.

'`--recheck`'
Ask '`config.status`' to update itself and exit (no instantiation). This option is useful if you change `configure`, so that the results of some tests might be different from the previous run. The '`--recheck`' option reruns `configure` with the same arguments you used before, plus the '`--no-create`' option, which

prevents `configure` from running '`config.status`' and creating '`Makefile`' and other files, and the '`--no-recursion`' option, which prevents `configure` from running other `configure` scripts in subdirectories. (This is so other Make rules can run '`config.status`' when it changes; see Section 4.7.5 [Automatic Remaking], page 30, for an example).

'`config.status`' checks several optional environment variables that can alter its behavior:

`CONFIG_SHELL` [Variable]

The shell with which to run `configure` for the '`--recheck`' option. It must be Bourne-compatible. The default is a shell that supports `LINENO` if available, and '`/bin/sh`' otherwise. Invoking `configure` by hand bypasses this setting, so you may need to use a command like '`CONFIG_SHELL=/bin/bash /bin/bash ./configure`' to insure that the same shell is used everywhere. The absolute name of the shell should be passed.

`CONFIG_STATUS` [Variable]

The file name to use for the shell script that records the configuration. The default is '`./config.status`'. This variable is useful when one package uses parts of another and the `configure` scripts shouldn't be merged because they are maintained separately.

You can use '`./config.status`' in your makefiles. For example, in the dependencies given above (see Section 4.7.5 [Automatic Remaking], page 30), '`config.status`' is run twice when '`configure.ac`' has changed. If that bothers you, you can make each run only regenerate the files for that rule:

```
config.h: stamp-h
stamp-h: config.h.in config.status
        ./config.status config.h
        echo > stamp-h

Makefile: Makefile.in config.status
        ./config.status Makefile
```

The calling convention of '`config.status`' has changed; see Section 17.1 [Obsolete config.status Use], page 207, for details.

17 Obsolete Constructs

Autoconf changes, and throughout the years some constructs have been obsoleted. Most of the changes involve the macros, but in some cases the tools themselves, or even some concepts, are now considered obsolete.

You may completely skip this chapter if you are new to Autoconf. Its intention is mainly to help maintainers updating their packages by understanding how to move to more modern constructs.

17.1 Obsolete 'config.status' Invocation

'config.status' now supports arguments to specify the files to instantiate; see Chapter 16 [config.status Invocation], page 205, for more details. Before, environment variables had to be used.

CONFIG_COMMANDS [Variable]
: The tags of the commands to execute. The default is the arguments given to AC_OUTPUT and AC_CONFIG_COMMANDS in 'configure.ac'.

CONFIG_FILES [Variable]
: The files in which to perform '@*variable*@' substitutions. The default is the arguments given to AC_OUTPUT and AC_CONFIG_FILES in 'configure.ac'.

CONFIG_HEADERS [Variable]
: The files in which to substitute C #define statements. The default is the arguments given to AC_CONFIG_HEADERS; if that macro was not called, 'config.status' ignores this variable.

CONFIG_LINKS [Variable]
: The symbolic links to establish. The default is the arguments given to AC_CONFIG_LINKS; if that macro was not called, 'config.status' ignores this variable.

In Chapter 16 [config.status Invocation], page 205, using this old interface, the example would be:

```
config.h: stamp-h
stamp-h: config.h.in config.status
        CONFIG_COMMANDS= CONFIG_LINKS= CONFIG_FILES= \
          CONFIG_HEADERS=config.h ./config.status
        echo > stamp-h

Makefile: Makefile.in config.status
        CONFIG_COMMANDS= CONFIG_LINKS= CONFIG_HEADERS= \
          CONFIG_FILES=Makefile ./config.status
```

(If 'configure.ac' does not call AC_CONFIG_HEADERS, there is no need to set CONFIG_HEADERS in the make rules. Equally for CONFIG_COMMANDS, etc.)

17.2 'acconfig.h'

In order to produce 'config.h.in', autoheader needs to build or to find templates for each symbol. Modern releases of Autoconf use AH_VERBATIM and AH_TEMPLATE (see Section 4.8.3 [Autoheader Macros], page 34), but in older releases a file, 'acconfig.h', contained the list of needed templates. autoheader copied comments and #define and #undef statements from 'acconfig.h' in the current directory, if present. This file used to be mandatory if you AC_DEFINE any additional symbols.

Modern releases of Autoconf also provide AH_TOP and AH_BOTTOM if you need to prepend/append some information to 'config.h.in'. Ancient versions of Autoconf had a similar feature: if './acconfig.h' contains the string '@TOP@', autoheader copies the lines before the line containing '@TOP@' into the top of the file that it generates. Similarly, if './acconfig.h' contains the string '@BOTTOM@', autoheader copies the lines after that line to the end of the file it generates. Either or both of those strings may be omitted. An even older alternate way to produce the same effect in ancient versions of Autoconf is to create the files '*file*.top' (typically 'config.h.top') and/or '*file*.bot' in the current directory. If they exist, autoheader copies them to the beginning and end, respectively, of its output.

In former versions of Autoconf, the files used in preparing a software package for distribution were:

```
configure.ac --.   .------> autoconf* -----> configure
               +---+
[aclocal.m4] --+   `---.
[acsite.m4] ---'       |
                       +--> [autoheader*] -> [config.h.in]
[acconfig.h] ----.     |
                 +-----'
[config.h.top] --+
[config.h.bot] --'
```

Using only the AH_ macros, 'configure.ac' should be self-contained, and should not depend upon 'acconfig.h' etc.

17.3 Using autoupdate to Modernize 'configure.ac'

The autoupdate program updates a 'configure.ac' file that calls Autoconf macros by their old names to use the current macro names. In version 2 of Autoconf, most of the macros were renamed to use a more uniform and descriptive naming scheme. See Section 9.2 [Macro Names], page 125, for a description of the new scheme. Although the old names still work (see Section 17.4 [Obsolete Macros], page 209, for a list of the old macros and the corresponding new names), you can make your 'configure.ac' files more readable and make it easier to use the current Autoconf documentation if you update them to use the new macro names.

If given no arguments, autoupdate updates 'configure.ac', backing up the original version with the suffix '~' (or the value of the environment variable SIMPLE_BACKUP_SUFFIX, if that is set). If you give autoupdate an argument, it reads that file instead of 'configure.ac' and writes the updated file to the standard output.

autoupdate accepts the following options:

‘`--help`’
‘`-h`’ Print a summary of the command line options and exit.

‘`--version`’
‘`-V`’ Print the version number of Autoconf and exit.

‘`--verbose`’
‘`-v`’ Report processing steps.

‘`--debug`’
‘`-d`’ Don’t remove the temporary files.

‘`--force`’
‘`-f`’ Force the update even if the file has not changed. Disregard the cache.

‘`--include=`*dir*’
‘`-I` *dir*’ Also look for input files in *dir*. Multiple invocations accumulate. Directories are browsed from last to first.

17.4 Obsolete Macros

Several macros are obsoleted in Autoconf, for various reasons (typically they failed to quote properly, couldn’t be extended for more recent issues, etc.). They are still supported, but deprecated: their use should be avoided.

During the jump from Autoconf version 1 to version 2, most of the macros were renamed to use a more uniform and descriptive naming scheme, but their signature did not change. See Section 9.2 [Macro Names], page 125, for a description of the new naming scheme. Below, if there is just the mapping from old names to new names for these macros, the reader is invited to refer to the definition of the new macro for the signature and the description.

`AC_ALLOCA` [Macro]
`AC_FUNC_ALLOCA`

`AC_ARG_ARRAY` [Macro]
removed because of limited usefulness

`AC_C_CROSS` [Macro]
This macro is obsolete; it does nothing.

`AC_C_LONG_DOUBLE` [Macro]
If the C compiler supports a working `long double` type with more range or precision than the `double` type, define `HAVE_LONG_DOUBLE`.

You should use `AC_TYPE_LONG_DOUBLE` or `AC_TYPE_LONG_DOUBLE_WIDER` instead. See Section 5.9.1 [Particular Types], page 68.

`AC_CANONICAL_SYSTEM` [Macro]
Determine the system type and set output variables to the names of the canonical system types. See Section 13.2 [Canonicalizing], page 190, for details about the variables this macro sets.

The user is encouraged to use either `AC_CANONICAL_BUILD`, or `AC_CANONICAL_HOST`, or `AC_CANONICAL_TARGET`, depending on the needs. Using `AC_CANONICAL_TARGET` is enough to run the two other macros.

AC_CHAR_UNSIGNED [Macro]

AC_C_CHAR_UNSIGNED

AC_CHECK_TYPE (*type*, *default*) [Macro]

Autoconf, up to 2.13, used to provide this version of AC_CHECK_TYPE, deprecated because of its flaws. First, although it is a member of the CHECK clan, it does more than just checking. Secondly, missing types are defined using #define, not typedef, and this can lead to problems in the case of pointer types.

This use of AC_CHECK_TYPE is obsolete and discouraged; see Section 5.9.2 [Generic Types], page 70, for the description of the current macro.

If the type *type* is not defined, define it to be the C (or C++) builtin type *default*, e.g., 'short int' or 'unsigned int'.

This macro is equivalent to:

```
AC_CHECK_TYPE([type], [],
  [AC_DEFINE_UNQUOTED([type], [default],
     [Define to 'default'
      if <sys/types.h> does not define.])])
```

In order to keep backward compatibility, the two versions of AC_CHECK_TYPE are implemented, selected by a simple heuristics:

1. If there are three or four arguments, the modern version is used.
2. If the second argument appears to be a C or C++ type, then the obsolete version is used. This happens if the argument is a C or C++ *builtin* type or a C identifier ending in '_t', optionally followed by one of '[(* ' and then by a string of zero or more characters taken from the set '[]()* _a-zA-Z0-9'.
3. If the second argument is spelled with the alphabet of valid C and C++ types, the user is warned and the modern version is used.
4. Otherwise, the modern version is used.

You are encouraged either to use a valid builtin type, or to use the equivalent modern code (see above), or better yet, to use AC_CHECK_TYPES together with

```
#if !HAVE_LOFF_T
typedef loff_t off_t;
#endif
```

AC_CHECKING (*feature-description*) [Macro]

Same as 'AC_MSG_NOTICE([checking *feature-description*...]'.

AC_COMPILE_CHECK (*echo-text*, *includes*, *function-body*, *action-if-true*, [*action-if-false*]) [Macro]

This is an obsolete version of AC_TRY_COMPILE itself replaced by AC_COMPILE_IFELSE (see Section 6.4 [Running the Compiler], page 93), with the addition that it prints 'checking for *echo-text*' to the standard output first, if *echo-text* is non-empty. Use AC_MSG_CHECKING and AC_MSG_RESULT instead to print messages (see Section 7.5 [Printing Messages], page 105).

AC_CONST [Macro]

AC_C_CONST

AC_CROSS_CHECK [Macro]

Same as AC_C_CROSS, which is obsolete too, and does nothing :-).

AC_CYGWIN [Macro]

Check for the Cygwin environment in which case the shell variable CYGWIN is set to 'yes'. Don't use this macro, the dignified means to check the nature of the host is using AC_CANONICAL_HOST. As a matter of fact this macro is defined as:

```
AC_REQUIRE([AC_CANONICAL_HOST])[]dnl
case $host_os in
  *cygwin* ) CYGWIN=yes;;
         * ) CYGWIN=no;;
esac
```

Beware that the variable CYGWIN has a special meaning when running Cygwin, and should not be changed. That's yet another reason not to use this macro.

AC_DECL_SYS_SIGLIST [Macro]

Same as:

```
AC_CHECK_DECLS([sys_siglist], [], [],
[#include <signal.h>
/* NetBSD declares sys_siglist in unistd.h.  */
#if HAVE_UNISTD_H
# include <unistd.h>
#endif
])
```

AC_DECL_YYTEXT [Macro]

Does nothing, now integrated in AC_PROG_LEX.

AC_DIR_HEADER [Macro]

Like calling AC_FUNC_CLOSEDIR_VOID andAC_HEADER_DIRENT, but defines a different set of C preprocessor macros to indicate which header file is found:

Header	Old Symbol	New Symbol
'dirent.h'	DIRENT	HAVE_DIRENT_H
'sys/ndir.h'	SYSNDIR	HAVE_SYS_NDIR_H
'sys/dir.h'	SYSDIR	HAVE_SYS_DIR_H
'ndir.h'	NDIR	HAVE_NDIR_H

AC_DYNIX_SEQ [Macro]

If on DYNIX/ptx, add '-lseq' to output variable LIBS. This macro used to be defined as

```
AC_CHECK_LIB([seq], [getmntent], [LIBS="-lseq $LIBS"])
```

now it is just AC_FUNC_GETMNTENT.

AC_EXEEXT [Macro]

Defined the output variable EXEEXT based on the output of the compiler, which is now done automatically. Typically set to empty string if Posix and '.exe' if a DOS variant.

AC_EMXOS2 [Macro]
Similar to AC_CYGWIN but checks for the EMX environment on OS/2 and sets EMXOS2.

AC_ERROR [Macro]
AC_MSG_ERROR

AC_FIND_X [Macro]
AC_PATH_X

AC_FIND_XTRA [Macro]
AC_PATH_XTRA

AC_FOREACH [Macro]
m4_foreach_w

AC_FUNC_CHECK [Macro]
AC_CHECK_FUNC

AC_FUNC_WAIT3 [Macro]
If wait3 is found and fills in the contents of its third argument (a 'struct rusage *'), which HP-UX does not do, define HAVE_WAIT3.

These days portable programs should use waitpid, not wait3, as wait3 has been removed from Posix.

AC_GCC_TRADITIONAL [Macro]
AC_PROG_GCC_TRADITIONAL

AC_GETGROUPS_T [Macro]
AC_TYPE_GETGROUPS

AC_GETLOADAVG [Macro]
AC_FUNC_GETLOADAVG

AC_HAVE_FUNCS [Macro]
AC_CHECK_FUNCS

AC_HAVE_HEADERS [Macro]
AC_CHECK_HEADERS

AC_HAVE_LIBRARY (*library*, [*action-if-found*], [*action-if-not-found*], [*other-libraries*]) [Macro]
This macro is equivalent to calling AC_CHECK_LIB with a *function* argument of main. In addition, *library* can be written as any of 'foo', '-lfoo', or 'libfoo.a'. In all of those cases, the compiler is passed '-lfoo'. However, *library* cannot be a shell variable; it must be a literal name.

AC_HAVE_POUNDBANG [Macro]
AC_SYS_INTERPRETER (different calling convention)

AC_HEADER_CHECK [Macro]
AC_CHECK_HEADER

`AC_HEADER_EGREP` [Macro]
`AC_EGREP_HEADER`

`AC_HELP_STRING` [Macro]
`AS_HELP_STRING`

`AC_INIT (`*`unique-file-in-source-dir`*`)` [Macro]
Formerly `AC_INIT` used to have a single argument, and was equivalent to:

```
AC_INIT
AC_CONFIG_SRCDIR(unique-file-in-source-dir)
```

`AC_INLINE` [Macro]
`AC_C_INLINE`

`AC_INT_16_BITS` [Macro]
If the C type `int` is 16 bits wide, define `INT_16_BITS`. Use '`AC_CHECK_SIZEOF(int)`' instead.

`AC_IRIX_SUN` [Macro]
If on IRIX (Silicon Graphics Unix), add '`-lsun`' to output `LIBS`. If you were using it to get `getmntent`, use `AC_FUNC_GETMNTENT` instead. If you used it for the NIS versions of the password and group functions, use '`AC_CHECK_LIB(sun, getpwnam)`'. Up to Autoconf 2.13, it used to be

```
AC_CHECK_LIB([sun], [getmntent], [LIBS="-lsun $LIBS"])
```

now it is defined as

```
AC_FUNC_GETMNTENT
AC_CHECK_LIB([sun], [getpwnam])
```

`AC_LANG_C` [Macro]
Same as '`AC_LANG([C])`'.

`AC_LANG_CPLUSPLUS` [Macro]
Same as '`AC_LANG([C++])`'.

`AC_LANG_FORTRAN77` [Macro]
Same as '`AC_LANG([Fortran 77])`'.

`AC_LANG_RESTORE` [Macro]
Select the *language* that is saved on the top of the stack, as set by `AC_LANG_SAVE`, remove it from the stack, and call `AC_LANG(`*`language`*`)`.

`AC_LANG_SAVE` [Macro]
Remember the current language (as set by `AC_LANG`) on a stack. The current language does not change. `AC_LANG_PUSH` is preferred.

`AC_LINK_FILES (`*`source...`*`, `*`dest...`*`)` [Macro]
This is an obsolete version of `AC_CONFIG_LINKS`. An updated version of:

```
AC_LINK_FILES(config/$machine.h config/$obj_format.h,
              host.h            object.h)
```

is:

```
AC_CONFIG_LINKS([host.h:config/$machine.h
                object.h:config/$obj_format.h])
```

AC_LN_S [Macro]
: AC_PROG_LN_S

AC_LONG_64_BITS [Macro]
: Define LONG_64_BITS if the C type long int is 64 bits wide. Use the generic macro 'AC_CHECK_SIZEOF([long int])' instead.

AC_LONG_DOUBLE [Macro]
: If the C compiler supports a working long double type with more range or precision than the double type, define HAVE_LONG_DOUBLE.

  You should use AC_TYPE_LONG_DOUBLE or AC_TYPE_LONG_DOUBLE_WIDER instead. See Section 5.9.1 [Particular Types], page 68.

AC_LONG_FILE_NAMES [Macro]
: AC_SYS_LONG_FILE_NAMES

AC_MAJOR_HEADER [Macro]
: AC_HEADER_MAJOR

AC_MEMORY_H [Macro]
: Used to define NEED_MEMORY_H if the mem functions were defined in 'memory.h'. Today it is equivalent to 'AC_CHECK_HEADERS([memory.h])'. Adjust your code to depend upon HAVE_MEMORY_H, not NEED_MEMORY_H; see Section 5.1.1 [Standard Symbols], page 39.

AC_MINGW32 [Macro]
: Similar to AC_CYGWIN but checks for the MinGW compiler environment and sets MINGW32.

AC_MINUS_C_MINUS_O [Macro]
: AC_PROG_CC_C_O

AC_MMAP [Macro]
: AC_FUNC_MMAP

AC_MODE_T [Macro]
: AC_TYPE_MODE_T

AC_OBJEXT [Macro]
: Defined the output variable OBJEXT based on the output of the compiler, after .c files have been excluded. Typically set to 'o' if Posix, 'obj' if a DOS variant. Now the compiler checking macros handle this automatically.

AC_OBSOLETE (*this-macro-name*, [*suggestion*]) [Macro]
: Make M4 print a message to the standard error output warning that *this-macro-name* is obsolete, and giving the file and line number where it was called. *this-macro-name* should be the name of the macro that is calling AC_OBSOLETE. If *suggestion* is given,

it is printed at the end of the warning message; for example, it can be a suggestion for what to use instead of *this-macro-name*.

For instance

```
AC_OBSOLETE([$0], [; use AC_CHECK_HEADERS(unistd.h) instead])dnl
```

You are encouraged to use `AU_DEFUN` instead, since it gives better services to the user.

`AC_OFF_T` [Macro]

`AC_TYPE_OFF_T`

`AC_OUTPUT` ([*file*]..., [*extra-cmds*], [*init-cmds*]) [Macro]

The use of `AC_OUTPUT` with argument is deprecated. This obsoleted interface is equivalent to:

```
AC_CONFIG_FILES(file...)
AC_CONFIG_COMMANDS([default],
                   extra-cmds, init-cmds)
AC_OUTPUT
```

`AC_OUTPUT_COMMANDS` (*extra-cmds*, [*init-cmds*]) [Macro]

Specify additional shell commands to run at the end of '`config.status`', and shell commands to initialize any variables from `configure`. This macro may be called multiple times. It is obsolete, replaced by `AC_CONFIG_COMMANDS`.

Here is an unrealistic example:

```
fubar=27
AC_OUTPUT_COMMANDS([echo this is extra $fubar, and so on.],
                   [fubar=$fubar])
AC_OUTPUT_COMMANDS([echo this is another, extra, bit],
                   [echo init bit])
```

Aside from the fact that `AC_CONFIG_COMMANDS` requires an additional key, an important difference is that `AC_OUTPUT_COMMANDS` is quoting its arguments twice, unlike `AC_CONFIG_COMMANDS`. This means that `AC_CONFIG_COMMANDS` can safely be given macro calls as arguments:

```
AC_CONFIG_COMMANDS(foo, [my_FOO()])
```

Conversely, where one level of quoting was enough for literal strings with `AC_OUTPUT_COMMANDS`, you need two with `AC_CONFIG_COMMANDS`. The following lines are equivalent:

```
AC_OUTPUT_COMMANDS([echo "Square brackets: []"])
AC_CONFIG_COMMANDS([default], [[echo "Square brackets: []"]])
```

`AC_PID_T` [Macro]

`AC_TYPE_PID_T`

`AC_PREFIX` [Macro]

`AC_PREFIX_PROGRAM`

`AC_PROGRAMS_CHECK` [Macro]

`AC_CHECK_PROGS`

AC_PROGRAMS_PATH [Macro]
AC_PATH_PROGS

AC_PROGRAM_CHECK [Macro]
AC_CHECK_PROG

AC_PROGRAM_EGREP [Macro]
AC_EGREP_CPP

AC_PROGRAM_PATH [Macro]
AC_PATH_PROG

AC_REMOTE_TAPE [Macro]
removed because of limited usefulness

AC_RESTARTABLE_SYSCALLS [Macro]
AC_SYS_RESTARTABLE_SYSCALLS

AC_RETSIGTYPE [Macro]
AC_TYPE_SIGNAL

AC_RSH [Macro]
removed because of limited usefulness

AC_SCO_INTL [Macro]
If on SCO Unix, add '`-lintl`' to output variable `LIBS`. This macro used to do this:

```
AC_CHECK_LIB([intl], [strftime], [LIBS="-lintl $LIBS"])
```

Now it just calls `AC_FUNC_STRFTIME` instead.

AC_SETVBUF_REVERSED [Macro]
AC_FUNC_SETVBUF_REVERSED

AC_SET_MAKE [Macro]
AC_PROG_MAKE_SET

AC_SIZEOF_TYPE [Macro]
AC_CHECK_SIZEOF

AC_SIZE_T [Macro]
AC_TYPE_SIZE_T

AC_STAT_MACROS_BROKEN [Macro]
AC_HEADER_STAT

AC_STDC_HEADERS [Macro]
AC_HEADER_STDC

AC_STRCOLL [Macro]
AC_FUNC_STRCOLL

AC_ST_BLKSIZE [Macro]
AC_CHECK_MEMBERS

`AC_ST_BLOCKS` [Macro]
: `AC_STRUCT_ST_BLOCKS`

`AC_ST_RDEV` [Macro]
: `AC_CHECK_MEMBERS`

`AC_SYS_RESTARTABLE_SYSCALLS` [Macro]
: If the system automatically restarts a system call that is interrupted by a signal, define `HAVE_RESTARTABLE_SYSCALLS`. This macro does not check whether system calls are restarted in general—it checks whether a signal handler installed with `signal` (but not `sigaction`) causes system calls to be restarted. It does not check whether system calls can be restarted when interrupted by signals that have no handler.

  These days portable programs should use `sigaction` with `SA_RESTART` if they want restartable system calls. They should not rely on `HAVE_RESTARTABLE_SYSCALLS`, since nowadays whether a system call is restartable is a dynamic issue, not a configuration-time issue.

`AC_SYS_SIGLIST_DECLARED` [Macro]
: `AC_DECL_SYS_SIGLIST`

`AC_TEST_CPP` [Macro]
: `AC_TRY_CPP`, replaced by `AC_PREPROC_IFELSE`.

`AC_TEST_PROGRAM` [Macro]
: `AC_TRY_RUN`, replaced by `AC_RUN_IFELSE`.

`AC_TIMEZONE` [Macro]
: `AC_STRUCT_TIMEZONE`

`AC_TIME_WITH_SYS_TIME` [Macro]
: `AC_HEADER_TIME`

`AC_TRY_COMPILE (`*`includes`*`, `*`function-body`*`, [`*`action-if-true`*`], [`*`action-if-false`*`])` [Macro]
: Same as:

```
AC_COMPILE_IFELSE(
  [AC_LANG_PROGRAM([[includes]],
     [[function-body]])],
  [action-if-true],
  [action-if-false])
```

  See Section 6.4 [Running the Compiler], page 93.

  This macro double quotes both *includes* and *function-body*.

  For C and C++, *includes* is any `#include` statements needed by the code in *function-body* (*includes* is ignored if the currently selected language is Fortran or Fortran 77). The compiler and compilation flags are determined by the current language (see Section 6.1 [Language Choice], page 87).

`AC_TRY_CPP (`*input*`, [`*action-if-true*`], [`*action-if-false*`])` [Macro]

Same as:

```
AC_PREPROC_IFELSE(
  [AC_LANG_SOURCE([[input]])],
  [action-if-true],
  [action-if-false])
```

See Section 6.3 [Running the Preprocessor], page 92.

This macro double quotes the *input*.

`AC_TRY_LINK (`*includes*`, `*function-body*`, [`*action-if-true*`], [`*action-if-false*`])` [Macro]

Same as:

```
AC_LINK_IFELSE(
  [AC_LANG_PROGRAM([[includes]],
     [[function-body]])],
  [action-if-true],
  [action-if-false])
```

See Section 6.4 [Running the Compiler], page 93.

This macro double quotes both *includes* and *function-body*.

Depending on the current language (see Section 6.1 [Language Choice], page 87), create a test program to see whether a function whose body consists of *function-body* can be compiled and linked. If the file compiles and links successfully, run shell commands *action-if-found*, otherwise run *action-if-not-found*.

This macro double quotes both *includes* and *function-body*.

For C and C++, *includes* is any `#include` statements needed by the code in *function-body* (*includes* is ignored if the currently selected language is Fortran or Fortran 77). The compiler and compilation flags are determined by the current language (see Section 6.1 [Language Choice], page 87), and in addition `LDFLAGS` and `LIBS` are used for linking.

`AC_TRY_LINK_FUNC (`*function*`, [`*action-if-found*`], [`*action-if-not-found*`])` [Macro]

This macro is equivalent to '`AC_LINK_IFELSE([AC_LANG_CALL([], [`*function*`])], [`*action-if-found*`], [`*action-if-not-found*`])`'.

`AC_TRY_RUN (`*program*`, [`*action-if-true*`], [`*action-if-false*`], [`*action-if-cross-compiling*`])` [Macro]

Same as:

```
AC_RUN_IFELSE(
  [AC_LANG_SOURCE([[program]])],
  [action-if-true],
  [action-if-false],
  [action-if-cross-compiling])
```

See Section 6.6 [Runtime], page 94.

AC_UID_T [Macro]
AC_TYPE_UID_T

AC_UNISTD_H [Macro]
Same as 'AC_CHECK_HEADERS([unistd.h])'.

AC_USG [Macro]
Define USG if the BSD string functions are defined in 'strings.h'. You should no longer depend upon USG, but on HAVE_STRING_H; see Section 5.1.1 [Standard Symbols], page 39.

AC_UTIME_NULL [Macro]
AC_FUNC_UTIME_NULL

AC_VALIDATE_CACHED_SYSTEM_TUPLE ([*cmd*]) [Macro]
If the cache file is inconsistent with the current host, target and build system types, it used to execute *cmd* or print a default error message. This is now handled by default.

AC_VERBOSE (*result-description*) [Macro]
AC_MSG_RESULT.

AC_VFORK [Macro]
AC_FUNC_VFORK

AC_VPRINTF [Macro]
AC_FUNC_VPRINTF

AC_WAIT3 [Macro]
AC_FUNC_WAIT3

AC_WARN [Macro]
AC_MSG_WARN

AC_WORDS_BIGENDIAN [Macro]
AC_C_BIGENDIAN

AC_XENIX_DIR [Macro]
This macro used to add '-lx' to output variable LIBS if on Xenix. Also, if 'dirent.h' is being checked for, added '-ldir' to LIBS. Now it is merely an alias of AC_HEADER_DIRENT instead, plus some code to detect whether running XENIX on which you should not depend:

```
AC_MSG_CHECKING([for Xenix])
AC_EGREP_CPP([yes],
[#if defined M_XENIX && !defined M_UNIX
  yes
#endif],
              [AC_MSG_RESULT([yes]); XENIX=yes],
              [AC_MSG_RESULT([no]); XENIX=])
```

AC_YYTEXT_POINTER [Macro]
AC_DECL_YYTEXT

17.5 Upgrading From Version 1

Autoconf version 2 is mostly backward compatible with version 1. However, it introduces better ways to do some things, and doesn't support some of the ugly things in version 1. So, depending on how sophisticated your '`configure.ac`' files are, you might have to do some manual work in order to upgrade to version 2. This chapter points out some problems to watch for when upgrading. Also, perhaps your `configure` scripts could benefit from some of the new features in version 2; the changes are summarized in the file '`NEWS`' in the Autoconf distribution.

17.5.1 Changed File Names

If you have an '`aclocal.m4`' installed with Autoconf (as opposed to in a particular package's source directory), you must rename it to '`acsite.m4`'. See Section 3.4 [autoconf Invocation], page 12.

If you distribute '`install.sh`' with your package, rename it to '`install-sh`' so `make` builtin rules don't inadvertently create a file called '`install`' from it. `AC_PROG_INSTALL` looks for the script under both names, but it is best to use the new name.

If you were using '`config.h.top`', '`config.h.bot`', or '`acconfig.h`', you still can, but you have less clutter if you use the `AH_` macros. See Section 4.8.3 [Autoheader Macros], page 34.

17.5.2 Changed Makefiles

Add '`@CFLAGS@`', '`@CPPFLAGS@`', and '`@LDFLAGS@`' in your '`Makefile.in`' files, so they can take advantage of the values of those variables in the environment when `configure` is run. Doing this isn't necessary, but it's a convenience for users.

Also add '`@configure_input@`' in a comment to each input file for `AC_OUTPUT`, so that the output files contain a comment saying they were produced by `configure`. Automatically selecting the right comment syntax for all the kinds of files that people call `AC_OUTPUT` on became too much work.

Add '`config.log`' and '`config.cache`' to the list of files you remove in `distclean` targets.

If you have the following in '`Makefile.in`':

```
prefix = /usr/local
exec_prefix = $(prefix)
```

you must change it to:

```
prefix = @prefix@
exec_prefix = @exec_prefix@
```

The old behavior of replacing those variables without '`@`' characters around them has been removed.

17.5.3 Changed Macros

Many of the macros were renamed in Autoconf version 2. You can still use the old names, but the new ones are clearer, and it's easier to find the documentation for them. See Section 17.4 [Obsolete Macros], page 209, for a table showing the new names for the old

macros. Use the `autoupdate` program to convert your '`configure.ac`' to using the new macro names. See Section 17.3 [autoupdate Invocation], page 208.

Some macros have been superseded by similar ones that do the job better, but are not call-compatible. If you get warnings about calling obsolete macros while running `autoconf`, you may safely ignore them, but your `configure` script generally works better if you follow the advice that is printed about what to replace the obsolete macros with. In particular, the mechanism for reporting the results of tests has changed. If you were using `echo` or `AC_VERBOSE` (perhaps via `AC_COMPILE_CHECK`), your `configure` script's output looks better if you switch to `AC_MSG_CHECKING` and `AC_MSG_RESULT`. See Section 7.5 [Printing Messages], page 105. Those macros work best in conjunction with cache variables. See Section 7.4 [Caching Results], page 102.

17.5.4 Changed Results

If you were checking the results of previous tests by examining the shell variable `DEFS`, you need to switch to checking the values of the cache variables for those tests. `DEFS` no longer exists while `configure` is running; it is only created when generating output files. This difference from version 1 is because properly quoting the contents of that variable turned out to be too cumbersome and inefficient to do every time `AC_DEFINE` is called. See Section 7.4.1 [Cache Variable Names], page 104.

For example, here is a '`configure.ac`' fragment written for Autoconf version 1:

```
AC_HAVE_FUNCS(syslog)
case "$DEFS" in
*-DHAVE_SYSLOG*) ;;
*) # syslog is not in the default libraries.  See if it's in some other.
  saved_LIBS="$LIBS"
  for lib in bsd socket inet; do
    AC_CHECKING(for syslog in -l$lib)
    LIBS="-l$lib $saved_LIBS"
    AC_HAVE_FUNCS(syslog)
    case "$DEFS" in
    *-DHAVE_SYSLOG*) break ;;
    *) ;;
    esac
    LIBS="$saved_LIBS"
  done ;;
esac
```

Here is a way to write it for version 2:

```
AC_CHECK_FUNCS([syslog])
if test $ac_cv_func_syslog = no; then
  # syslog is not in the default libraries.  See if it's in some other.
  for lib in bsd socket inet; do
    AC_CHECK_LIB([$lib], [syslog], [AC_DEFINE([HAVE_SYSLOG])
      LIBS="-l$lib $LIBS"; break])
  done
fi
```

If you were working around bugs in `AC_DEFINE_UNQUOTED` by adding backslashes before quotes, you need to remove them. It now works predictably, and does not treat quotes (except back quotes) specially. See Section 7.2 [Setting Output Variables], page 100.

All of the Boolean shell variables set by Autoconf macros now use '`yes`' for the true value. Most of them use '`no`' for false, though for backward compatibility some use the empty string instead. If you were relying on a shell variable being set to something like 1 or '`t`' for true, you need to change your tests.

17.5.5 Changed Macro Writing

When defining your own macros, you should now use `AC_DEFUN` instead of `define`. `AC_DEFUN` automatically calls `AC_PROVIDE` and ensures that macros called via `AC_REQUIRE` do not interrupt other macros, to prevent nested '`checking...`' messages on the screen. There's no actual harm in continuing to use the older way, but it's less convenient and attractive. See Section 9.1 [Macro Definitions], page 125.

You probably looked at the macros that came with Autoconf as a guide for how to do things. It would be a good idea to take a look at the new versions of them, as the style is somewhat improved and they take advantage of some new features.

If you were doing tricky things with undocumented Autoconf internals (macros, variables, diversions), check whether you need to change anything to account for changes that have been made. Perhaps you can even use an officially supported technique in version 2 instead of kludging. Or perhaps not.

To speed up your locally written feature tests, add caching to them. See whether any of your tests are of general enough usefulness to encapsulate them into macros that you can share.

17.6 Upgrading From Version 2.13

The introduction of the previous section (see Section 17.5 [Autoconf 1], page 220) perfectly suits this section...

> Autoconf version 2.50 is mostly backward compatible with version 2.13. However, it introduces better ways to do some things, and doesn't support some of the ugly things in version 2.13. So, depending on how sophisticated your '`configure.ac`' files are, you might have to do some manual work in order to upgrade to version 2.50. This chapter points out some problems to watch for when upgrading. Also, perhaps your `configure` scripts could benefit from some of the new features in version 2.50; the changes are summarized in the file '`NEWS`' in the Autoconf distribution.

17.6.1 Changed Quotation

The most important changes are invisible to you: the implementation of most macros have completely changed. This allowed more factorization of the code, better error messages, a higher uniformity of the user's interface etc. Unfortunately, as a side effect, some construct which used to (miraculously) work might break starting with Autoconf 2.50. The most common culprit is bad quotation.

For instance, in the following example, the message is not properly quoted:

```
AC_INIT
AC_CHECK_HEADERS(foo.h, ,
  AC_MSG_ERROR(cannot find foo.h, bailing out))
AC_OUTPUT
```

Autoconf 2.13 simply ignores it:

```
$ autoconf-2.13; ./configure --silent
creating cache ./config.cache
configure: error: cannot find foo.h
$
```

while Autoconf 2.50 produces a broken 'configure':

```
$ autoconf-2.50; ./configure --silent
configure: error: cannot find foo.h
./configure: exit: bad non-numeric arg `bailing'
./configure: exit: bad non-numeric arg `bailing'
$
```

The message needs to be quoted, and the AC_MSG_ERROR invocation too!

```
AC_INIT([Example], [1.0], [bug-example@example.org])
AC_CHECK_HEADERS([foo.h], [],
  [AC_MSG_ERROR([cannot find foo.h, bailing out])])
AC_OUTPUT
```

Many many (and many more) Autoconf macros were lacking proper quotation, including no less than... AC_DEFUN itself!

```
$ cat configure.in
AC_DEFUN([AC_PROG_INSTALL],
[# My own much better version
])
AC_INIT
AC_PROG_INSTALL
AC_OUTPUT
$ autoconf-2.13
autoconf: Undefined macros:
***BUG in Autoconf--please report*** AC_FD_MSG
***BUG in Autoconf--please report*** AC_EPI
configure.in:1:AC_DEFUN([AC_PROG_INSTALL],
configure.in:5:AC_PROG_INSTALL
$ autoconf-2.50
$
```

17.6.2 New Macros

While Autoconf was relatively dormant in the late 1990s, Automake provided Autoconf-like macros for a while. Starting with Autoconf 2.50 in 2001, Autoconf provided versions of these macros, integrated in the AC_ namespace, instead of AM_. But in order to ease the upgrading via autoupdate, bindings to such AM_ macros are provided.

Unfortunately older versions of Automake (e.g., Automake 1.4) did not quote the names of these macros. Therefore, when m4 finds something like 'AC_DEFUN(AM_TYPE_PTRDIFF_T,

...)' in 'aclocal.m4', AM_TYPE_PTRDIFF_T is expanded, replaced with its Autoconf definition.

Fortunately Autoconf catches pre-AC_INIT expansions, and complains, in its own words:

```
$ cat configure.ac
AC_INIT([Example], [1.0], [bug-example@example.org])
AM_TYPE_PTRDIFF_T
$ aclocal-1.4
$ autoconf
aclocal.m4:17: error: m4_defn: undefined macro: _m4_divert_diversion
aclocal.m4:17: the top level
autom4te: m4 failed with exit status: 1
$
```

Modern versions of Automake no longer define most of these macros, and properly quote the names of the remaining macros. If you must use an old Automake, do not depend upon macros from Automake as it is simply not its job to provide macros (but the one it requires itself):

```
$ cat configure.ac
AC_INIT([Example], [1.0], [bug-example@example.org])
AM_TYPE_PTRDIFF_T
$ rm aclocal.m4
$ autoupdate
autoupdate: 'configure.ac' is updated
$ cat configure.ac
AC_INIT([Example], [1.0], [bug-example@example.org])
AC_CHECK_TYPES([ptrdiff_t])
$ aclocal-1.4
$ autoconf
$
```

17.6.3 Hosts and Cross-Compilation

Based on the experience of compiler writers, and after long public debates, many aspects of the cross-compilation chain have changed:

- the relationship between the build, host, and target architecture types,
- the command line interface for specifying them to configure,
- the variables defined in configure,
- the enabling of cross-compilation mode.

The relationship between build, host, and target have been cleaned up: the chain of default is now simply: target defaults to host, host to build, and build to the result of config.guess. Nevertheless, in order to ease the transition from 2.13 to 2.50, the following transition scheme is implemented. *Do not rely on it*, as it will be completely disabled in a couple of releases (we cannot keep it, as it proves to cause more problems than it cures).

They all default to the result of running config.guess, unless you specify either '--build' or '--host'. In this case, the default becomes the system type you specified. If

you specify both, and they're different, `configure` enters cross compilation mode, so it doesn't run any tests that require execution.

Hint: if you mean to override the result of `config.guess`, prefer '`--build`' over '`--host`'. In the future, '`--host`' will not override the name of the build system type. Whenever you specify '`--host`', be sure to specify '`--build`' too.

For backward compatibility, `configure` accepts a system type as an option by itself. Such an option overrides the defaults for build, host, and target system types. The following configure statement configures a cross toolchain that runs on NetBSD/alpha but generates code for GNU Hurd/sparc, which is also the build platform.

```
./configure --host=alpha-netbsd sparc-gnu
```

In Autoconf 2.13 and before, the variables `build`, `host`, and `target` had a different semantics before and after the invocation of `AC_CANONICAL_BUILD` etc. Now, the argument of '`--build`' is strictly copied into `build_alias`, and is left empty otherwise. After the `AC_CANONICAL_BUILD`, `build` is set to the canonicalized build type. To ease the transition, before, its contents is the same as that of `build_alias`. Do *not* rely on this broken feature.

For consistency with the backward compatibility scheme exposed above, when '`--host`' is specified but '`--build`' isn't, the build system is assumed to be the same as '`--host`', and '`build_alias`' is set to that value. Eventually, this historically incorrect behavior will go away.

The former scheme to enable cross-compilation proved to cause more harm than good, in particular, it used to be triggered too easily, leaving regular end users puzzled in front of cryptic error messages. `configure` could even enter cross-compilation mode only because the compiler was not functional. This is mainly because `configure` used to try to detect cross-compilation, instead of waiting for an explicit flag from the user.

Now, `configure` enters cross-compilation mode if and only if '`--host`' is passed.

That's the short documentation. To ease the transition between 2.13 and its successors, a more complicated scheme is implemented. *Do not rely on the following*, as it will be removed in the near future.

If you specify '`--host`', but not '`--build`', when `configure` performs the first compiler test it tries to run an executable produced by the compiler. If the execution fails, it enters cross-compilation mode. This is fragile. Moreover, by the time the compiler test is performed, it may be too late to modify the build-system type: other tests may have already been performed. Therefore, whenever you specify '`--host`', be sure to specify '`--build`' too.

```
./configure --build=i686-pc-linux-gnu --host=m68k-coff
```

enters cross-compilation mode. The former interface, which consisted in setting the compiler to a cross-compiler without informing `configure` is obsolete. For instance, `configure` fails if it can't run the code generated by the specified compiler if you configure as follows:

```
./configure CC=m68k-coff-gcc
```

17.6.4 AC_LIBOBJ vs. LIBOBJS

Up to Autoconf 2.13, the replacement of functions was triggered via the variable LIBOBJS. Since Autoconf 2.50, the macro AC_LIBOBJ should be used instead (see Section 5.5.3 [Generic Functions], page 56). Starting at Autoconf 2.53, the use of LIBOBJS is an error.

This change is mandated by the unification of the GNU Build System components. In particular, the various fragile techniques used to parse a 'configure.ac' are all replaced with the use of traces. As a consequence, any action must be traceable, which obsoletes critical variable assignments. Fortunately, LIBOBJS was the only problem, and it can even be handled gracefully (read, "without your having to change something").

There were two typical uses of LIBOBJS: asking for a replacement function, and adjusting LIBOBJS for Automake and/or Libtool.

As for function replacement, the fix is immediate: use AC_LIBOBJ. For instance:

```
LIBOBJS="$LIBOBJS fnmatch.o"
LIBOBJS="$LIBOBJS malloc.$ac_objext"
```

should be replaced with:

```
AC_LIBOBJ([fnmatch])
AC_LIBOBJ([malloc])
```

When used with Automake 1.10 or newer, a suitable value for LIBOBJDIR is set so that the LIBOBJS and LTLIBOBJS can be referenced from any 'Makefile.am'. Even without Automake, arranging for LIBOBJDIR to be set correctly enables referencing LIBOBJS and LTLIBOBJS in another directory. The LIBOJBDIR feature is experimental.

17.6.5 AC_FOO_IFELSE vs. AC_TRY_FOO

Since Autoconf 2.50, internal codes uses AC_PREPROC_IFELSE, AC_COMPILE_IFELSE, AC_LINK_IFELSE, and AC_RUN_IFELSE on one hand and AC_LANG_SOURCES, and AC_LANG_PROGRAM on the other hand instead of the deprecated AC_TRY_CPP, AC_TRY_COMPILE, AC_TRY_LINK, and AC_TRY_RUN. The motivations where:

- a more consistent interface: AC_TRY_COMPILE etc. were double quoting their arguments;
- the combinatoric explosion is solved by decomposing on the one hand the generation of sources, and on the other hand executing the program;
- this scheme helps supporting more languages than plain C and C++.

In addition to the change of syntax, the philosophy has changed too: while emphasis was put on speed at the expense of accuracy, today's Autoconf promotes accuracy of the testing framework at, ahem. . . , the expense of speed.

As a perfect example of what is *not* to be done, here is how to find out whether a header file contains a particular declaration, such as a typedef, a structure, a structure member, or a function. Use AC_EGREP_HEADER instead of running grep directly on the header file; on some systems the symbol might be defined in another header file that the file you are checking includes.

As a (bad) example, here is how you should not check for C preprocessor symbols, either defined by header files or predefined by the C preprocessor: using AC_EGREP_CPP:

```
AC_EGREP_CPP(yes,
[#ifdef _AIX
  yes
#endif
], is_aix=yes, is_aix=no)
```

The above example, properly written would (i) use `AC_LANG_PROGRAM`, and (ii) run the compiler:

```
AC_COMPILE_IFELSE([AC_LANG_PROGRAM(
[[#if !defined _AIX
 error: This isn't AIX!
#endif
]])],
                   [is_aix=yes],
                   [is_aix=no])
```

18 Generating Test Suites with Autotest

N.B.: This section describes an experimental feature which will be part of Autoconf in a forthcoming release. Although we believe Autotest is stabilizing, this documentation describes an interface which might change in the future: do not depend upon Autotest without subscribing to the Autoconf mailing lists.

It is paradoxical that portable projects depend on nonportable tools to run their test suite. Autoconf by itself is the paragon of this problem: although it aims at perfectly portability, up to 2.13 its test suite was using DejaGNU, a rich and complex testing framework, but which is far from being standard on Posix systems. Worse yet, it was likely to be missing on the most fragile platforms, the very platforms that are most likely to torture Autoconf and exhibit deficiencies.

To circumvent this problem, many package maintainers have developed their own testing framework, based on simple shell scripts whose sole outputs are exit status values describing whether the test succeeded. Most of these tests share common patterns, and this can result in lots of duplicated code and tedious maintenance.

Following exactly the same reasoning that yielded to the inception of Autoconf, Autotest provides a test suite generation framework, based on M4 macros building a portable shell script. The suite itself is equipped with automatic logging and tracing facilities which greatly diminish the interaction with bug reporters, and simple timing reports.

Autoconf itself has been using Autotest for years, and we do attest that it has considerably improved the strength of the test suite and the quality of bug reports. Other projects are known to use some generation of Autotest, such as Bison, Free Recode, Free Wdiff, GNU Tar, each of them with different needs, and this usage has validated Autotest as a general testing framework.

Nonetheless, compared to DejaGNU, Autotest is inadequate for interactive tool testing, which is probably its main limitation.

18.1 Using an Autotest Test Suite

18.1.1 `testsuite` Scripts

Generating testing or validation suites using Autotest is rather easy. The whole validation suite is held in a file to be processed through `autom4te`, itself using GNU M4 under the scene, to produce a stand-alone Bourne shell script which then gets distributed. Neither `autom4te` nor GNU M4 are needed at the installer's end.

Each test of the validation suite should be part of some test group. A *test group* is a sequence of interwoven tests that ought to be executed together, usually because one test in the group creates data files than a later test in the same group needs to read. Complex test groups make later debugging more tedious. It is much better to keep only a few tests per test group. Ideally there is only one test per test group.

For all but the simplest packages, some file such as '`testsuite.at`' does not fully hold all test sources, as these are often easier to maintain in separate files. Each of these separate files holds a single test group, or a sequence of test groups all addressing some common functionality in the package. In such cases, '`testsuite.at`' merely initializes the validation

suite, and sometimes does elementary health checking, before listing include statements for all other test files. The special file '`package.m4`', containing the identification of the package, is automatically included if found.

A convenient alternative consists in moving all the global issues (local Autotest macros, elementary health checking, and `AT_INIT` invocation) into the file `local.at`, and making '`testsuite.at`' be a simple list of `m4_include` of sub test suites. In such case, generating the whole test suite or pieces of it is only a matter of choosing the `autom4te` command line arguments.

The validation scripts that Autotest produces are by convention called `testsuite`. When run, `testsuite` executes each test group in turn, producing only one summary line per test to say if that particular test succeeded or failed. At end of all tests, summarizing counters get printed. One debugging directory is left for each test group which failed, if any: such directories are named '`testsuite.dir/`*nn*', where *nn* is the sequence number of the test group, and they include:

- a debugging script named '`run`' which reruns the test in *debug mode* (see Section 18.3 [testsuite Invocation], page 233). The automatic generation of debugging scripts has the purpose of easing the chase for bugs.
- all the files created with `AT_DATA`
- a log of the run, named '`testsuite.log`'

In the ideal situation, none of the tests fail, and consequently no debugging directory is left behind for validation.

It often happens in practice that individual tests in the validation suite need to get information coming out of the configuration process. Some of this information, common for all validation suites, is provided through the file '`atconfig`', automatically created by `AC_CONFIG_TESTDIR`. For configuration informations which your testing environment specifically needs, you might prepare an optional file named '`atlocal.in`', instantiated by `AC_CONFIG_FILES`. The configuration process produces '`atconfig`' and '`atlocal`' out of these two input files, and these two produced files are automatically read by the '`testsuite`' script.

Here is a diagram showing the relationship between files.

Files used in preparing a software package for distribution:



Files used in configuring a software package:



Files created during the test suite execution:



18.1.2 Autotest Logs

When run, the test suite creates a log file named after itself, e.g., a test suite named `testsuite` creates '`testsuite.log`'. It contains a lot of information, usually more than maintainers actually need, but therefore most of the time it contains all that is needed:

command line arguments
: A bad but unfortunately widespread habit consists of setting environment variables before the command, such as in '`CC=my-home-grown-cc ./testsuite`'. The test suite does not know this change, hence (i) it cannot report it to you, and (ii) it cannot preserve the value of `CC` for subsequent runs. Autoconf faced exactly the same problem, and solved it by asking users to pass the variable definitions as command line arguments. Autotest requires this rule, too, but has no means to enforce it; the log then contains a trace of the variables that were changed by the user.

'`ChangeLog`' excerpts
: The topmost lines of all the '`ChangeLog`' files found in the source hierarchy. This is especially useful when bugs are reported against development versions of the package, since the version string does not provide sufficient information to know the exact state of the sources the user compiled. Of course, this relies on the use of a '`ChangeLog`'.

build machine
: Running a test suite in a cross-compile environment is not an easy task, since it would mean having the test suite run on a machine *build*, while running programs on a machine *host*. It is much simpler to run both the test suite and the programs on *host*, but then, from the point of view of the test suite, there remains a single environment, *host* = *build*. The log contains relevant information on the state of the build machine, including some important environment variables.

tested programs
: The absolute file name and answers to '`--version`' of the tested programs (see Section 18.2 [Writing testsuite.at], page 231, `AT_TESTED`).

configuration log
: The contents of '`config.log`', as created by `configure`, are appended. It contains the configuration flags and a detailed report on the configuration itself.

18.2 Writing '`testsuite.at`'

The '`testsuite.at`' is a Bourne shell script making use of special Autotest M4 macros. It often contains a call to `AT_INIT` near its beginning followed by one call to `m4_include` per

source file for tests. Each such included file, or the remainder of '`testsuite.at`' if include files are not used, contain a sequence of test groups. Each test group begins with a call to `AT_SETUP`, then an arbitrary number of shell commands or calls to `AT_CHECK`, and then completes with a call to `AT_CLEANUP`.

`AT_INIT` ([*name*]) [Macro]
Initialize Autotest. Giving a *name* to the test suite is encouraged if your package includes several test suites. In any case, the test suite always displays the package name and version. It also inherits the package bug report address.

`AT_COPYRIGHT` (*copyright-notice*) [Macro]
State that, in addition to the Free Software Foundation's copyright on the Autotest macros, parts of your test suite are covered by *copyright-notice*.

The *copyright-notice* shows up in both the head of `testsuite` and in '`testsuite --version`'.

`AT_TESTED` (*executables*) [Macro]
Log the file name and answer to '`--version`' of each program in space-separated list *executables*. Several invocations register new executables, in other words, don't fear registering one program several times.

Autotest test suites rely on `PATH` to find the tested program. This avoids the need to generate absolute names of the various tools, and makes it possible to test installed programs. Therefore, knowing which programs are being exercised is crucial to understanding problems in the test suite itself, or its occasional misuses. It is a good idea to also subscribe foreign programs you depend upon, to avoid incompatible diagnostics.

`AT_SETUP` (*test-group-name*) [Macro]
This macro starts a group of related tests, all to be executed in the same subshell. It accepts a single argument, which holds a few words (no more than about 30 or 40 characters) quickly describing the purpose of the test group being started.

`AT_KEYWORDS` (*keywords*) [Macro]
Associate the space-separated list of *keywords* to the enclosing test group. This makes it possible to run "slices" of the test suite. For instance, if some of your test groups exercise some '`foo`' feature, then using '`AT_KEYWORDS(foo)`' lets you run '`./testsuite -k foo`' to run exclusively these test groups. The *title* of the test group is automatically recorded to `AT_KEYWORDS`.

Several invocations within a test group accumulate new keywords. In other words, don't fear registering the same keyword several times in a test group.

`AT_CAPTURE_FILE` (*file*) [Macro]
If the current test group fails, log the contents of *file*. Several identical calls within one test group have no additional effect.

`AT_XFAIL_IF` (*shell-condition*) [Macro]
Determine whether the test is expected to fail because it is a known bug (for unsupported features, you should skip the test). *shell-condition* is a shell expression such as

a `test` command; you can instantiate this macro many times from within the same test group, and one of the conditions is enough to turn the test into an expected failure.

`AT_CLEANUP` [Macro]
End the current test group.

`AT_DATA (`*`file`*`, `*`contents`*`)` [Macro]
Initialize an input data *file* with given *contents*. Of course, the *contents* have to be properly quoted between square brackets to protect against included commas or spurious M4 expansion. The contents ought to end with an end of line.

`AT_CHECK (`*`commands`*`, [`*`status`* = '0'], [*`stdout`* = ''], [*`stderr`* = ''], [*`run-if-fail`*], [*`run-if-pass`*])` [Macro]
Execute a test by performing given shell *commands*. These commands should normally exit with *status*, while producing expected *stdout* and *stderr* contents. If *commands* exit with status 77, then the whole test group is skipped. Otherwise, if this test fails, run shell commands *run-if-fail* or, if this test passes, run shell commands *run-if-pass*.

The *commands must not* redirect the standard output, nor the standard error.

If *status*, or *stdout*, or *stderr* is '`ignore`', then the corresponding value is not checked.

The special value '`expout`' for *stdout* means the expected output of the *commands* is the content of the file '`expout`'. If *stdout* is '`stdout`', then the standard output of the *commands* is available for further tests in the file '`stdout`'. Similarly for *stderr* with '`expout`' and '`stderr`'.

18.3 Running `testsuite` Scripts

Autotest test suites support the following arguments:

'`--help`'
'`-h`' Display the list of options and exit successfully.

'`--version`'
'`-V`' Display the version of the test suite and exit successfully.

'`--clean`'
'`-c`' Remove all the files the test suite might have created and exit. Meant for `clean` Make targets.

'`--list`'
'`-l`' List all the tests (or only the selection), including their possible keywords.

By default all tests are performed (or described with '`--list`') in the default environment first silently, then verbosely, but the environment, set of tests, and verbosity level can be tuned:

'*`variable=value`*'
Set the environment *variable* to *value*. Use this rather than '`FOO=foo ./testsuite`' as debugging scripts would then run in a different environment.

The variable `AUTOTEST_PATH` specifies the testing path to prepend to `PATH`. Relative directory names (not starting with '`/`') are considered to be relative to the top level of the package being built. All directories are made absolute, first starting from the top level *build* tree, then from the *source* tree. For instance '`./testsuite AUTOTEST_PATH=tests:bin`' for a '`/src/foo-1.0`' source package built in '`/tmp/foo`' results in '`/tmp/foo/tests:/tmp/foo/bin`' and then '`/src/foo-1.0/tests:/src/foo-1.0/bin`' being prepended to `PATH`.

'*number*'
'*number-number*'
'*number-*'
'*-number*' Add the corresponding test groups, with obvious semantics, to the selection.

'`--keywords=`*keywords*'
'`-k` *keywords*'
Add to the selection the test groups with title or keywords (arguments to `AT_SETUP` or `AT_KEYWORDS`) that match *all* keywords of the comma separated list *keywords*, case-insensitively. Use '`!`' immediately before the keyword to invert the selection for this keyword. By default, the keywords match whole words; enclose them in '`.*`' to also match parts of words.

For example, running

```
./testsuite -k 'autoupdate,.*FUNC.*'
```

selects all tests tagged '`autoupdate`' *and* with tags containing '`FUNC`' (as in '`AC_CHECK_FUNC`', '`AC_FUNC_FNMATCH`', etc.), while

```
./testsuite -k '!autoupdate' -k '.*FUNC.*'
```

selects all tests not tagged '`autoupdate`' *or* with tags containing '`FUNC`'.

'`--errexit`'
'`-e`' If any test fails, immediately abort testing. It implies '`--debug`': post test group clean up, and top-level logging are inhibited. This option is meant for the full test suite, it is not really useful for generated debugging scripts.

'`--verbose`'
'`-v`' Force more verbosity in the detailed output of what is being done. This is the default for debugging scripts.

'`--debug`'
'`-d`' Do not remove the files after a test group was performed —but they are still removed *before*, therefore using this option is sane when running several test groups. Create debugging scripts. Do not overwrite the top-level log (in order to preserve supposedly existing full log file). This is the default for debugging scripts, but it can also be useful to debug the testsuite itself.

'`--trace`'
'`-x`' Trigger shell tracing of the test groups.

18.4 Making `testsuite` Scripts

For putting Autotest into movement, you need some configuration and makefile machinery. We recommend, at least if your package uses deep or shallow hierarchies, that you use

'`tests/`' as the name of the directory holding all your tests and their makefile. Here is a check list of things to do.

- Make sure to create the file '`package.m4`', which defines the identity of the package. It must define `AT_PACKAGE_STRING`, the full signature of the package, and `AT_PACKAGE_BUGREPORT`, the address to which bug reports should be sent. For sake of completeness, we suggest that you also define `AT_PACKAGE_NAME`, `AT_PACKAGE_TARNAME`, and `AT_PACKAGE_VERSION`. See Section 4.1 [Initializing configure], page 17, for a description of these variables. We suggest the following makefile excerpt:

```
$(srcdir)/package.m4: $(top_srcdir)/configure.ac
        {                                       \
          echo '# Signature of the current package.'; \
          echo 'm4_define([AT_PACKAGE_NAME],      [@PACKAGE_NAME@])'; \
          echo 'm4_define([AT_PACKAGE_TARNAME],   [@PACKAGE_TARNAME@])'; \
          echo 'm4_define([AT_PACKAGE_VERSION],   [@PACKAGE_VERSION@])'; \
          echo 'm4_define([AT_PACKAGE_STRING],    [@PACKAGE_STRING@])'; \
          echo 'm4_define([AT_PACKAGE_BUGREPORT], [@PACKAGE_BUGREPORT@])'; \
        } >'$(srcdir)/package.m4'
```

  Be sure to distribute '`package.m4`' and to put it into the source hierarchy: the test suite ought to be shipped!

- Invoke `AC_CONFIG_TESTDIR`.

  `AC_CONFIG_TESTDIR` (*directory*, [*test-path* = '`directory`']) [Macro]
  An Autotest test suite is to be configured in *directory*. This macro requires the instantiation of '*directory*`/atconfig`' from '*directory*`/atconfig.in`', and sets the default `AUTOTEST_PATH` to *test-path* (see Section 18.3 [testsuite Invocation], page 233).

- Still within '`configure.ac`', as appropriate, ensure that some `AC_CONFIG_FILES` command includes substitution for '`tests/atlocal`'.
- The '`tests/Makefile.in`' should be modified so the validation in your package is triggered by '`make check`'. An example is provided below.

With Automake, here is a minimal example about how to link '`make check`' with a validation suite.

```
EXTRA_DIST = testsuite.at $(TESTSUITE) atlocal.in
TESTSUITE = $(srcdir)/testsuite

check-local: atconfig atlocal $(TESTSUITE)
        $(SHELL) '$(TESTSUITE)' $(TESTSUITEFLAGS)

installcheck-local: atconfig atlocal $(TESTSUITE)
        $(SHELL) '$(TESTSUITE)' AUTOTEST_PATH='$(bindir)' \
          $(TESTSUITEFLAGS)

clean-local:
        test ! -f '$(TESTSUITE)' || \
         $(SHELL) '$(TESTSUITE)' --clean

AUTOTEST = $(AUTOM4TE) --language=autotest
```

```
$(TESTSUITE): $(srcdir)/testsuite.at
        $(AUTOTEST) -I '$(srcdir)' -o $@.tmp $@.at
        mv $@.tmp $@
```

You might want to list explicitly the dependencies, i.e., the list of the files '`testsuite.at`' includes.

With strict Autoconf, you might need to add lines inspired from the following:

```
subdir = tests

atconfig: $(top_builddir)/config.status
        cd $(top_builddir) && \
           $(SHELL) ./config.status $(subdir)/$@

atlocal: $(srcdir)/atlocal.in $(top_builddir)/config.status
        cd $(top_builddir) && \
           $(SHELL) ./config.status $(subdir)/$@
```

and manage to have '`atconfig.in`' and `$(EXTRA_DIST)` distributed.

With all this in place, and if you have not initialized '`TESTSUITEFLAGS`' within your makefile, you can fine-tune test suite execution with this variable, for example:

```
make check TESTSUITEFLAGS='-v -d -x 75 -k AC_PROG_CC CFLAGS=-g'
```

19 Frequent Autoconf Questions, with answers

Several questions about Autoconf come up occasionally. Here some of them are addressed.

19.1 Distributing `configure` Scripts

> What are the restrictions on distributing `configure` scripts that Autoconf generates? How does that affect my programs that use them?

There are no restrictions on how the configuration scripts that Autoconf produces may be distributed or used. In Autoconf version 1, they were covered by the GNU General Public License. We still encourage software authors to distribute their work under terms like those of the GPL, but doing so is not required to use Autoconf.

Of the other files that might be used with `configure`, '`config.h.in`' is under whatever copyright you use for your '`configure.ac`'. '`config.sub`' and '`config.guess`' have an exception to the GPL when they are used with an Autoconf-generated `configure` script, which permits you to distribute them under the same terms as the rest of your package. '`install-sh`' is from the X Consortium and is not copyrighted.

19.2 Why Require GNU M4?

> Why does Autoconf require GNU M4?

Many M4 implementations have hard-coded limitations on the size and number of macros that Autoconf exceeds. They also lack several builtin macros that it would be difficult to get along without in a sophisticated application like Autoconf, including:

```
m4_builtin
m4_indir
m4_bpatsubst
__file__
__line__
```

Autoconf requires version 1.4.4 or later of GNU M4.

Since only software maintainers need to use Autoconf, and since GNU M4 is simple to configure and install, it seems reasonable to require GNU M4 to be installed also. Many maintainers of GNU and other free software already have most of the GNU utilities installed, since they prefer them.

19.3 How Can I Bootstrap?

> If Autoconf requires GNU M4 and GNU M4 has an Autoconf `configure` script, how do I bootstrap? It seems like a chicken and egg problem!

This is a misunderstanding. Although GNU M4 does come with a `configure` script produced by Autoconf, Autoconf is not required in order to run the script and install GNU M4. Autoconf is only required if you want to change the M4 `configure` script, which few people have to do (mainly its maintainer).

19.4 Why Not Imake?

Why not use Imake instead of `configure` scripts?

Several people have written addressing this question, so I include adaptations of their explanations here.

The following answer is based on one written by Richard Pixley:

> Autoconf generated scripts frequently work on machines that it has never been set up to handle before. That is, it does a good job of inferring a configuration for a new system. Imake cannot do this.
>
> Imake uses a common database of host specific data. For X11, this makes sense because the distribution is made as a collection of tools, by one central authority who has control over the database.
>
> GNU tools are not released this way. Each GNU tool has a maintainer; these maintainers are scattered across the world. Using a common database would be a maintenance nightmare. Autoconf may appear to be this kind of database, but in fact it is not. Instead of listing host dependencies, it lists program requirements.
>
> If you view the GNU suite as a collection of native tools, then the problems are similar. But the GNU development tools can be configured as cross tools in almost any host+target permutation. All of these configurations can be installed concurrently. They can even be configured to share host independent files across hosts. Imake doesn't address these issues.
>
> Imake templates are a form of standardization. The GNU coding standards address the same issues without necessarily imposing the same restrictions.

Here is some further explanation, written by Per Bothner:

> One of the advantages of Imake is that it easy to generate large makefiles using the '`#include`' and macro mechanisms of `cpp`. However, `cpp` is not programmable: it has limited conditional facilities, and no looping. And `cpp` cannot inspect its environment.
>
> All of these problems are solved by using `sh` instead of `cpp`. The shell is fully programmable, has macro substitution, can execute (or source) other shell scripts, and can inspect its environment.

Paul Eggert elaborates more:

> With Autoconf, installers need not assume that Imake itself is already installed and working well. This may not seem like much of an advantage to people who are accustomed to Imake. But on many hosts Imake is not installed or the default installation is not working well, and requiring Imake to install a package hinders the acceptance of that package on those hosts. For example, the Imake template and configuration files might not be installed properly on a host, or the Imake build procedure might wrongly assume that all source files are in one big directory tree, or the Imake configuration might assume one compiler whereas the package or the installer needs to use another, or there might be a version mismatch between the Imake expected by the package and the Imake supported by the host. These problems are much rarer with Autoconf, where each package comes with its own independent configuration processor.

> Also, Imake often suffers from unexpected interactions between `make` and the installer's C preprocessor. The fundamental problem here is that the C preprocessor was designed to preprocess C programs, not makefiles. This is much less of a problem with Autoconf, which uses the general-purpose preprocessor M4, and where the package's author (rather than the installer) does the preprocessing in a standard way.

Finally, Mark Eichin notes:

> Imake isn't all that extensible, either. In order to add new features to Imake, you need to provide your own project template, and duplicate most of the features of the existing one. This means that for a sophisticated project, using the vendor-provided Imake templates fails to provide any leverage—since they don't cover anything that your own project needs (unless it is an X11 program).
>
> On the other side, though:
>
> The one advantage that Imake has over `configure`: '`Imakefile`' files tend to be much shorter (likewise, less redundant) than '`Makefile.in`' files. There is a fix to this, however—at least for the Kerberos V5 tree, we've modified things to call in common '`post.in`' and '`pre.in`' makefile fragments for the entire tree. This means that a lot of common things don't have to be duplicated, even though they normally are in `configure` setups.

19.5 How Do I `#define` Installation Directories?

> My program needs library files, installed in `datadir` and similar. If I use
>
> ```
> AC_DEFINE_UNQUOTED([DATADIR], [$datadir],
>   [Define to the read-only architecture-independent
>    data directory.])
> ```
>
> I get
>
> ```
> #define DATADIR "${prefix}/share"
> ```

As already explained, this behavior is on purpose, mandated by the GNU Coding Standards, see Section 4.7.2 [Installation Directory Variables], page 25. There are several means to achieve a similar goal:

- Do not use `AC_DEFINE` but use your makefile to pass the actual value of `datadir` via compilation flags. See Section 4.7.2 [Installation Directory Variables], page 25, for the details.
- This solution can be simplified when compiling a program: you may either extend the `CPPFLAGS`:

  ```
  CPPFLAGS = -DDATADIR='"$(datadir)"' @CPPFLAGS@
  ```

  or create a dedicated header file:

  ```
  DISTCLEANFILES = datadir.h
  datadir.h: Makefile
  ```

```
echo '#define DATADIR "$(datadir)"' >$@
```

– Use `AC_DEFINE` but have `configure` compute the literal value of `datadir` and others. Many people have wrapped macros to automate this task. For instance, the macro `AC_DEFINE_DIR` from the Autoconf Macro Archive (`http://autoconf-archive.cryp.to/`).

  This solution does not conform to the GNU Coding Standards.

– Note that all the previous solutions hard wire the absolute name of these directories in the executables, which is not a good property. You may try to compute the names relative to `prefix`, and try to find `prefix` at runtime, this way your package is relocatable. Some macros are already available to address this issue: see `adl_COMPUTE_RELATIVE_PATHS` and `adl_COMPUTE_STANDARD_RELATIVE_PATHS` on the Autoconf Macro Archive (`http://autoconf-archive.cryp.to/`).

19.6 What is 'autom4te.cache'?

What is this directory '`autom4te.cache`'? Can I safely remove it?

In the GNU Build System, '`configure.ac`' plays a central role and is read by many tools: `autoconf` to create '`configure`', `autoheader` to create '`config.h.in`', `automake` to create '`Makefile.in`', `autoscan` to check the completeness of '`configure.ac`', `autoreconf` to check the GNU Build System components that are used. To "read '`configure.ac`'" actually means to compile it with M4, which can be a long process for complex '`configure.ac`'.

This is why all these tools, instead of running directly M4, invoke `autom4te` (see Section 8.2.1 [autom4te Invocation], page 113) which, while answering to a specific demand, stores additional information in '`autom4te.cache`' for future runs. For instance, if you run `autoconf`, behind the scenes, `autom4te` also stores information for the other tools, so that when you invoke `autoheader` or `automake` etc., reprocessing '`configure.ac`' is not needed. The speed up is frequently of 30%, and is increasing with the size of '`configure.ac`'.

But it is and remains being simply a cache: you can safely remove it.

Can I permanently get rid of it?

The creation of this cache can be disabled from '`~/.autom4te.cfg`', see Section 8.2.2 [Customizing autom4te], page 117, for more details. You should be aware that disabling the cache slows down the Autoconf test suite by 40%. The more GNU Build System components are used, the more the cache is useful; for instance running '`autoreconf -f`' on the Core Utilities is twice slower without the cache *although '`--force`' implies that the cache is not fully exploited*, and eight times slower than without '`--force`'.

19.7 Header Present But Cannot Be Compiled

The most important guideline to bear in mind when checking for features is to mimic as much as possible the intended use. Unfortunately, old versions of `AC_CHECK_HEADER` and `AC_CHECK_HEADERS` failed to follow this idea, and called the preprocessor, instead of the compiler, to check for headers. As a result, incompatibilities between headers went unnoticed during configuration, and maintainers finally had to deal with this issue elsewhere.

As of Autoconf 2.56 both checks are performed, and `configure` complains loudly if the compiler and the preprocessor do not agree. For the time being the result used is that of the

preprocessor, to give maintainers time to adjust their '`configure.ac`', but in the future, only the compiler will be considered.

Consider the following example:

```
$ cat number.h
typedef int number;
$ cat pi.h
const number pi = 3;
$ cat configure.ac
AC_INIT([Example], [1.0], [bug-example@example.org])
AC_CHECK_HEADERS([pi.h])
$ autoconf -Wall
$ ./configure
checking for gcc... gcc
checking for C compiler default output file name... a.out
checking whether the C compiler works... yes
checking whether we are cross compiling... no
checking for suffix of executables...
checking for suffix of object files... o
checking whether we are using the GNU C compiler... yes
checking whether gcc accepts -g... yes
checking for gcc option to accept ISO C89... none needed
checking how to run the C preprocessor... gcc -E
checking for grep that handles long lines and -e... grep
checking for egrep... grep -E
checking for ANSI C header files... yes
checking for sys/types.h... yes
checking for sys/stat.h... yes
checking for stdlib.h... yes
checking for string.h... yes
checking for memory.h... yes
checking for strings.h... yes
checking for inttypes.h... yes
checking for stdint.h... yes
checking for unistd.h... yes
checking pi.h usability... no
checking pi.h presence... yes
configure: WARNING: pi.h: present but cannot be compiled
configure: WARNING: pi.h:     check for missing prerequisite headers?
configure: WARNING: pi.h: see the Autoconf documentation
configure: WARNING: pi.h:     section "Present But Cannot Be Compiled"
configure: WARNING: pi.h: proceeding with the preprocessor's result
configure: WARNING: pi.h: in the future, the compiler will take precedence
configure: WARNING:     ## ------------------------------------- ##
configure: WARNING:     ## Report this to bug-example@example.org ##
configure: WARNING:     ## ------------------------------------- ##
checking for pi.h... yes
```

The proper way the handle this case is using the fourth argument (see Section 5.6.3 [Generic Headers], page 64):

```
$ cat configure.ac
AC_INIT([Example], [1.0], [bug-example@example.org])
AC_CHECK_HEADERS([number.h pi.h], [], [],
[[#if HAVE_NUMBER_H
# include <number.h>
#endif
]])
```

```
$ autoconf -Wall
$ ./configure
checking for gcc... gcc
checking for C compiler default output... a.out
checking whether the C compiler works... yes
checking whether we are cross compiling... no
checking for suffix of executables...
checking for suffix of object files... o
checking whether we are using the GNU C compiler... yes
checking whether gcc accepts -g... yes
checking for gcc option to accept ANSI C... none needed
checking for number.h... yes
checking for pi.h... yes
```

See Section 5.6.2 [Particular Headers], page 59, for a list of headers with their prerequisite.

20 History of Autoconf

You may be wondering, Why was Autoconf originally written? How did it get into its present form? (Why does it look like gorilla spit?) If you're not wondering, then this chapter contains no information useful to you, and you might as well skip it. If you *are* wondering, then let there be light...

20.1 Genesis

In June 1991 I was maintaining many of the GNU utilities for the Free Software Foundation. As they were ported to more platforms and more programs were added, the number of '`-D`' options that users had to select in the makefile (around 20) became burdensome. Especially for me—I had to test each new release on a bunch of different systems. So I wrote a little shell script to guess some of the correct settings for the fileutils package, and released it as part of fileutils 2.0. That `configure` script worked well enough that the next month I adapted it (by hand) to create similar `configure` scripts for several other GNU utilities packages. Brian Berliner also adapted one of my scripts for his CVS revision control system.

Later that summer, I learned that Richard Stallman and Richard Pixley were developing similar scripts to use in the GNU compiler tools; so I adapted my `configure` scripts to support their evolving interface: using the file name '`Makefile.in`' as the templates; adding '`+srcdir`', the first option (of many); and creating '`config.status`' files.

20.2 Exodus

As I got feedback from users, I incorporated many improvements, using Emacs to search and replace, cut and paste, similar changes in each of the scripts. As I adapted more GNU utilities packages to use `configure` scripts, updating them all by hand became impractical. Rich Murphey, the maintainer of the GNU graphics utilities, sent me mail saying that the `configure` scripts were great, and asking if I had a tool for generating them that I could send him. No, I thought, but I should! So I started to work out how to generate them. And the journey from the slavery of hand-written `configure` scripts to the abundance and ease of Autoconf began.

Cygnus `configure`, which was being developed at around that time, is table driven; it is meant to deal mainly with a discrete number of system types with a small number of mainly unguessable features (such as details of the object file format). The automatic configuration system that Brian Fox had developed for Bash takes a similar approach. For general use, it seems to me a hopeless cause to try to maintain an up-to-date database of which features each variant of each operating system has. It's easier and more reliable to check for most features on the fly—especially on hybrid systems that people have hacked on locally or that have patches from vendors installed.

I considered using an architecture similar to that of Cygnus `configure`, where there is a single `configure` script that reads pieces of '`configure.in`' when run. But I didn't want to have to distribute all of the feature tests with every package, so I settled on having a different `configure` made from each '`configure.in`' by a preprocessor. That approach also offered more control and flexibility.

I looked briefly into using the Metaconfig package, by Larry Wall, Harlan Stenn, and Raphael Manfredi, but I decided not to for several reasons. The `Configure` scripts it

produces are interactive, which I find quite inconvenient; I didn't like the ways it checked for some features (such as library functions); I didn't know that it was still being maintained, and the `Configure` scripts I had seen didn't work on many modern systems (such as System V R4 and NeXT); it wasn't flexible in what it could do in response to a feature's presence or absence; I found it confusing to learn; and it was too big and complex for my needs (I didn't realize then how much Autoconf would eventually have to grow).

I considered using Perl to generate my style of `configure` scripts, but decided that M4 was better suited to the job of simple textual substitutions: it gets in the way less, because output is implicit. Plus, everyone already has it. (Initially I didn't rely on the GNU extensions to M4.) Also, some of my friends at the University of Maryland had recently been putting M4 front ends on several programs, including `tvtwm`, and I was interested in trying out a new language.

20.3 Leviticus

Since my `configure` scripts determine the system's capabilities automatically, with no interactive user intervention, I decided to call the program that generates them Autoconfig. But with a version number tacked on, that name would be too long for old Unix file systems, so I shortened it to Autoconf.

In the fall of 1991 I called together a group of fellow questers after the Holy Grail of portability (er, that is, alpha testers) to give me feedback as I encapsulated pieces of my handwritten scripts in M4 macros and continued to add features and improve the techniques used in the checks. Prominent among the testers were François Pinard, who came up with the idea of making an Autoconf shell script to run M4 and check for unresolved macro calls; Richard Pixley, who suggested running the compiler instead of searching the file system to find include files and symbols, for more accurate results; Karl Berry, who got Autoconf to configure TEX and added the macro index to the documentation; and Ian Lance Taylor, who added support for creating a C header file as an alternative to putting '`-D`' options in a makefile, so he could use Autoconf for his UUCP package. The alpha testers cheerfully adjusted their files again and again as the names and calling conventions of the Autoconf macros changed from release to release. They all contributed many specific checks, great ideas, and bug fixes.

20.4 Numbers

In July 1992, after months of alpha testing, I released Autoconf 1.0, and converted many GNU packages to use it. I was surprised by how positive the reaction to it was. More people started using it than I could keep track of, including people working on software that wasn't part of the GNU Project (such as TCL, FSP, and Kerberos V5). Autoconf continued to improve rapidly, as many people using the `configure` scripts reported problems they encountered.

Autoconf turned out to be a good torture test for M4 implementations. Unix M4 started to dump core because of the length of the macros that Autoconf defined, and several bugs showed up in GNU M4 as well. Eventually, we realized that we needed to use some features that only GNU M4 has. 4.3BSD M4, in particular, has an impoverished set of builtin macros; the System V version is better, but still doesn't provide everything we need.

More development occurred as people put Autoconf under more stresses (and to uses I hadn't anticipated). Karl Berry added checks for X11. david zuhn contributed C++ support. François Pinard made it diagnose invalid arguments. Jim Blandy bravely coerced it into configuring GNU Emacs, laying the groundwork for several later improvements. Roland McGrath got it to configure the GNU C Library, wrote the `autoheader` script to automate the creation of C header file templates, and added a '`--verbose`' option to `configure`. Noah Friedman added the '`--autoconf-dir`' option and `AC_MACRODIR` environment variable. (He also coined the term *autoconfiscate* to mean "adapt a software package to use Autoconf".) Roland and Noah improved the quoting protection in `AC_DEFINE` and fixed many bugs, especially when I got sick of dealing with portability problems from February through June, 1993.

20.5 Deuteronomy

A long wish list for major features had accumulated, and the effect of several years of patching by various people had left some residual cruft. In April 1994, while working for Cygnus Support, I began a major revision of Autoconf. I added most of the features of the Cygnus `configure` that Autoconf had lacked, largely by adapting the relevant parts of Cygnus `configure` with the help of david zuhn and Ken Raeburn. These features include support for using '`config.sub`', '`config.guess`', '`--host`', and '`--target`'; making links to files; and running `configure` scripts in subdirectories. Adding these features enabled Ken to convert GNU `as`, and Rob Savoye to convert DejaGNU, to using Autoconf.

I added more features in response to other peoples' requests. Many people had asked for `configure` scripts to share the results of the checks between runs, because (particularly when configuring a large source tree, like Cygnus does) they were frustratingly slow. Mike Haertel suggested adding site-specific initialization scripts. People distributing software that had to unpack on MS-DOS asked for a way to override the '`.in`' extension on the file names, which produced file names like '`config.h.in`' containing two dots. Jim Avera did an extensive examination of the problems with quoting in `AC_DEFINE` and `AC_SUBST`; his insights led to significant improvements. Richard Stallman asked that compiler output be sent to '`config.log`' instead of '`/dev/null`', to help people debug the Emacs `configure` script.

I made some other changes because of my dissatisfaction with the quality of the program. I made the messages showing results of the checks less ambiguous, always printing a result. I regularized the names of the macros and cleaned up coding style inconsistencies. I added some auxiliary utilities that I had developed to help convert source code packages to use Autoconf. With the help of François Pinard, I made the macros not interrupt each others' messages. (That feature revealed some performance bottlenecks in GNU M4, which he hastily corrected!) I reorganized the documentation around problems people want to solve. And I began a test suite, because experience had shown that Autoconf has a pronounced tendency to regress when we change it.

Again, several alpha testers gave invaluable feedback, especially François Pinard, Jim Meyering, Karl Berry, Rob Savoye, Ken Raeburn, and Mark Eichin.

Finally, version 2.0 was ready. And there was much rejoicing. (And I have free time again. I think. Yeah, right.)

Appendix A Copying This Manual

A.1 GNU Free Documentation License

Version 1.2, November 2002

Copyright © 2000,2001,2002 Free Software Foundation, Inc.
51 Franklin St, Fifth Floor, Boston, MA 02110-1301, USA

Everyone is permitted to copy and distribute verbatim copies
of this license document, but changing it is not allowed.

0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document *free* in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or non-commercially. Secondarily, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

3. COPYING IN QUANTITY

   If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

   If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

   If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

   It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

4. MODIFICATIONS

   You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

   A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any,

be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.

B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.

C. State on the Title page the name of the publisher of the Modified Version, as the publisher.

D. Preserve all the copyright notices of the Document.

E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.

F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.

G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.

H. Include an unaltered copy of this License.

I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.

J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.

K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.

L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.

M. Delete any section Entitled "Endorsements". Such a section may not be included in the Modified Version.

N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.

O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their

titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

5. COMBINING DOCUMENTS

   You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

   The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

   In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements."

6. COLLECTIONS OF DOCUMENTS

   You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

   You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

7. AGGREGATION WITH INDEPENDENT WORKS

   A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

   If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

8. TRANSLATION

   Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

   If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

9. TERMINATION

   You may not copy, modify, sublicense, or distribute the Document except as expressly provided for under this License. Any other attempt to copy, modify, sublicense or distribute the Document is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.

10. FUTURE REVISIONS OF THIS LICENSE

    The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See `http://www.gnu.org/copyleft/`.

    Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation.

A.1.1 ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

```
Copyright (C)  year  your name.
Permission is granted to copy, distribute and/or modify this document
under the terms of the GNU Free Documentation License, Version 1.2
or any later version published by the Free Software Foundation;
with no Invariant Sections, no Front-Cover Texts, and no Back-Cover
Texts.  A copy of the license is included in the section entitled ``GNU
Free Documentation License''.
```

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with...Texts." line with this:

```
with the Invariant Sections being list their titles, with
the Front-Cover Texts being list, and with the Back-Cover Texts
being list.
```

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.

Appendix B Indices

B.1 Environment Variable Index

This is an alphabetical list of the environment variables that Autoconf checks.

B

BIN_SH ... 145

C

CDPATH ... 145
CONFIG_COMMANDS ... 207
CONFIG_FILES ... 207
CONFIG_HEADERS ... 207
CONFIG_LINKS ... 207
CONFIG_SHELL ... 206
CONFIG_SITE ... 199
CONFIG_STATUS ... 206

D

DUALCASE ... 146

E

ENV ... 146

I

IFS ... 146

L

LANG ... 147
LANGUAGE ... 147
LC_ADDRESS ... 147
LC_ALL ... 147
LC_COLLATE ... 147
LC_CTYPE ... 147
LC_IDENTIFICATION ... 147
LC_MEASUREMENT ... 147
LC_MESSAGES ... 147
LC_MONETARY ... 147
LC_NAME ... 147
LC_NUMERIC ... 147
LC_PAPER ... 147
LC_TELEPHONE ... 147
LC_TIME ... 147

M

M4 ... 113
MAIL ... 146
MAILPATH ... 146

N

NULLCMD ... 149

P

PATH_SEPARATOR ... 149
PS1 ... 146
PS2 ... 146
PS4 ... 146
PWD ... 149

S

SIMPLE_BACKUP_SUFFIX ... 208

W

WARNINGS ... 13, 16, 34, 114

X

XMKMF ... 83

B.2 Output Variable Index

This is an alphabetical list of the variables that Autoconf can substitute into files that it creates, typically one or more makefiles. See Section 7.2 [Setting Output Variables], page 100, for more information on how this is done.

A

abs_builddir ... 24
abs_srcdir ... 25
abs_top_builddir ... 25
abs_top_srcdir ... 25
ALLOCA ... 50
AWK ... 41

B

bindir 25
build 190
build_alias 190
build_cpu 190
build_os 190
build_vendor 190
builddir 24

C

CC 73, 76, 83
CFLAGS 23, 73
configure_input 23
CPP 73
CPPFLAGS 23
cross_compiling 95
CXX 76
CXXCPP 77
CXXFLAGS 23, 76

D

datadir 25
datarootdir 25
DEFS 23
docdir 25
dvidir 25

E

ECHO_C 24
ECHO_N 24
ECHO_T 24
EGREP 41
ERL 78, 88, 94
ERLANG_INSTALL_LIB_DIR 28, 85
ERLANG_INSTALL_LIB_DIR_*library* 28, 85
ERLANG_LIB_DIR 84
ERLANG_LIB_DIR_*library* 85
ERLANG_ROOT_DIR 84
ERLC 77, 88
ERLCFLAGS 24, 77, 88
exec_prefix 25
EXEEXT 70, 211

F

F77 78
FC 78
FCFLAGS 24, 78
FCLIBS 79
FFLAGS 24, 78
FGREP 41
FLIBS 79

G

GETGROUPS_LIBS 51
GETLOADAVG_LIBS 52
GREP 41

H

host 190
host_alias 190
host_cpu 190
host_os 190
host_vendor 190
htmldir 25

I

includedir 25
infodir 26
INSTALL 41
INSTALL_DATA 41
INSTALL_PROGRAM 41
INSTALL_SCRIPT 41

K

KMEM_GROUP 52

L

LDFLAGS 24
LEX 42
LEX_OUTPUT_ROOT 42
LEXLIB 42
libdir 26
libexecdir 26
LIBOBJDIR 226
LIBOBJS 52, 53, 56, 57, 67
LIBS 24, 84, 216, 219
LN_S 43
localedir 26
localstatedir 26

M

mandir 26
MKDIR_P 42

N

NEED_SETGID 52

O

OBJC 77
OBJCCPP 77
OBJCFLAGS 24, 77
OBJEXT 70, 214
oldincludedir 26

P

PACKAGE_BUGREPORT 17
PACKAGE_NAME 17
PACKAGE_STRING 17
PACKAGE_TARNAME 17
PACKAGE_VERSION 17
pdfdir 26
POW_LIB 55
prefix 26
program_transform_name 198
psdir 26

R

RANLIB 43

S

sbindir 26
SED 43
SET_MAKE 20
sharedstatedir 26
srcdir 25
subdirs 36
sysconfdir 26

T

target 190
target_alias 190
target_cpu 190
target_os 190
target_vendor 190
top_builddir 25
top_srcdir 25

X

X_CFLAGS 83
X_EXTRA_LIBS 83
X_LIBS 83
X_PRE_LIBS 83

Y

YACC 43

B.3 Preprocessor Symbol Index

This is an alphabetical list of the C preprocessor symbols that the Autoconf macros define. To work with Autoconf, C source code needs to use these names in `#if` directives.

_

__CHAR_UNSIGNED__ 76
__EXTENSIONS__ 84
__PROTOTYPES 76
_ALL_SOURCE 84
_FILE_OFFSET_BITS 83
_GNU_SOURCE 84
_LARGE_FILES 83
_LARGEFILE_SOURCE 51
_MINIX 84
_POSIX_1_SOURCE 84
_POSIX_PTHREAD_SEMANTICS 84
_POSIX_SOURCE 84
_POSIX_VERSION 63

C

C_ALLOCA 50
C_GETLOADAVG 52
CLOSEDIR_VOID 50
const 75
CXX_NO_MINUS_C_MINUS_O 77

D

DGUX 52
DIRENT 211

F

F77_DUMMY_MAIN 80
F77_FUNC 80
F77_FUNC_ 80
F77_MAIN 80
F77_NO_MINUS_C_MINUS_O 79
FC_FUNC 80
FC_FUNC_ 80
FC_MAIN 80
FC_NO_MINUS_C_MINUS_O 79

G

GETGROUPS_T 68
GETLODAVG_PRIVILEGED 52
GETPGRP_VOID 52
gid_t 69
GWINSZ_IN_SYS_IOCTL 64

H

HAVE__BOOL 61
HAVE_ALLOCA_H 50
HAVE_CONFIG_H 32
HAVE_DECL_STRERROR_R 55
HAVE_DECL_*symbol* 65, 66
HAVE_DIRENT_H 59

HAVE_DOPRNT 55
HAVE_*function* 56
HAVE_GETMNTENT 52
HAVE_*header* 64, 65
HAVE_INT16_T 68
HAVE_INT32_T 68
HAVE_INT64_T 68
HAVE_INT8_T 68
HAVE_INTMAX_T 68
HAVE_INTPTR_T 68
HAVE_LONG_DOUBLE 69, 209
HAVE_LONG_DOUBLE_WIDER 69
HAVE_LONG_FILE_NAMES 83
HAVE_LONG_LONG_INT 69
HAVE_LSTAT_EMPTY_STRING_BUG 54
HAVE_MALLOC 53
HAVE_MBRTOWC 53
HAVE_MMAP 53
HAVE_NDIR_H 59
HAVE_NLIST_H 52
HAVE_OBSTACK 54
HAVE_REALLOC 54
HAVE_RESOLV_H 60
HAVE_RESTARTABLE_SYSCALLS 217
HAVE_ST_BLKSIZE 67
HAVE_ST_BLOCKS 67
HAVE_ST_RDEV 67
HAVE_STAT_EMPTY_STRING_BUG 54
HAVE_STDBOOL_H 61
HAVE_STRCOLL 54
HAVE_STRERROR_R 55
HAVE_STRFTIME 55
HAVE_STRINGIZE 76
HAVE_STRNLEN 55
HAVE_STRUCT_DIRENT_D_INO 66
HAVE_STRUCT_DIRENT_D_TYPE 67
HAVE_STRUCT_STAT_ST_BLKSIZE 67
HAVE_STRUCT_STAT_ST_BLOCKS 67
HAVE_STRUCT_STAT_ST_RDEV 67
HAVE_SYS_DIR_H 59
HAVE_SYS_NDIR_H 59
HAVE_SYS_WAIT_H 62
HAVE_TM_ZONE 67
HAVE_TYPEOF 76
HAVE_TZNAME 67
HAVE_UINT16_T 69
HAVE_UINT32_T 70
HAVE_UINT64_T 70
HAVE_UINT8_T 69
HAVE_UINTMAX_T 70
HAVE_UINTPTR_T 70
HAVE_UNSIGNED_LONG_LONG_INT 70
HAVE_UTIME_NULL 55
HAVE_VFORK_H 51
HAVE_VPRINTF 55
HAVE_WAIT3 212
HAVE_WORKING_FORK 51
HAVE_WORKING_VFORK 51

I

inline 75
INT_16_BITS 213
int16_t 68
int32_t 68
int64_t 68
int8_t 68
intmax_t 68
intptr_t 68

L

LONG_64_BITS 214
LSTAT_FOLLOWS_SLASHED_SYMLINK 52

M

MAJOR_IN_MKDEV 60
MAJOR_IN_SYSMACROS 60
malloc 53
mbstate_t 69
mode_t 69

N

NDEBUG 59
NDIR 211
NEED_MEMORY_H 214
NEED_SETGID 52
NLIST_NAME_UNION 52
NO_MINUS_C_MINUS_O 73

O

off_t 69

P

PACKAGE_BUGREPORT 17
PACKAGE_NAME 17
PACKAGE_STRING 17
PACKAGE_TARNAME 17
PACKAGE_VERSION 17
PARAMS 76
pid_t 69
PROTOTYPES 76

R

realloc 54
restrict 75
RETSIGTYPE 69

S

SELECT_TYPE_ARG1 54
SELECT_TYPE_ARG234 54

SELECT_TYPE_ARG5 54
SETPGRP_VOID 54
SETVBUF_REVERSED 54
size_t 69
ssize_t 69
STAT_MACROS_BROKEN 61
STDC_HEADERS 61
STRERROR_R_CHAR_P 55
SVR4 52
SYS_SIGLIST_DECLARED 211
SYSDIR 211
SYSNDIR 211

T

TIME_WITH_SYS_TIME 63
TM_IN_SYS_TIME 67
typeof 76

U

uid_t 69
uint16_t 69
uint32_t 70
uint64_t 70
uint8_t 69
uintmax_t 70
uintptr_t 70
UMAX 52
UMAX4_3 52
USG 219

V

vfork 51
volatile 75

W

WORDS_BIGENDIAN 74

X

X_DISPLAY_MISSING 83

Y

YYTEXT_POINTER 42

B.4 Autoconf Macro Index

This is an alphabetical list of the Autoconf macros. To make the list easier to use, the macros are listed without their preceding 'AC_'.

A

AC_PROG_MKDIR_P 42
AH_BOTTOM 35
AH_HEADER 32
AH_TEMPLATE 35
AH_TOP 35
AH_VERBATIM 34
AIX 84
ALLOCA 209
ARG_ARRAY 209
ARG_ENABLE 196
ARG_PROGRAM 198
ARG_VAR 101
ARG_WITH 194
AU_ALIAS 129
AU_DEFUN 129

B

BEFORE 129

C

C_BIGENDIAN 74
C_CHAR_UNSIGNED 76
C_CONST 75
C_CROSS 209
C_INLINE 75
C_LONG_DOUBLE 209
C_PROTOTYPES 76
C_RESTRICT 75
C_STRINGIZE 76
C_TYPEOF 76
C_VOLATILE 75
CACHE_CHECK 103
CACHE_LOAD 105
CACHE_SAVE 105
CACHE_VAL 102
CANONICAL_BUILD 190
CANONICAL_HOST 190
CANONICAL_SYSTEM 209
CANONICAL_TARGET 190
CHAR_UNSIGNED 210
CHECK_ALIGNOF 71
CHECK_DECL 65
CHECK_DECLS 65
CHECK_DECLS_ONCE 66
CHECK_FILE 45
CHECK_FILES 46
CHECK_FUNC 56
CHECK_FUNCS 56
CHECK_FUNCS_ONCE 56
CHECK_HEADER 64

CHECK_HEADERS 64
CHECK_HEADERS_ONCE 65
CHECK_LIB 46
CHECK_MEMBER 67
CHECK_MEMBERS 68
CHECK_PROG 44
CHECK_PROGS 44
CHECK_SIZEOF 71
CHECK_TARGET_TOOL 44
CHECK_TARGET_TOOLS 44
CHECK_TOOL 44
CHECK_TOOLS 45
CHECK_TYPE 70, 210
CHECK_TYPES 70
CHECKING 210
COMPILE_CHECK 210
COMPILE_IFELSE 93
CONFIG_AUX_DIR 18
CONFIG_COMMANDS 35
CONFIG_COMMANDS_POST 36
CONFIG_COMMANDS_PRE 35
CONFIG_FILES 22
CONFIG_HEADERS 32
CONFIG_LIBOBJ_DIR 57
CONFIG_LINKS 36
CONFIG_MACRO_DIR 19
CONFIG_SRCDIR 18
CONFIG_SUBDIRS 36
CONFIG_TESTDIR 235
CONST 210
COPYRIGHT 18
CROSS_CHECK 211
CYGWIN 211

D

DATAROOTDIR_CHECKED 29
DECL_SYS_SIGLIST 211
DECL_YYTEXT 211
DEFINE 99
DEFINE_UNQUOTED 100
DEFUN 125
DEFUN_ONCE 129
DIAGNOSE 126
DIR_HEADER 211
DYNIX_SEQ 211

E

EGREP_CPP 93
EGREP_HEADER 93
EMXOS2 212
ENABLE 196
ERLANG_CHECK_LIB 85
ERLANG_NEED_ERL 78
ERLANG_NEED_ERLC 78
ERLANG_PATH_ERL 78
ERLANG_PATH_ERLC 77
ERLANG_SUBST_INSTALL_LIB_DIR 28, 85
ERLANG_SUBST_INSTALL_LIB_SUBDIR 28, 85
ERLANG_SUBST_LIB_DIR 84
ERLANG_SUBST_ROOT_DIR 84
ERROR 212
EXEEXT 211

F

F77_DUMMY_MAIN 80
F77_FUNC 81
F77_LIBRARY_LDFLAGS 79
F77_MAIN 80
F77_WRAPPERS 80
FATAL 127
FC_FREEFORM 82
FC_FUNC 81
FC_LIBRARY_LDFLAGS 79
FC_MAIN 80
FC_SRCEXT 82
FC_WRAPPERS 80
FIND_X 212
FIND_XTRA 212
FOREACH 212
FUNC_ALLOCA 50
FUNC_CHECK 212
FUNC_CHOWN 50
FUNC_CLOSEDIR_VOID 50
FUNC_ERROR_AT_LINE 51
FUNC_FNMATCH 51
FUNC_FNMATCH_GNU 51
FUNC_FORK 51
FUNC_FSEEKO 51
FUNC_GETGROUPS 51
FUNC_GETLOADAVG 52
FUNC_GETMNTENT 52
FUNC_GETPGRP 52
FUNC_LSTAT 54
FUNC_LSTAT_FOLLOWS_SLASHED_SYMLINK 52
FUNC_MALLOC 53
FUNC_MBRTOWC 53
FUNC_MEMCMP 53
FUNC_MKTIME 53
FUNC_MMAP 53
FUNC_OBSTACK 54
FUNC_REALLOC 54
FUNC_SELECT_ARGTYPES 54
FUNC_SETPGRP 54
FUNC_SETVBUF_REVERSED 54
FUNC_STAT 54
FUNC_STRCOLL 54
FUNC_STRERROR_R 55
FUNC_STRFTIME 55
FUNC_STRNLEN 55
FUNC_STRTOD 55
FUNC_STRTOLD 55
FUNC_UTIME_NULL 55
FUNC_VPRINTF 55

FUNC_WAIT3 ... 212

G

GCC_TRADITIONAL ... 212
GETGROUPS_T ... 212
GETLOADAVG ... 212
GNU_SOURCE ... 84

H

HAVE_C_BACKSLASH_A ... 74
HAVE_FUNCS ... 212
HAVE_HEADERS ... 212
HAVE_LIBRARY ... 212
HAVE_POUNDBANG ... 212
HEADER_ASSERT ... 59
HEADER_CHECK ... 212
HEADER_DIRENT ... 59
HEADER_EGREP ... 213
HEADER_MAJOR ... 60
HEADER_RESOLV ... 60
HEADER_STAT ... 61
HEADER_STDBOOL ... 61
HEADER_STDC ... 61
HEADER_SYS_WAIT ... 62
HEADER_TIME ... 63
HEADER_TIOCGWINSZ ... 64
HELP_STRING ... 197, 213

I

INCLUDES_DEFAULT ... 40
INIT ... 17, 213
INLINE ... 213
INT_16_BITS ... 213
IRIX_SUN ... 213
ISC_POSIX ... 84

L

LANG_ASSERT ... 88
LANG_C ... 213
LANG_CALL ... 92
LANG_CONFTEST ... 90
LANG_CPLUSPLUS ... 213
LANG_FORTRAN77 ... 213
LANG_FUNC_LINK_TRY ... 92
LANG_POP ... 88
LANG_PROGRAM ... 90
LANG_PUSH ... 88
LANG_RESTORE ... 213
LANG_SAVE ... 213
LANG_SOURCE ... 90
LANG_WERROR ... 72
LIBOBJ ... 56
LIBSOURCE ... 56
LIBSOURCES ... 57
LINK_FILES ... 213
LINK_IFELSE ... 94
LN_S ... 214
LONG_64_BITS ... 214
LONG_DOUBLE ... 214
LONG_FILE_NAMES ... 214

M

MAJOR_HEADER ... 214
MEMORY_H ... 214
MINGW32 ... 214
MINIX ... 84
MINUS_C_MINUS_O ... 214
MMAP ... 214
MODE_T ... 214
MSG_CHECKING ... 106
MSG_ERROR ... 106
MSG_FAILURE ... 106
MSG_NOTICE ... 106
MSG_RESULT ... 106
MSG_WARN ... 106

O

OBJEXT ... 214
OBSOLETE ... 214
OFF_T ... 215
OUTPUT ... 19, 215
OUTPUT_COMMANDS ... 215

P

PACKAGE_BUGREPORT ... 17
PACKAGE_NAME ... 17
PACKAGE_STRING ... 17
PACKAGE_TARNAME ... 17
PACKAGE_VERSION ... 17
PATH_PROG ... 45
PATH_PROGS ... 45
PATH_TARGET_TOOL ... 45
PATH_TOOL ... 45
PATH_X ... 83
PATH_XTRA ... 83
PID_T ... 215
PREFIX ... 215
PREFIX_DEFAULT ... 37
PREFIX_PROGRAM ... 37
PREPROC_IFELSE ... 92
PREREQ ... 18
PRESERVE_HELP_ORDER ... 193
PROG_AWK ... 41
PROG_CC ... 73
PROG_CC_C_O ... 73
PROG_CC_C89 ... 74
PROG_CC_C99 ... 74
PROG_CC_STDC ... 74
PROG_CPP ... 73

PROG_CPP_WERROR ... 73
PROG_CXX ... 76
PROG_CXX_C_O ... 77
PROG_CXXCPP ... 77
PROG_EGREP ... 41
PROG_F77 ... 78
PROG_F77_C_O ... 79
PROG_FC ... 78
PROG_FC_C_O ... 79
PROG_FGREP ... 41
PROG_GCC_TRADITIONAL ... 76
PROG_GREP ... 41
PROG_INSTALL ... 41
PROG_LEX ... 42
PROG_LN_S ... 43
PROG_MAKE_SET ... 20
PROG_OBJC ... 77
PROG_OBJCCPP ... 77
PROG_RANLIB ... 43
PROG_SED ... 43
PROG_YACC ... 43
PROGRAM_CHECK ... 216
PROGRAM_EGREP ... 216
PROGRAM_PATH ... 216
PROGRAMS_CHECK ... 215
PROGRAMS_PATH ... 216

R

REMOTE_TAPE ... 216
REPLACE_FNMATCH ... 55
REPLACE_FUNCS ... 57
REQUIRE ... 127
REQUIRE_AUX_FILE ... 19
REQUIRE_CPP ... 88
RESTARTABLE_SYSCALLS ... 216
RETSIGTYPE ... 216
REVISION ... 18
RSH ... 216
RUN_IFELSE ... 94

S

SCO_INTL ... 216
SEARCH_LIBS ... 46
SET_MAKE ... 216
SETVBUF_REVERSED ... 216
SIZE_T ... 216
SIZEOF_TYPE ... 216
ST_BLKSIZE ... 216
ST_BLOCKS ... 217
ST_RDEV ... 217
STAT_MACROS_BROKEN ... 216
STDC_HEADERS ... 216
STRCOLL ... 216
STRUCT_DIRENT_D_INO ... 66
STRUCT_DIRENT_D_TYPE ... 67
STRUCT_ST_BLKSIZE ... 67
STRUCT_ST_BLOCKS ... 67
STRUCT_ST_RDEV ... 67
STRUCT_TIMEZONE ... 67
STRUCT_TM ... 67
SUBST ... 100
SUBST_FILE ... 101
SYS_INTERPRETER ... 83
SYS_LARGEFILE ... 83
SYS_LONG_FILE_NAMES ... 83
SYS_POSIX_TERMIOS ... 84
SYS_RESTARTABLE_SYSCALLS ... 217
SYS_SIGLIST_DECLARED ... 217

T

TEST_CPP ... 217
TEST_PROGRAM ... 217
TIME_WITH_SYS_TIME ... 217
TIMEZONE ... 217
TRY_COMPILE ... 217
TRY_CPP ... 218
TRY_LINK ... 218
TRY_LINK_FUNC ... 218
TRY_RUN ... 218
TYPE_GETGROUPS ... 68
TYPE_INT16_T ... 68
TYPE_INT32_T ... 68
TYPE_INT64_T ... 68
TYPE_INT8_T ... 68
TYPE_INTMAX_T ... 68
TYPE_INTPTR_T ... 68
TYPE_LONG_DOUBLE ... 69
TYPE_LONG_DOUBLE_WIDER ... 69
TYPE_LONG_LONG_INT ... 69
TYPE_MBSTATE_T ... 69
TYPE_MODE_T ... 69
TYPE_OFF_T ... 69
TYPE_PID_T ... 69
TYPE_SIGNAL ... 69
TYPE_SIZE_T ... 69
TYPE_SSIZE_T ... 69
TYPE_UID_T ... 69
TYPE_UINT16_T ... 69
TYPE_UINT32_T ... 70
TYPE_UINT64_T ... 70
TYPE_UINT8_T ... 69
TYPE_UINTMAX_T ... 70
TYPE_UINTPTR_T ... 70
TYPE_UNSIGNED_LONG_LONG_INT ... 70

U

UID_T ... 219
UNISTD_H ... 219
USE_SYSTEM_EXTENSIONS ... 84
USG ... 219
UTIME_NULL ... 219

V

VALIDATE_CACHED_SYSTEM_TUPLE 219
VERBOSE 219
VFORK 219
VPRINTF 219

W

WAIT3 219
WARN 219
WARNING 127
WITH 195
WORDS_BIGENDIAN 219

X

XENIX_DIR 219

Y

YYTEXT_POINTER 219

B.5 M4 Macro Index

This is an alphabetical list of the M4, M4sugar, and M4sh macros. To make the list easier to use, the macros are listed without their preceding '`m4_`' or '`AS_`'.

A

`append` ... 120
`append_uniq` ... 120

B

`BOURNE_COMPATIBLE` ... 121
`bpatsubst` ... 118
`bregexp` ... 118
`builtin` ... 118

C

`CASE` ... 121

D

`decr` ... 118
`define` ... 118
`defn` ... 118
`DIRNAME` ... 121
`dnl` ... 118
`dquote` ... 119
`dumpdef` ... 118

E

`errprint` ... 118
`esyscmd` ... 118
`eval` ... 118
`exit` ... 118

F

`for` ... 119
`foreach` ... 119
`foreach_w` ... 119
`format` ... 118

I

`if` ... 118
`IF` ... 121
`ifdef` ... 118
`include` ... 118
`incr` ... 118
`index` ... 118
`indir` ... 118

L

`len` ... 118

M

`maketemp` ... 118
`MESSAGE_FD` ... 123
`MESSAGE_LOG_FD` ... 123
`MKDIR_P` ... 122

N

`normalize` ... 120

O

`ORIGINAL_STDIN_FD` ... 123

P

`pattern_allow` ... 121
`pattern_forbid` ... 120
`popdef` ... 118
`pushdef` ... 118

Q

`quote` ... 119

R

`re_escape` ... 120

S

`SET_CATFILE` ... 122
`SHELL_SANITIZE` ... 122
`shift` ... 118
`sinclude` ... 118
`split` ... 120
`substr` ... 118
`syscmd` ... 118
`sysval` ... 118

T

`tolower` ... 120
`toupper` ... 120
`TR_CPP` ... 122
`TR_SH` ... 122
`translit` ... 118

U

`undefine` ... 118, 119

W

`wrap` ... 118

B.6 Autotest Macro Index

This is an alphabetical list of the Autotest macros. To make the list easier to use, the macros are listed without their preceding '`AT_`'.

C

`CAPTURE_FILE` ... 232
`CHECK` ... 233
`CLEANUP` ... 233
`COPYRIGHT` ... 232

D

`DATA` ... 233

I

`INIT` ... 232

K

`KEYWORDS` ... 232

S

`SETUP` ... 232

T

`TESTED` ... 232

X

`XFAIL_IF` ... 232

B.7 Program and Function Index

This is an alphabetical list of the programs and functions which portability is discussed in this document.

!

`!` ... 150

.

`.` ... 150

/

`/usr/bin/ksh` on Solaris ... 134
`/usr/dt/bin/dtksh` on Solaris ... 134
`/usr/xpg4/bin/sh` on Solaris ... 134

A

`alloca` ... 50
'`alloca.h`' ... 50
'`assert.h`' ... 59
Awk ... 158

B

`basename` ... 159
`break` ... 150

C

`case` ... 150
`cat` ... 160
`cc` ... 160
`cd` ... 151
`chmod` ... 160
`chown` ... 50
`closedir` ... 50
`cmp` ... 160
`cp` ... 160
'`ctype.h`' ... 61

D

`date` ... 161
`diff` ... 161
'`dirent.h`' ... 59
`dirname` ... 161

E

`echo` ... 151
`egrep` ... 161
`error_at_line` ... 51
`eval` ... 152
`exit` ... 47
`exit` ... 152
`export` ... 153
`expr` ... 162
`expr` ('`|`') ... 162

F

`false` ... 153

fgrep 163
find 163
'float.h' 61
fnmatch 51, 55
'fnmatch.h' 55
for 153
fork 51
free 47
fseeko 51

G

getgroups 51
getloadavg 52
getmntent 52
getpgid 52
getpgrp 52
grep 164

I

if 154
'inttypes.h' 58, 68
isinf 47
isnan 47

J

join 164

K

'ksh' 134
'ksh88' 134
'ksh93' 134

L

'linux/irda.h' 58
'linux/random.h' 58
ln 165
ls 165
lstat 52, 54

M

make 171
malloc 48, 53
mbrtowc 53
memcmp 53
mkdir 165
mktemp 165
mktime 53
mmap 53
mv 166

N

'ndir.h' 59
'net/if.h' 58
'netinet/if_ether.h' 58
'nlist.h' 52

O

od 166

P

'pdksh' 134
printf 154
putenv 48
pwd 154

R

read 154
realloc 48, 54
'resolv.h' 60

S

sed 166
sed ('t') 168
select 54
set 155
setpgrp 54
setvbuf 54
shift 156
signal 48
'signal.h' 69
snprintf 48
source 156
sprintf 48
sscanf 48
stat 54
'stdarg.h' 61
'stdbool.h' 61
'stdint.h' 58, 68
'stdlib.h' 59, 61, 68
strcoll 54
strerror_r 49, 55
strftime 55
'string.h' 61, 62
'strings.h' 62
strnlen 49, 55
strtod 55
strtold 55
'sys/dir.h' 59
'sys/ioctl.h' 64
'sys/mkdev.h' 60
'sys/mount.h' 59
'sys/ndir.h' 59
'sys/ptem.h' 59
'sys/socket.h' 59

‘sys/stat.h’ 61
‘sys/sysmacros.h’ 60
‘sys/time.h’ 63, 67
‘sys/types.h’ 68
‘sys/ucred.h’ 59
‘sys/wait.h’ 62
sysconf 49
‘system.h’ 61

T

‘termios.h’ 64
test 156
‘time.h’ 63, 67
touch 169
trap 157
true 158

U

‘unistd.h’ 63
unlink 49
unset 158
unsetenv 49
utime 55

V

va_copy 49
va_list 49
vfork 51
‘vfork.h’ 51
vprintf 55
vsnprintf 48
vsprintf 48

W

‘wchar.h’ 69

X

‘X11/extensions/scrnsaver.h’ 59

B.8 Concept Index

This is an alphabetical list of the files, tools, and concepts introduced in this document.

"

‘"$@"’ 140

$

$(*commands*) 143
$<, explicit rules, and VPATH 176
${*var*=*expanded-value*} 142
${*var*=*literal*} 141

@

‘@&t@’ 111
‘@S|@’ 111

^

^ quoting 143

_

_m4_divert_diversion 223

`

‘*commands*‘ 142

A

‘acconfig.h’ 208
‘aclocal.m4’ 7
Ash 133
autoconf 12
Autoconf upgrading 220, 222
autoheader 33
Autoheader macros 34
Autom4te Library 116
‘autom4te.cache’ 115
‘autom4te.cfg’ 117
Automake 3
Automatic remaking 30
automatic rule rewriting and VPATH 176
autopoint 15
autoreconf 15
autoscan 11
Autotest 229
AUTOTEST_PATH 233
autoupdate 208

B

Back trace 13, 114
Bash 134
Bash 2.05 and later 134
Bootstrap 237
BSD make and ‘obj/’ 175
buffer overruns 186

Build directories ... 29

C

C function portability ... 47
C types ... 68
Cache ... 102
Cache variable ... 104
Cache, enabling ... 204
Canonical system type ... 190
`changequote` ... 110
Coding style ... 130
Command Substitution ... 142
Commands for configuration ... 35
Comments in '`Makefile`' rules ... 174
Common autoconf behavior ... 39
Compilers ... 70
'`config.h`' ... 31
'`config.h.bot`' ... 208
'`config.h.in`' ... 32
'`config.h.top`' ... 208
`config.status` ... 205
`config.sub` ... 190
Configuration actions ... 20
Configuration commands ... 35
Configuration file creation ... 22
Configuration Header ... 31
Configuration Header Template ... 32
Configuration links ... 36
`configure` ... 7, 201
Configure subdirectories ... 36
'`configure.ac`' ... 7
'`configure.in`' ... 7
Copyright Notice ... 18, 232
Creating configuration files ... 22
Creating temporary files ... 165
Cross compilation ... 224

D

Darwin ... 96
'`datarootdir`' ... 28
Declaration, checking ... 65
Default includes ... 39
Dependencies between macros ... 127
descriptors ... 122
Descriptors ... 136
Directories, build ... 29
Directories, installation ... 25
`dnl` ... 125, 130
double-colon rules and `VPATH` ... 176

E

Endianness ... 74
Erlang ... 77
Erlang, Library, checking ... 84
exiting portably ... 187
explicit rules, `$<`, and `VPATH` ... 176
External software ... 193

F

F77 ... 78
FDL, GNU Free Documentation License ... 247
file descriptors ... 122
File descriptors ... 136
File system conventions ... 138
File, checking ... 45
floating point ... 187
Forbidden patterns ... 120
Fortran ... 78
Function, checking ... 50

G

Gettext ... 15
GNU build system ... 3
Gnulib ... 3

H

Header portability ... 58
Header templates ... 32
Header, checking ... 57
Help strings ... 197
Here-documents ... 135
History of autoconf ... 243

I

`ifnames` ... 12
Imake ... 238
Includes, default ... 39
input ... 122
Install prefix ... 37
Installation directories ... 25
Instantiation ... 19
Introduction ... 1

K

Korn shell ... 134
Ksh ... 134

L

Language ... 87
Large file support ... 83
LFS ... 83
Library, checking ... 46
Libtool ... 4
License ... 237, 247
Limitations of `make` ... 171
Limitations of shell builtins ... 150
Limitations of usual tools ... 158

Links 36
Links for configuration 36
Listing directories 165
low-level output 122

M

M4 107
M4 quotation 107
M4sugar 118
Macro invocation stack 13, 114
Macros, called once 129
Macros, obsoleting 129
Macros, ordering 128
Macros, prerequisites 127
`make -k` 175
`make` and `MAKEFLAGS` 173
`make` and `SHELL` 174
'`Makefile`' rules and comments 174
Makefile substitutions 22
`MAKEFLAGS` and `make` 173
Making directories 165
Messages, from `autoconf` 126
Messages, from `configure` 105
Moving open files 166

N

Notices in `configure` 18
null pointers 186

O

'`obj/`', subdirectory 175
Obsolete constructs 207
Obsoleting macros 129
obstack 54
One-shot macros 129
Options, package 196
Ordering macros 128
Output variables 23, 100
Output variables, special characters in 102
output, low-level 122
Outputting files 19
overflow, arithmetic 186

P

Package options 196
'`package.m4`' 235
Patterns, forbidden 120
portability 185
Portability of C functions 47
Portability of headers 58
Portable C and C++ programming 185
Portable shell programming 133
positional parameters 141
Posix termios headers 84
Prefix for install 37
Preprocessors 70
prerequisite directories and `VPATH` 179
Prerequisite macros 127
Previous Variable 101
Program names, transforming 198
Programs, checking 41

Q

QNX 4.25 96
quadrigraphs 111
quotation 9, 107

R

Remaking automatically 30
Revision 18
Rule, Single Suffix Inference 182

S

Separated Dependencies 182
`SHELL` and `make` 174
Shell assignments 144
Shell builtins 150
Shell file descriptors 136
Shell here-documents 135
Shell parentheses 144
Shell slashes 145
Shell substitutions 140
Shell variables 145
Shellology 133
Single Suffix Inference Rule 182
Site defaults 199
Site details 197
Special shell variables 145
standard input 122
Standard symbols 39
Structure, checking 66
Subdirectory configure 36
Substitutions in makefiles 22
Symbolic links 165
System type 189, 190
Systemology 96

T

termios Posix headers 84
test group 229
`testsuite` 229, 233
timestamp resolution 160, 169, 182
Transforming program names 198
Tru64 96
Types 68

U

undefined macro 223
Unix version 7 96
Upgrading autoconf 220, 222

V

V7 96
Variable, Precious 101
Version 18
`VPATH` 175
`VPATH` and automatic rule rewriting 176
`VPATH` and double-colon rules 176
`VPATH` and prerequisite directories 179
`VPATH`, explicit rules, and `$<` 176
`VPATH`, resolving target pathnames 179

X

X Window System 83

Z

Zsh 135